DE – 4.5-5; H – 5-6; CL – none; F – conchoidal to uneven; M – thick tabular crystals, granular, massive.
Origin and occurrence: Magmatic, metamorphic and in placers, associated with pyrrhotite, rutile, magnetite and other minerals. Crystals weighing up

Ilmenite, 11 mm x, Binntal, Switzerland

to 30 kg (66 lb) were described from the Faraday mine near Bancroft, Ontario, Canada. Crystals up to 150 mm (6 in) in size occurred near Girardville, Quebec, Canada. Crystals also reached up to 100 mm (4 in) near Miass, Ural mountains, Russia. Crystals up to 120 mm 120 mm ($4^{7}/_{16}$ in), were found in Arendal and Kragero, Norway. Crystal rosettes up to 10 mm ($^{3}/_{8}$ in) in size come from Maderanertal, Switzerland. It is also common in placers (Kamituga, Kivu, Zaire; Sri Lanka; Travancore, India; Madagascar etc.).

Perovskite

$CaTiO_3$

ORTHORHOMBIC ● ● ●

Properties: C – dark brown to black; S – colorless to gray; L – metallic to adamantine; D – opaque; DE – 4.0-4.3; H – 5.5-6; CL – imperfect; F – conchoidal to uneven; M – pseudo-cubic crystals, granular.
Origin and occurrence: Magmatic in basic and ultrabasic rocks, metamorphic, together with magnetite, zircon and other minerals. Fine pseudo-cubic crystals up to 40 mm ($1^{9}/_{16}$ in) in size come from Zlatoust and Akhmatovsk, Ural mountains, Russia. It occurs as crystals up to 80 mm ($3^{1}/_{8}$ in), associated with magnetite crystals in the Gardiner complex, Greenland. Crystals up to 40 mm ($1^{9}/_{16}$ in) were found in Jacupiranga, Sao Paulo, Brazil. Crystals from Val Malenco, Italy, reached up to 20 mm ($^{25}/_{32}$ in). Crystals up to 20 mm ($^{25}/_{32}$ in) were lately found in Afrikanda, Kola Peninsula, Russia.

Loparite-(Ce)

$(Ce,Na,Ca)TiO_3$

ORTHORHOMBIC ●

Properties: C – black, S – dark red-brown, L – metallic; D – opaque; DE – 4.6-4.9; H – 5.5-6; M – pseudo-cubic crystals, granular; R – metamict.
Origin and occurrence: Magmatic in alkaline rocks, with lorenzenite, eudialyte and aegirine. Fine interpenetration twins up to 20 mm ($^{25}/_{32}$ in) in size come from Mount Nyorkpakhk, Kola Peninsula, Russia.

Perovskite, 60 mm, Zlatoust, Russia

Stibiconite, 230 mm, Catorce, Mexico



Stibiconite

$Sb^{3+}Sb^{5+}{}_2O_6(OH)$

CUBIC ● ● ●

Properties: C – white, creamy, light yellow, brown; S – white; L – vitreous, greasy to dull; D – opaque; DE – 4.1-5.8; H – 3-6; M – pseudo-morphs after stibnite crystals, earthy, massive.
Origin and occurrence: Secondary, as a result of the stibnite oxidation, associated with valentinite and other minerals. Fine pseudo-morphs after stibnite crystals up to 30 cm (12 in) long come from Catorce, San Luis Potosí, Mexico. Similar pseudo-morphs were also found in Kostainik, Serbia; in the Ichinokawa mine, Japan and in Pereta, Italy. Pseudo-morphs after stibnite up to 20 cm ($7\,^{7}/_{8}$ in) long occur also in Çukuroren, Turkey.

Bindheimite, 4 mm, Rudabánya, Hungary

Bindheimite

$Pb_2Sb_2O_6(O,OH)$

CUBIC ● ● ●

Properties: C – yellow, brown, gray; S – yellow, L – resinous, dull to earthy; D – translucent to opaque; DE – 4.6-5.6; H – 4-4.5; F – conchoidal to earthy; M – botryoidal, nodular and earthy crusts.
Origin and occurrence: Secondary in the oxidation zone of Pb-Sb deposits. Needles up to 10 mm ($^{3}/_{8}$ in) long come from Rudník, Czech Republic. It is common in Broken Hill, New South Wales, Australia; in Bisbee, Arizona, USA and in Sidi-Amor-ben-Salem, Tunisia. Lamellar pseudo-morphs up to several cm in size are known from Tsumeb, Namibia.

Pyrochlore

$(Na,Ca)_2Nb_2O_6(OH,F)$

CUBIC ● ● ●

Properties: C – yellow-brown, brown, black; S – brown; L – vitreous to greasy; D – translucent to opaque. DE – 4.5; H – 5-5.5; CL – locally good; F – conchoidal to uneven; M – octahedral crystals, granular; R – radioactive (admixtures of U, Th).
Origin and occurrence: Magmatic in alkaline rocks, together with zircon, astrophyllite and other minerals. Fine brown shiny crystals up to 20 mm ($^{25}/_{32}$ in) in size come from the vicinity of Vishnevogorsk, Ural mountains, Russia. Crystals reaching 10 mm ($^{3}/_{8}$ in) occur in the Panda Hill deposit, Tanzania. Crystals are also known from Oka, Quebec, Canada. Single octahedra measuring 5 mm ($^{3}/_{16}$ in) were found in Luesha, Kivu, Zaire. *Application:* Nb,U and Th ore.

Microlite, 7 mm x, Gillette Quarry, U.S.A.



Pyrochlore, 58 mm, Vishnevogorsk, Ural Mts., Russia



Betafite

$(Ca,Na,U)_2(Ti,Nb,Ta)_2O_6(OH)$

CUBIC ● ●

Properties: C – black, brown, yellow-brown; SB red-brown; L – resinous to greasy; D – translucent to opaque; DE – 4.2; H – 3-5.5; CL – none; F – conchoidal to uneven; M – octahedral crystals; R – radioactive, metamict.

Origin and occurrence: Magmatic in granitic pegmatites, rich in U, Th and rare earth elements, associated with beryl, euxenite-(Y) and other minerals. The world's best specimens come from many localities in Madagascar (Betafo, Ambatofotsikely etc.), where crystals up to 6 kg (13 lb 3 oz) were found. Beautiful specimens with crystals up to 100 mm (4 in) in size occur in the Silver Crater mine near Bancroft, Ontario, Canada. It is also known from Evje, Norway.

Betafite, 20 mm, Silver Crater, Canada



Mikrolite

$(Na,Ca)_2Ta_2O_6(O,OH,F)$

CUBIC ● ● ●

Properties: C – brown, yellow, green, reddish; S – white; L – vitreous to greasy, locally adamantine; D – translucent to opaque; DE – 5-6.4; H – 6-6.5; CL – locally good; F – conchoidal to uneven; M – octahedral crystals, granular, massive.

Origin and occurrence: Magmatic, typical for granitic pegmatites, together with manganocolumbite, manganotantalite and other minerals. Octahedra up to 65 mm (2$^{9}/_{16}$ in) in size occur in Ankola, Uganda. Crystals up to 30 mm (1$^{3}/_{16}$ in) in size come from Virgem da Lapa, Minas Gerais, Brazil. Crystals up to 75 mm (3 in) are reported from the Harding pegmatite, New Mexico, USA. It occurs in important accumulations near Wodgina, Western Australia.

Quartz, 60 mm, Herkimer, U.S.A.



Quartz

SiO_2

TRIGONAL ● ● ● ● ●

Varieties: rock crystal, citrine, smoky citrine, morion, amethyst, rose quartz, chrysoprase, jasper, chalcedony, agate, onyx, sardonyx, aventurine, heliotrope, tiger's eye, falcon s eye.

Properties: C – colorless (rock crystal), white, yellow (citrine), brown (smoky citrine), black (morion), purple (amethyst), pink (rose quartz), green (chrysoprase); D – these varieties are mostly transparent, often translucent; C – other varieties are mainly multicolored, separate colors have different hues and the color is commonly caused by microscopic admixtures of other minerals; varieties: red, green, brown, yellow (jasper), banded with different colors (agate); white

Rock crystal, 95 mm, La Gardette, France



and black bands (onyx), white and red-brown bands (sardonyx), green to red-brown with mica or hematite inclusions (aventurine), dark green with red spots (heliotrope), yellow-brown to black-brown, fibrous with silky luster (tiger's eye), blue-gray to yellow-brown, fibrous with silky luster (falcon's eye); S – white; L – vitreous, silky, dull; D – transparent to translucent, opaque; DE – 2.6; H – 7; CL – none; F –

Smoky quartz, 70 mm, Middle Moat Mt., U.S.A.



Citrine, 32 mm, Charcas, Mexico



Smoky quartz, 81 mm, Switzerland



Morion, 100 mm, Agadir, Kazakhstan



Amethyst, 100 mm, Bochovice, Czech Republic



conchoidal; M – long to short prismatic, acicular, dipyramidal to tabular crystals, fibrous, botryoidal and stalactitic aggregates and coatings, concretions, geodes, granular, massive.
Origin and occurrence: Magmatic in different types of rocks, mainly in granites, granitic pegmatites and volcanic rocks; metamorphic in different types of rocks, mainly in quartzites and mica schists; hydrothermal in different types of ore and Alpine-

Rose quartz, 145 mm, Minas Gerais, Brazil



Amethyst, 200 mm, Guerrero, Mexico



type veins; secondary in the oxidation zone of ore deposits; also in different types of sedimentary rocks and in organic remains, also in placers. Probably the most common mineral in the Earth's crust and the most important rock-forming mineral, as well.

Large crystals of rock quartz up to 7 m (23 ft) long come from pegmatites in the Betafo region in Madagascar and from the Alpine-type veins, like Uri, Grimsel and Furka, Switzerland; perfect crystals are known from the cracks in marbles near Carrara, Italy; it also occurs in the quartz veins in Herkimer, New York and Hot Springs, Arkansas, USA. Citrine occurs mainly in granitic pegmatites and large crystals come from Goias, Brazil; from Suky and Netín, Czech Republic; from Murzinka, Ural mountains, Russia. Smoky quartz originates mostly in granitic pegmatites, it also occurs in the

Chalcedony, 68 mm, High Atlas, Morocco



Carnelian, 40 mm, Nova Paka, Czech Republic



Chrysoprase, 60 mm, Szklary, Poland



Alpine-type quartz veins and in cavities of volcanic rocks. Perfect crystals up to several meters long, come from many places, the largest crystal, weighing 77 tons, was found in Kazakhstan; perfect crystals occur in pegmatites in many places in Brazil; also in Korostenskiy massif, Ukraine; in the Pikes Peak batholith, Colorado, USA; in the Alpine-type veins in Maderanertal and in Grimsel, Switzerland. Morion crystals, commonly associated with smoky citrine, were found in quartz veins and in pegmatites.

Its crystals are known from St. Gotthard, Switzerland. Amethyst comes from quartz and ore veins, cavities in volcanic rocks, rare in the Alpine-type veins. Famous localities in volcanic rocks are in the states of Rio Grande do Sul and Minas Gerais, Brazil, doubly terminated crystal, weighing 5.5 tons, come from Diamantina. In Serra do Mar, Rio Grande do Sul, a cavity covered with amethyst

Jasper, 50 mm, Ural Mts., Russia



Jasper, 60 mm, Oregon, U.S.A.

Petrified wood, 70 mm, Podkrkonosi, Czech Republic

crystals measuring 10 x 2 x 1 m (33 x 6 x 3 ft 3in) was found; rich druses occur also in the ore veins in Porcura, Romania and Julimes, Mexico. Rose quartz, forming masses up to several meters in granitic pegmatites in the Rose Quartz pit, Quadeville, Ontario, Canada; in Ambositra, Madagascar; crystals up to 10 mm (3/8 in) long growing on quartz crystals, come from Sapucaia, Minas Gerais, Brazil. Dark green chrysoprase veins up to 50 mm (2 in) thick are known from serpentinites in Szklary,

Iron stained quartz, 95 mm, Horovice, Czech Republic

Agate, 50 mm, Železnice, Czech Republic



Onyx, 65 mm, Brazil



Poland. Jasper is known from volcanic rocks and their contacts with sediments, locally as a result of petrification of organic matter, mainly plants, it is also known from quartz veins. Rich aggregates occur in Idar-Oberstein, Germany; in Podkrkonoši region and in Krušne hory mountains, Czech Republic; in the Petrified Forest National Park, Holbrook, Arizona, USA; in Ural mountains, Russia; in Kabamby, Madagascar. Chalcedony is mostly found in quartz veins and geodes in volcanic rocks, also in sediments.

Rich aggregates come from Idar-Oberstein, Germany; Julimes, Mexico; many localities in Uruguay and Brazil; in Huttenberg, Austria. Agates are known from cavities in volcanic rocks, rare in hydrothermal veins and in sediments. The most important localities are located in the southern part of Brazil in the state of Rio Grande do Sul; in Uruguay; also in Yemen; India; Mongolia; in several

Moss agate, 40 mm, Krdjali, Bulgaria



Agate, 140 mm, Horní Halze, Czech Republic



Agate, 60 mm, Brazil



localities in the USA; in Idar-Oberstein, Germany; in Podkrkonosi, Czech Republic. The most famous localities of onyx and sardonyx are in Brazil and Uruguay.

Rich aggregates of aventurine come from Miass, Ural mountains, Russia; Mariazell, Austria; Belany, India. Heliotrope occurs in Idar-Oberstein, Germany; Kozakov, Czech Republic and in Brazil.

Application: important raw material in glass industry, many colored varieties, like amethyst, smoky citrine, citrine, onyx, sardonyx, and heliotrope are cut as gemstones.

Aventurine, 50 mm, India



Tiger's eye, 50 mm, Griqualand, South Africa



Tridymite, 9 mm, Big Luc Mt., U.S.A.



Tridymite

SiO_2

ORTHORHOMBIC ● ● ●

Properties: C – colorless to white; S – white; L – vitreous; D – transparent; DE – 2.3; H – 6.5-7; CL – none; F – conchoidal; M – pseudo-hexagonal tabular crystals.

Cristobalite, 110 mm, Vechec, Slovakia

Origin and occurrence: Magmatic in cavities of young felsic volcanic rocks in association with cristobalite, chalcedony and other minerals. Pseudo-hexagonal tabular crystals up to 10 mm (3/8 in) in size, come from Vechec, Slovakia. Similar crystals found in Ichigayama, Japan. Crystals up to 10 mm (3/8 in) occur with topaz and other minerals in the Thomas Range, Utah, USA.

Cristobalite

SiO_2

TETRAGONAL ● ● ●

Varieties: lussatite (fibrous)

Properties: C – colorless to white; S – white; L – vitreous; D – translucent; DE – 2.3; H – 6.5; CL – none; M – pseudo-octahedral crystals, spherical and botryoidal aggregates.

Origin and occurrence: Magmatic in cavities of young felsic volcanic rocks, associated with tridymite. Crystals up to 4 mm (5/32 in) are known from Cerro San Cristobal, Hidalgo, Mexico. Crystals up to 2 mm (1/16 in) long occur in Vechec, Slovakia. Gray spherical aggregates come from Coso Hot Springs, California, USA.

Common opal, 60 mm, Křemže, Czech Republic



Opal, 50 mm, Herlany, Slovakia

Opal

$SiO_2 . n H_2O$

AMORPHOUS ● ● ● ● ●

Varieties: hyalite, milky opal, fire opal, precious opal, wooden opal, geysirite.

Properties: C – colorless (hyalite), white (milky opal), red (fire opal), iridescence (precious opal), brown, red-brown, yellow, green, gray, blue; S – white; L – vitreous, dull, earthy, waxy; D – transparent to translucent, opaque; DE – 2.1; H – 5.5-6.5; CL – none; F – conchoidal; M – botryoidal and stalactitic aggregates, coatings, concretions, geodes, massive; LU – white, yellow-green, green.

Origin and occurrence: Hydrothermal in volcanic rocks and tuffs, also in various types of volcanic rocks and tuffites, in different types of sedimentary rocks, in organic remnants and hot springs, rare in

Hyalite, 45 mm, Valec, Czech Republic



Opal, 47 mm, Opal Butte, U.S.A.



Wooden opal, 40 mm, Lubietová, Slovakia

hydrothermal veins; secondary in the weathering zone of different types of rocks. It is often associated with chalcedony. Coatings and stalactitic aggregates of hyalite up to 50 mm (2 in) thick known from Cerritos, Mexico; Valec, Czech Republic; Klamath Falls, Oregon, USA. Milky opal occurs in Dubník, Slovakia; Smrcek, Czech Republic and many other localities. The most famous locality of fire opal is Zimapan, Hidalgo, Mexico. Precious opal comes from many localities in Australia, e.g. Baracoo River, Queensland; Coober Pedy, Southern Australia and White Cliffs, New South Wales, where it forms rich aggregates and veinlets in sandstones; classic locality is Dubnik, Slovakia, where it occurs in

Dendritic opal, 56 mm, Křemže, Czech Republic



Fire opal, 20 mm, Mexico



andesites and was probably mined already by ancient Romans. Beautiful precious opals come also from the Virgin Valley, Nevada, USA. Petrified trees, known as wooden opal, reach lengths of several meters in the Petrified Forest National Park, Holbrook, Arizona, USA; in L'ubietova and Povraznik, Slovakia. White geysirite is known mainly from the hot springs in Iceland; Yellowstone National Park, Wyoming, USA; New Zealand.

Application: colored opal varieties, primarily precious opal and fire opal are cut as gemstones, diatomite in chemical industry.

Precious opal, 55 mm, Opal Butte, U.S.A.



Melanophlogite, 80 mm, Fortullino, Italy



Melanophlogite

SiO_2

CUBIC ●

Properties: C – colorless, white; S – colorless; L – vitreous; D – transparent; DE – 2; H – 6.5; CL – none; M – pseudo-cubic crystals, spherical aggregates.
Origin and occurrence: Hydrothermal, associated with sulfur and other minerals. It was originally described from the sulfur deposit in Racalmuto, Sicily, Italy as crystals up to 4 mm (5/32 in) in size. It is also known from Chvaletice, Czech Republic, where it forms crystals up to 2 mm (1/16 in) in size, in Alpine-type veins.

Rutile

TiO_2

TETRAGONAL ● ● ● ●

Properties: C – red-brown, red, brown, yellowish, black; S – light brown; L – metallic to adamantine; D – transparent to translucent; DE – 4.2; H – 6-6.5; CL – good; F – conchoidal to uneven; M – short prismatic, striated crystals, common twins, acicular crystals, granular, massive.
Origin and occurrence: Magmatic and metamorphic, also in placers, together with monazite-(Ce), topaz, beryl, quartz and other minerals. The largest crystals up to 150 mm (6 in) in size come from the Mount Graves, Georgia, USA. Beautiful epitaxial intergrowths with hematite occur in Cavradischlucht, St. Gotthard, Switzerland and in Ibitiara, Bahia, Brazil. It is common as inclusions in smoky citrine (quartz) crystals from Ibitiara, Bahia and Itabira, Minas Gerais, Brazil. Knee-like crystal twins up to 70 (2¾ in) cm in size were found in the vicinity of Golcuv Jenikov and Sobeslav, Czech Republic.
Application: Ti ore.

Rutile, 21 mm, Ibitiara, Brazil



Rutile, 48 mm, Bahia, Brazil



Cassiterite, 110 mm, Yunnan, China



Cassiterite

SnO_2

TETRAGONAL ● ● ● ●

Properties: C – colorless, brown, black; S – white, grayish, brown; L – metallic to adamantine, dull; D – transparent to opaque; DE – 6.3-7.2; H – 6-7; CL – imperfect; F – conchoidal to uneven; M – dipyramidal and short prismatic crystals, multiple twins, granular, massive.
Origin and occurrence: Magmatic in pegmatites, hydrothermal in high-temperature deposits, metamorphic and in placers, together with wolframite, topaz and other minerals. Crystal twins up to 150 mm (6 in) in size come from Horni Slavkov, Czech Republic. Crystals of similar size were also found in Panasqueira, Portugal. Fine twins up to 80 mm (3⅛ in) were found in Rossarden, Tasmania, Australia. Crystals up to 70 mm (2¾ in) in size were found in Llallagua, colorless and transparent crystals up to 50 mm (2 in) in size in Viloco, Bolivia. Crystals up to 110 mm ($4\frac{5}{16}$ in) occurred lately in Tenkergin, Chukotka, Russia. Crystals up to 130 mm ($5\frac{2}{16}$ in) in size are known from pegmatites in Minas Gerais, Brazil (Fazenda do Funil). New finds of shiny crystals up to 100 mm (4 in) long were made in Hunan and Yunnan provinces, China.
Application: Sn ore.

Plattnerite

PbO_2

TETRAGONAL ● ●

Properties: C – black; S – brown; L – metallic to adamantine; D – opaque; DE – 9.6; H – 5.5; CL – none; M – acicular crystals, botryoidal aggregates, massive.
Origin and occurrence: Secondary, as a result of the oxidation of other Pb minerals, together with pyromorphite, hemimorphite and other minerals. Fine crystals come from Mina Ojuela, Mapimi, Durango, Mexico and from the Blanchard mine, New Mexico, USA. Botryoidal aggregates, weighing up to 100 kg (220 lb), were found in the Morning mine, Mullan, Idaho, USA.

Plattnerite, 150 mm, Mapimi, Mexico



Pyrolusite, 88 mm, Baraga, U.S.A.



Pyrolusite

MnO_2

TETRAGONAL ● ● ● ●

Properties: C – black, steel-gray; S – black; L – metallic to dull; D – opaque; DE – 5.1; H – 6-6.5; CL – perfect; F – uneven; M – prismatic to acicular striated crystals, stalactitic and botryoidal aggregates, granular, massive.

Origin and occurrence: Secondary, as a result of alteration of manganite and other primary Mn minerals, also hydrothermal. Crystals up to 20 mm ($^{25}/_{32}$ in) long come from Horní Blatna, Czech Republic. Radial shiny aggregates were found in Ohrenstock, Germany. It occurred in Ilfeld, Germany, too. Large sedimentary Mn deposits, where pyrolusite is the main constituent, are known near Chiaturi, Georgia or near Nikopol, Ukraine. Crystals are reported also from Tsumeb, Namibia and Hotazel, South Africa.

Application: important Mn ore.

Hollandite

$Ba(Mn^{4+},Mn^{2+})_8O_{16}$

MONOCLINIC ● ● ●

Properties: C – gray-black; S – black; L – submetallic; D – opaque; DE – 5; H – 6; CL – good; M – short prismatic crystals, racemous and columnar aggregates.

Origin and occurrence: Metamorphic in Mn deposits with braunite, scheelite and other minerals, also secondary. Crystals up to 5 mm ($^{3}/_{16}$ in) long come from the Bradshaw mountains, Arizona, USA. It is common in the metamorphosed Mn deposits in Ultevis, Sweden; in Nagpur and Balaghat, India.

Coronadite

$Pb(Mn^{4+},Mn^{2+})_8O_{16}$

TETRAGONAL ● ● ●

Properties: C – black, black-gray; S – brown-black; L – submetallic to dull; D – opaque; DE – 5.4; H – 4.5-5.5; M – botryoidal crusts with fibrous structure, massive.

Origin and occurrence: Secondary in the oxidation zone of Mn deposits. Spherical aggregates up to 100 mm (4 in) in diameter come from the Bou Tazoult mine, Imini, Morocco. Small crystals were found in the Beltana mine, Southern Australia, Australia and in the Silver Bill mine, Arizona, USA.

Todorokite

$(Mn^{2+},Ca,Mg)Mn^{4+}{}_3O_7 . H_2O$

MONOCLINIC ● ● ●

Properties: C – gray, brown-black, black; S – brown;

L – metallic to dull; D – opaque; DE – 3.5-3.8; H – 1; CL – perfect; M – platy crystals, stalactitic and nodular aggregates.
Origin and occurrence: Secondary mineral, as a result of the oxidation of Mn minerals. Crystals are reported from several mines in the Kalahari region, South Africa (Hotazel, Smart). It was originally described from the Todoroki mine, Hokkaido, Japan. It is an important constituent of oceanic Mn concretions.

Ferrotapiolite

$FeTa_2O_6$

TETRAGONAL ● ● ●

Properties: C – black, brown; V – red-brown; L – submetallic, adamantine, resinous; D – opaque; DE – 7-7.8; H – 6-6.5; CL – none; F – uneven to conchoidal; M – dipyramidal and short prismatic crystals, massive.
Origin and occurrence: Magmatic in pegmatites, together with manganotantalite, microlite, cassiterite and other minerals. Crystals up to 40 mm ($1^{9}/_{16}$ in) in size are known from the vicinity of Governador Valadares, Minas Gerais, Brazil. A crystal 120 mm ($4^{7}/_{16}$ in) long has been described from Angarf, Morocco. Short prismatic crystals come from pegmatites near Topsham and Paris, Maine, USA.

Ilmenorutile

(Ti,Nb,Fe)O_2

TETRAGONAL ● ● ●

Properties: C – black; S – brown; L – submetallic; D – opaque; DE – 4.2; H – 6-6.5; CL – good; F – conchoidal to uneven; M – prismatic crystals, granular.
Origin and occurrence: Magmatic in pegmatites, together with schorl, zircon, fluorapatite and other minerals. Prisms several cm long come from Udraz near Pisek, Czech Republic. It is also known from the vicinity of Miass, Ural mountains, Russia and Evje, Norway.

Todorokite, 60 mm, Kamogun, Japan



Ferrotapiolite, 60 mm, Maršíkov, Czech Republic



Ilmenorutile, 10mm x, Pisek, Czech Republic



Anatase

TiO_2

TETRAGONAL ● ● ●

Properties: C – black-gray, brown, red-brown, blue, rare colorless; S – white; L – submetallic to adamantine; D – transparent to opaque; DE – 3.8-4; H – 5.5-6; CL – perfect; F – conchoidal; M – dipyramidal and tabular crystals.
Origin and occurrence: Hydrothermal in the Alpine-type veins, associated with brookite and quartz, also sedimentary and metamorphic. Beautiful crystals up to 50 mm (2 in) long were found in Alpa Lercheltini, Binntal, Switzerland. Famous black-blue crystals reaching up to 30 mm ($1^{3}/_{16}$ in) come from Matskorhae, Hardangervidda, Norway. Crystals up to 15 mm ($1^{9}/_{32}$ in) were recently found in Dodo, Polar Ural, Russia. Crystals up to 30 mm ($1^{3}/_{16}$ in) in size occurred in the Old Lot and Vulcan mines, Colorado, USA.

Tellurite

TeO_2

ORTHORHOMBIC ● ●

Properties: C – yellow, yellow-orange; S – yellowish; L – adamantine; D – transparent; DE – 5.8; H – 2; CL – perfect; M – acicular and thin tabular crystals, radial aggregates, pulverulent.
Origin and occurrence: Secondary, resulting from the oxidation of AuBTe ores. Crystals up to 10 mm ($^{3}/_{8}$ in) long occurred in the Kawazu and Susaki mines, Japan. Beautiful specimens were found in Moctezuma, Sonora, Mexico; it also comes from Cripple Creek, Colorado, USA.

Brookite

TiO_2

ORTHORHOMBIC ● ● ●

Properties: C – light to dark brown, yellow-brown, black; S – white to gray; L – submetallic to adamantine; D – transparent to translucent, opaque; DE – 4.1; H – 5.5-6; CL – imperfect; F – conchoidal to uneven; M – tabular, dipyramidal, long and short prismatic crystals.
Origin and occurrence: Hydrothermal along the fissures of the Alpine-type veins and in granitic and alkaline pegmatites; it occurs as pseudo-morphs after titanite and ilmenite; also in sedimentary rocks. Perfect tabular crystals up to 50 mm (2 in) in size found in Rieder Tobel, Switzerland; Magnet Cove, Arkansas, USA; Passo di Viza, Italy. New finds of crystals up to 50 mm in size made in Dodo, Polar Ural, Russia.

Anatase, 16 mm, Hardangervidda, Norway



Brookite, 50 mm, Puiva, Polar Urals, Russia




Tellurite, 1 mm x, Fata Baii, Romania

Ferberite
$FeWO_4$

MONOCLINIC ● ● ●

Properties: C – black; S – brown-black to black; L – submetallic; D – opaque; DE – 7.5; H – 4-4.5; CL – perfect; F – uneven; M – short prismatic to tabular crystals, granular, massive.
Origin and occurrence: Hydrothermal in high- to medium-temperature ore veins, in greisens and skarns; rare magmatic in granitic pegmatites and granites; it also occurs in placers. It is usually associated with cassiterite, scheelite, sulfides and quartz. Perfect tabular crystals up to 120 mm ($4\frac{7}{16}$ in) in size found in the Quartz Creek mine, Colorado, USA; also in Cínovec, Czech Republic; Panasqueira, Portugal; Ehrenfriedersdorf, Germany and Potosí, Bolivia.
Application: W ore.

Hübnerite
$MnWO_4$

MONOCLINIC ● ● ●

Properties: C – yellow-brown, red-brown, black; S – yellow-brown to black-gray; L – submetallic; D – translucent to opaque; DE – 7.2; H – 4-4.5; CL – perfect; F – uneven; M – short prismatic to tabular crystals, granular, massive.
Origin and occurrence: Hydrothermal in high- to medium-temperature ore veins, in greisens; rarely magmatic in granitic pegmatites; also in placers. Perfect tabular to short prismatic crystals up to 25 cm ($9\frac{11}{16}$ in) in size, come from the Huayllapon mine, Pasto Bueno, Peru; also from Baia Sprie, Romania; Kara-Oba, Kazakhstan; the Sweet Home mine, Alma and Silverton, Colorado, USA.
Application: W ore.


Ferberite, 68 mm, Mundo Nuovo, Peru


Hubnerite, 39 mm, Silverton, U.S.A.

Titanowodginite, 20 mm, Tanco, Canada



Titanowodginite

$MnTiTa_2O_8$

ORTHORHOMBIC ●

Properties: C – dark brown, black; S – dark brown; L – submetallic; D – translucent to opaque; DE – 6.9; H – 5.5; CL – imperfect; F – uneven; M – dipyramidal crystals, granular.
Origin and occurrence: Magmatic in granitic pegmatites. Dipyramidal crystals up to 10 mm ($^3/_8$ in) long occur in the Tanco mine, Bernic Lake, Manitoba, Canada.
Application: Ta ore.

Ferrocolumbite, 90 mm, Middletown, U.S.A.



Ferrocolumbite

$FeNb_2O_6$

ORTHORHOMBIC ● ● ●

Properties: C – black, red-brown; S – red-brown to black; L – submetallic; D – translucent to opaque; DE – 5.2; H – 6; CL – good; F – uneven to conchoidal; M – long to short prismatic and tabular crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites and granites; rare hydrothermal in high-temperature ore veins and in greisens; also in placers. Tabular crystals up to 1 m (39$^3/_8$ in) in size occur in granitic pegmatites near Custer and Keystone, South Dakota, USA; in Malakialina, Madagascar; Ichikawa, Japan; masses, weighing up to 270 kg (594 lb) come from the Meyers quarry, Colorado, USA.
Application: Nb ore.

Manganotantalite

$MnTa_2O_6$

ORTHORHOMBIC ● ● ●

Properties: C – red, red-brown, black-brown, black; S – dark red to black; L – submetallic; D – translucent to opaque; DE – 8.0; H – 6-6.5; CL – good; F – uneven

Manganotantalite, 19 mm, Nuristan, Afghanistan



Euxenite-(Y), 40 mm, Ambatofotsy, Madagascar



to conchoidal; M – prismatic to tabular crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites and granites; also in placers. Crystals up to 100 mm (4 in) in size come from Li-bearing pegmatites in the Tanco Mine, Bernic Lake, Manitoba, Canada; also from Sao Jose da Safira, Minas Gerais, Brazil.
Application: Ta ore.

Euxenite-(Y)

(Y,Ce,U,Th) (Nb,Ta,Ti)$_2$O$_6$

ORTHORHOMBIC ● ●

Properties: C – black with brownish and green hues; S – gray, yellowish, brownish; L – submetallic, resinous; D – translucent to opaque; DE – 4.6; H – 6; CL – none; F – conchoidal; M – tabular crystals, granular, massive; R – locally weakly radioactive, commonly metamict.
Origin and occurrence: Magmatic in granitic and alkaline pegmatites; also in placers. Typically associated with monazite-(Ce), zircon, ilmenite and other oxides of rare earth elements. Crystals up to 150 mm (6 in) in size are known from Kragero and Hitterö, Norway; from Ankazobe, Madagascar.

Aeschynite-(Ce)

(Ce,Ca) (Ti,Nb)$_2$O$_6$

ORTHORHOMBIC ● ●

Properties: C – black, red-brown, yellow; S – red-yellow; L – vitreous, resinous, adamantine; D – translucent to opaque; DE – 5.0; H – 5.5; CL – none; F – conchoidal; M – prismatic and tabular crystals, granular, massive; R – locally weakly radioactive, commonly metamict.
Origin and occurrence: Magmatic in alkaline and granitic pegmatites and carbonatites. It is associated with zircon and oxides of rare earth elements. Crystals up to 190 mm (7$^{8}/_{16}$ in) long occur in Quadeville, Ontario, Canada; other localities are Kragero, Norway; Trout Creek Pass, Colorado, USA.

Aeschynite-(Ce), 45 mm, Hittero, Norway



Stibiotantalite

SbTaO$_4$

ORTHORHOMBIC ● ●

Properties: C – yellow, yellow-brown, red-brown, yellow-green; S – yellow-brown; L – submetallic, vitreous, resinous; D – transparent to translucent; DE – 7.5; H – 5-5.5; CL – good; F – uneven to conchoidal; M – prismatic, tabular and dipyramidal crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites; also in placers. Crystals up to 120 mm (4$^{7}/_{16}$ in) in size occur in Muiane, Alto Ligonha, Mozambique; also found in the Little Three mine, Ramona, and the Himalaya mine, Mesa Grande, California, USA. Also known from Greenbushes, Western Australia, Australia.
Application: Ta ore.

Stibiotantalite, 10 mm grain, Dobrá Voda, Czech Republic



Uraninite

UO_2

CUBIC ● ● ● ●

Properties: C – black, black-brown, black-gray; S – black, black-brown to greenish; L – submetallic, greasy, earthy; D – opaque; DE – 7.5-10,6; H – 5-6. earthy aggregates 3; CL – imperfect; F – uneven to conchoidal; M – cubic crystals, botryoidal aggregates, granular. massive; R – strong radioactive.

Origin and occurrence: Mainly hydrothermal in ore veins, skarns; magmatic in granitic pegmatites; in sedimentary rocks; also in placers. Usually associated with other U minerals, e.g. coffinite and secondary alteration products, mainly U micas. Perfect crystals up to 100 mm (4 in) in size and weighing up to 2.5 kg (5 lb 8 oz) come from the Fissure mine, Wilberforce, Ontario, Canada, where they occur in simple pegmatites, cross-cutting marbles.

Crystals are also known from Dieresis, Spain and Shinkolobwe, Zair. Rich botryoidal aggregates were found in Jachymov and Slavkovice, Czech Republic; in Bois-Noirs and Margnac, France.

Application: U ore.

Uraninite, 8 mm x, Portland, U.S.A.



Gibbsite, 80 mm, Gamba, Brazil



Gibbsite

$Al(OH)_3$

MONOCLINIC ● ● ●

Properties: C – colorless, gray, white, greenish; S – white; L – vitreous, pearly; D – transparent to translucent; DE – 2.4; H – 2.5-3.5; CL – perfect; F – uneven; M – tabular crystals, lamellar and earthy aggregates, coatings and stalactitic films, granular, massive.
Origin and occurrence: Hydrothermal as a product of alteration Al-rich rocks; secondary in the oxidation associated with goethite; metamorphic in weakly metamorphosed Al-rich rocks, typically with diaspore; a constituent of bauxites. Tabular crystals up to 100 mm (4 in) in size were found in Zlatoust, Ural mountains, Russia; also in Villa Rica, Minas Gerais, Brazil.

Brucite

$Mg(OH)_2$

TRIGONAL ● ● ●

Properties: C – colorless, gray, white, bluish, blue, yellow, brown; S – white; L – vitreous, pearly; D – transparent to translucent; DE – 2.4; H – 2.5; CL – perfect; F – uneven; M – tabular crystals, foliated, acicular and earthy aggregates, granular, massive.
Origin and occurrence: Hydrothermal in veins in serpentinites or dolomitic marbles, a product of periclase alteration; rare metamorphic in skarns and marbles. Perfect crystals up to 18 cm in size, come from the Low's mine, Pennsylvania and the Tiliy Foster mine, New York, USA; also known from Asbestos, Quebec, Canada; Predazzo, the Alps, Italy; blue crystals up to 50 mm (2 in) in size were found in the Bazhenovskoye deposit, Azbest, Ural mountains, Russia.

Brucite, 30 mm, Azbest, Russia



Diaspore

$AlO(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, gray, white, greenish, yellowish, pink, purplish; S – white; L – vitreous, pearly; D – transparent to translucent; DE – 3.4; H – 6.5-7; CL – perfect; F – conchoidal; M – tabular crystals, foliated aggregates, stalactitic films, granular, massive.
Origin and occurrence: Hydrothermal as a product of alteration Al-rich minerals, e.g. andalusite, typically with pyrophyllite and corundum; metamorphic in Al-rich rocks; a constituent of bauxites. Tabular crystals up to 120 mm ($4\frac{7}{16}$ in) in size come from Menderess, Turkey; also from Naxos, Greece; Chester, Massachusetts, USA.

Diaspore, 35 mm, Milas, Turkey



Goethite, 77 mm, Santa Eulalia, Mexico



Goethite, 60 mm, Pribram, Czech Republic



Goethite

$Fe^{3+}O(OH)$

ORTHORHOMBIC ● ● ● ● ●

Varieties: velvet ore

Properties: C – black-brown, yellow-brown, brown; S – yellow-brown; L – submetallic, metallic, silky, earthy; D – translucent to opaque; DE – 4.3; H – 5-5.5; CL – perfect; F – uneven to conchoidal; M – acicular to prismatic crystals, botryoidal aggregates, commonly with radial structure, coatings and stalactitic films, earthy, granular, massive.

Lepidocrocite, 30 mm, Rudabanya, Hungary



Origin and occurrence: Secondary as one of the most common minerals of the oxidation zone of ore deposits, it forms a significant part of limonite; hydrothermal in ore veins, in cavities in pegmatites and volcanic rocks. It forms pseudo-morphs after pyrite and other Fe sulfides. Rich botryoidal aggregates of velvet ore with a velvety surface come from Príbram, Czech Republic; acicular crystals up to 50 mm (2 in) long are known from Bottalack and Redruth, Cornwall, UK; it also occurs in Siegen and Horhausen, Germany; in Florissant, Colorado, USA.
Application: Fe ore.

Manganite

$Mn^{3+}O(OH)$

MONOCLINIC ● ● ● ●

Properties: C – black to black-gray; S – red-brown to black; L – submetallic to dull; D – opaque; DE – 4.3; H – 4; CL – perfect; F – uneven to conchoidal; M – long to short prismatic crystals, acicular and earthy aggregates, concretions, granular, massive.
Origin and occurrence: Hydrothermal in low-temperature ore veins, together with quartz; secondary in the oxidation zone of ore deposits; sedimentary and rare metamorphic in Mn-rich rocks. Druses of black crystals up to 40 mm (1⁹/₁₆ in) long come from the classic locality Ilfeld, Germany; it also occurs in Ohrenstock and Ilmenau, Germany; in Nikopol, Ukraine; in Sterling Hill, New Jersey, USA; in the N'Chwaning No. 2 mine, Kuruman, South Africa.
Application: Mn ore.

Lepidocrocite

$Fe^{3+}O(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – dark red to red-brown; S – orange to brick-red; L – submetallic, adamantine to silky; D – transparent to opaque; DE – 4.0; H – 5; CL – perfect; F – uneven to conchoidal; M – tabular to short prismatic crystals, acicular, bladed and earthy aggregates, concretions, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of ore deposits, overgrown on botryoidal goethite. It occurs together with goethite as a constituent of limonite, its tabular crystals and their aggregates are known from Herdorf, Germany and Rancie, France.

Manganite, 85 mm, Ilfeld, Germany

Lithiophorite

$(Al,Li)Mn^{4+}O_2(OH)_2$

MONOCLINIC ● ● ●

Properties: C – black, commonly with bluish tint; S – black-gray to black; L – metallic to dull; D – opaque; DE – 3.3; H – 3; CL – perfect; F – uneven; M – scaly crystals, botryoidal and earthy aggregates, coatings, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of ore deposits and along the cracks in sedimentary rocks. Botryoidal aggregates occur in Schneeberg, Germany; Jivina and Zajecov, Czech Republic; Miyazaki, Japan.

Lithiphorite, 60 mm, Rangersdorf, Germany

Curite

$Pb_2U_5O_{17} \cdot 4\,H_2O$

ORTHORHOMBIC ● ●

Properties: C – dark orange to red-orange; S – light orange; L – adamantine to earthy; D – transparent to translucent; DE – 7.4; H – 4-5; CL – good; F – uneven; M – acicular crystals, earthy aggregates, coatings, massive; R – strong radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits, associated with other secondary U minerals, e.g. torbernite, kasolite and uranophane. Rich aggregates were found in Shinkolobwe, Zaire; also known from La Crouzille, France; South Alligator, Northern Territory, Australia.

Curite, 30 mm, Shinkolobwe, Zair



5. Carbonates

Magnesite

$MgCO_3$

TRIGONAL ● ● ● ●

Properties: C – colorless, white, yellowish, brownish, black; S – white; L – vitreous to dull; D – transparent; DE – 3.1; H – 4; CL – perfect; F – conchoidal; M – rhombohedral and prismatic crystals, massive cleavable aggregates, earthy; LU – occasionally blue or green.
Origin and occurrence: Rarely magmatic, mainly hydrothermal metasomatic and metamorphic. The largest crystals are known from Brumado, Bahia, Brazil, reaching up to 1 m ($39\frac{3}{8}$ in) in size, embedded in metamorphosed dolomites. Crystals in cavities in the same locality are up to 50 mm (2 in) in size. Also crystals up to 50 mm (2 in) found in the Eugui quarries, Spain. Crystals up to 10 mm ($\frac{3}{8}$ in) across come also from Val Malenco, Italy. It prevails as massive aggregates, forming huge deposits, like Veitsch, Austria; Liao-Tung, China. Many deposits are located in Slovakia (Jelsavska Dubrava, Hnusta).
Application: heat-resistant material.

← +

Calcite, 40 mm, Houghton Co., U.S.A.
Magnesite, 148 mm, Brumado, Brazil

Smithsonite, 32 mm, Tsumeb, Namibia

←

Smithsonite

$ZnCO_3$

TRIGONAL ● ● ●

Properties: C – white, gray, green, pink, blue; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 4.4; H – 4-5; CL – perfect; F – conchoidal to uneven; M – rhombohedral crystals, botryoidal and stalactitic aggregates, massive; LU – sometimes green or blue.
Origin and occurrence: Supergene, as a result of oxidation of the primary Zn ores, associated with other supergene Pb minerals. The largest yellow scalenohedra crystals up to 40 mm ($1\frac{9}{16}$ in) in size come from Broken Hill, New South Wales, Australia. Pink crystals, up to 30 mm ($1\frac{3}{16}$ in) long occurred in Tsumeb, Namibia. World famous blue-green botryoidal crusts up to 100 mm (4 in) thick found in the Kelly Mine, Magdalena, New Mexico, USA. Nice aggregates and banded stalactites described from Monte Poni, Sardinia, Italy.

Smithsonite, 40 mm, New Mexico, U.S.A.

Siderite, 26 mm, Governador Valadares, Brazil



Siderite

$FeCO_3$

TRIGONAL ● ● ● ●

Properties: C – yellow, brown, black; S – yellowish-white; L – vitreous; D – translucent; DE – 4; H-4; CL – perfect; F – uneven to conchoidal; M – rhombohedral crystals, granular, massive.

Origin and occurrence: Hydrothermal in medium- and low-temperature deposits, sedimentary. Crystals up to 40 cm long found in Mont St.-Hilaire, Quebec, Canada. Crystals up to 100 mm (4 in) in size come from Panasqueira, Portugal. Crystals up to 30 mm ($1\frac{3}{16}$ in) in size occurred in Neudorf, Germany. Rhombs up to 20 mm ($\frac{25}{32}$ in) also found in Pribram, Czech Republic. Pseudo-morphs of goethite after siderite up to 70 mm (2¾ in) across described from Pikes Peak, Colorado, USA. Deposits of massive siderite in Erzberg and Hüttenberg, Austria yielded crystals up to 50 mm (2 in) long. Fine crystals reported from Tavistock, Devon and Redruth, Cornwall, UK.

Application: important Fe ore.

Sfaerocobaltite

$CoCO_3$

TRIGONAL ● ● ●

Properties: C – pink, gray, brown; S – red; L – vitreous; D – transparent to translucent; DE – 4.1; H – 4; CL – perfect; M – scalenohedral and rhombohedral crystals, radial aggregates, massive.

Origin and occurrence: Secondary, as a product of the oxidation of primary Co minerals. The best specimens, with crystals up to 30 mm ($1\frac{3}{16}$ in) long, come from Zaire (Musonoi; Kakanda). Crystals up to 10 mm (4 in) long known from Bou Azzer, Morocco.

Sphaerocobaltite, 16 mm, Bou Azzer, Morocco



Rhodochrosite, 117 mm, Sweet Home Mine, U.S.A.



Rhodochrosite

$MnCO_3$

TRIGONAL ● ● ● ●

Properties: C – white, pink, red, brown, locally black coatings on crystals; S – white; L – vitreous; D – transparent to translucent; DE – 3.6; H – 3.5-4; CL – perfect; F – conchoidal to uneven; M – rhombohedral and scalenohedral crystals, hemispherical and botryoidal aggregates, granular, massive.
Origin and occurrence: Only rare in pegmatites, hydrothermal in medium- and low-temperature veins, sedimentary and metamorphic. The most beautiful crystals come from the Sweet Home mine, Alma, Colorado, USA, where rhombs up to 150 mm (6 in) in size occur, associated with purple fluorite, hubnerite, tetrahedrite and other minerals. Beautiful dark red scalehohedra, up to 100 mm (4 in) found in the N'Chwaning No.1 and 2 mines, Kuruman, South Africa. Pink rhombs up to 80 mm (3⅛ in) come from Silverton, Colorado, USA. Nice pink hemispheres and botryoidal aggregates are known from Cavnic and Baia Sprie, Romania. Similar specimens occurred in Huaron, Peru. Pink banded crusts and stalactites were found in the Mina Capillitas, Catamarca, Argentina. Pink rhombs, associated with bertrandite, were lately found in Kounrad, Kazakhstan.

Rhodochrosite, 70 mm, Mina Capillitas, Argentina



Calcite, 150 mm, Elmwood Mine, U.S.A.



Calcite

$CaCO_3$

TRIGONAL ● ● ● ● ●

Properties: C – colorless, white, gray, yellow, brown, pink, red, blue, green, black; S – white; L – vitreous to pearly; D – transparent to opaque; DE – 2.7; H – 3; CL – perfect; F – conchoidal; M – crystals of various habit, concretions, stalactites, oolitic aggregates, granular, massive; LU – sometimes red to orange.

Calcite, 30 mm, Tunguzka, Russia



Origin and occurrence: One of the most common minerals, resulting from a wide range of conditions, it is magmatic, hydrothermal, sedimentary, metamorphic and secondary, it occurs in various parageneses. Large crystals found in many localities throughout the world. Pinkish and yellow crystals over 500 mm (20 in) long come from Joplin, Missouri and from the Elmwood mine, Tennessee, USA. Beautiful calcite crystals, crystallographically of very complex habits, found in Dalnegorsk, Russia. Nice calcite specimens occurred also in Mexico (Naica, Chihuahua; Charcas, San Luis Potosí). European localities, like Príbram, Czech Republic; St. Andreasberg, Germany; Kongsberg, Norway are famous by their calcites, too. Wine yellow, complicated crystals are known from the Sarbayskoye deposit in Rudnyi, Kazakhstan. Clear cleavable aggregates of the birefringent calcite (so called Iceland spar) were found in basalt cavities in Helgustadir, Iceland. The largest of them reached up to 6 x 2 m (20 x 6 ft 6 in) in size. Very nice scalenohedra up to 80 mm (3⅛ in) long with copper inclusions occur in Keweenaw Peninsula, Michigan, USA. Perfect scalenohedra and their twins up to 100 mm (4 in) long are known from Egremont and Frizington, UK. Beautiful butterfly twins up to 80 mm (3⅛ in) recently reported from Guiyang, Hunan, China. Crystals of calcite with sand inclusions up to 100 mm (4 in) in size come from the vicinity of Fontainebleau, France.

Application: building industry, optical industry.

Dolomite, 33 mm x, Navarro, Spain



Dolomite

$CaMg(CO_3)_2$

TRIGONAL ● ● ● ● ●

Properties: C – gray-white, pink, red, green, brown, black; S – white; L – vitreous to pearly; D – transparent to translucent, DE – 2.9; H – 3.5; CL – perfect; F – conchoidal; M – rhombohedral crystals, massive.

Origin and occurrence: Magmatic in pegmatites, hydrothermal, metasomatic, sedimentary and metamorphic, together with siderite, magnesite, calcite and other minerals. Crystals up to 100 mm (4 in) long found in Brumado, Bahia, Brazil. Fine crystals also occurred in Banska Stiavnica, Slovakia and in Cavnic, Romania. Crystals up to 200 mm ($7\,{}^{7}/_{8}$ in) in size come from Eugui, Spain. Crystals up to 150 mm (6 in) long found in cavities in dolomitic rocks in Lengenbach, Binntal, Switzerland. Crystals several cm long known from Jachymov, Czech Republic. Large accumulations of massive dolomite are common in magnesite deposits.

Application: metallurgy, heat-resistant material.

Ankerite, 20 mm xx, Roudny, Czech Republic



Ankerite

$CaFe(CO_3)_2$

TRIGONAL ● ● ● ●

Properties: C – white, yellowish, brown-yellow; S – white; L – vitreous to pearly; D – translucent; DE – 3; H – 3.5-4; CL – perfect; F – conchoidal; M – rhombohedral crystals, granular.

Origin and occurrence: Hydrothermal in medium- and low-temperature veins, also sedimentary and metamorphic, together with siderite and other minerals. Crystals up to 50 mm (2 in) occurred in the Tui mine, New Zealand. Brown rhombs up to 40 mm ($1\,{}^{9}/_{16}$ in) in size known from Gilman, Colorado, USA. Yellowish crystals up to 10 mm (${}^{3}/_{8}$ in) come from concretions near Kladno, Czech Republic. Massive aggregates are common in metasomatic deposits of siderite (e.g. Nizna Slana, Slovakia).

Kutnohorite, 60 mm, Kutna Hora, Czech Republic



Huntite, 110 mm, Koksin, Czech Republic



Kutnohorite

$CaMn(CO_3)_2$

TRIGONAL ● ● ●

Properties: C – white, gray, pink, yellowish; S – white; L – vitreous; D – translucent; DE – 3.1; H – 3.5-4; CL – perfect; F – conchoidal; M – poorly developed crystals, granular, massive.
Origin and occurrence: Hydrothermal and metamorphic, associated with ankerite, quartz and other minerals. Poorly developed crystals are known from Kutna Hora, Czech Republic. Small crystals several mm in size are described from Mont St.-Hilaire, Quebec, Canada. Large crystals occurred in Moncure, North Carolina, USA. Small gray-white crystals were found in Broken Hill, New South Wales, Australia.

Huntite

$CaMg(CO_3)_2$

TRIGONAL ● ●

Properties: C – white; S – white; L – earthy; D – opaque; DE – 2.7; H – 1.5; CL – none; F – conchoidal; M – fibrous aggregates, earthy.
Origin and occurrence: Secondary mineral resulting from the oxidation of dolomite, associated with magnesite and dolomite. Fine fibrous aggregates come

Aragonite, 49 mm, Tazouta, Morocco



Flos ferri, 110 mm, Erzberg, Austria



from Koksin, Czech Republic. It also occurs in the Ala-Mar deposit, Nevada, USA. Massive aggregates are known from the Boquira mine, Bahia, Brazil.

Aragonite

$CaCO_3$

ORTHORHOMBIC ● ● ● ●

Varieties: flos ferri, hot-spring tufa, peastone, tarnowitzite.

Properties: C – colorless, white, yellow, reddish, greenish, purplish, bluish, gray; S – white; L – vitreous; D – transparent to opaque; DE – 3; H – 3.5-4.5; CL – imperfect; F – conchoidal; M – prismatic crystals, oolitic, banded, columnar and dendritic aggregates, massive; LU – locally weak cream yellow.

Peastone, 35 mm, Karlovy Vary, Czech Republic



Origin and occurrence: Primary as a late hydrothermal mineral of high-temperature deposits more commonly secondary as a product of the oxidation of siderite and pyrite. It also results from precipitation of thermal springs, it is sedimentary and metamorphic. Fine white prismatic crystals up to 70 mm (2¼ in) long found together with blue celestite crystals in _pania Dolina, Slovakia. Similar crystals come from sulfur deposits in Cianciano, Italy and Tarnobrzeg, Poland. Maybe the best aragonite crystals in the world are known from the gossan of the magnesite deposit in Podrecany, Slovakia, where druses of crystals up to 200 mm (7⅞ in) long were found. Wine yellow crystals up to 100 mm (¾ in) long occurred in cavities of volcanic rocks in Horenec near Bilina, Czech Republic. Those crystals were the only gem rough, suitable for facetting, in the world. Very interesting copper pseudo-morphs after aragonite come from Corocoro, Bolivia. Banded and oolitic aggregates found in Karlovy Vary, Czech Republic. Dendritic aggregates from Erzberg, Austria and elsewhere are known as flos ferri.

Application: decorative stone.

Strontianite, 34 mm, Hardin Co., U.S.A.



Strontianite

$SrCO_3$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, gray, yellowish, greenish, reddish, brown; S – white; L – vitreous to resinous; D – transparent to translucent; DE – 3.8; H – 3.5; CL – perfect; F – conchoidal to uneven; M – prismatic and acicular crystals, columnar and fibrous aggregates, massive, earthy.
Origin and occurrence: Hydrothermal in low-temperature veins, in cavities of volcanic rocks, mainly sedimentary, together with calcite and zeolites. Crystals up to 80 mm (3⅛ in) long occur near Bleiberg, Austria. Smaller crystals known from Strontian, Scotland. Crystals up to 50 mm long found in marls in Ahlen near Münster, Germany.

Witherite

$BaCO_3$

ORTHORHOMBIC ● ●

Properties: C – white, gray, yellowish; S – white; L – vitreous to greasy. D – translucent; DE – 4.3; H – 3.5; CL – good; F – uneven; M – pseudo-hexagonal dipyramidal crystals, fibrous and botryoidal aggregates, massive.
Origin and occurrence: Hydrothermal in low-temperature deposits with fluorite, barite, calcite and other minerals. Beautiful yellowish crystals up to 120 mm ($4\frac{11}{16}$in) long come from the Minerva No.1 mine, Cave-in-Rock, Illinois, USA. Crystals, up to 70 mm (2¾ in) in size occurred in Hexham and Alston Moor, England, UK. Its pseudo-hexagonal crystals or botryoidal aggregates were very rare in Pribram, Czech Republic.

Cerussite

$PbCO_3$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, whitish, yellow, black; S – white; L – greasy to adamantine; D – translucent; DE – 6.6; H – 3-3.5; CL – good; F – conchoidal; M –

Witherite, 20 mm x, Alston Moor, UK



Cerussite, 92 mm, Tsumeb, Namibia



prismatic and pyramidal crystals, common trillings and twins, granular, massive; LU – sometimes yellowish.

Origin and occurrence: Secondary mineral, resulting from the oxidation of galena and other Pb minerals, together with pyromorphite, vanadinite, barite and other minerals. The best specimens come from Tsumeb, Namibia, where trillings up to 200 mm (7⅞ in) in diameter occurred. Large twins also known from Broken Hill, New South Wales, Australia. Beautiful crystals up to 50 mm (2 in) in size reported from Mibladen, Morocco. Fine crystals up to 50 mm (2 in) long found in Stribro, Czech Republic. Typical white acicular crystals, up to 60 mm (2⅜ in) long come from the Flux mine, Arizona, USA.

Barytocalcite

$BaCa(CO_3)_2$

MONOCLINIC ● ●

Properties: C – colorless, white, gray, yellowish; S – colorless; L – vitreous to resinous; D – transparent to translucent; DE – 3.7; H – 4; CL – perfect; F – conchoidal to uneven; M – prismatic, often striated crystals, massive; LU – light yellow.

Origin and occurrence: Hydrothermal in low-temperature veins, together with calcite, barite and other minerals. Crystals several cm in size and cleavable masses are known from Alston Moor, Cumbria, UK. Imperfect crystals about 10 mm (⅜ in) in size occurred in Stříbro, Czech Republic. It is also described from Freiberg, Germany and from Langban, Sweden.

Barytocalcite, 52 mm, Alston Moor, UK



Azurite, 48 mm, Touissit, Morocco



Malachite, 63 mm, Mashamba West, Zair



Azurite

$Cu_3(CO_3)_2(OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – blue; S – blue; L – vitreous; D – transparent to opaque; DE – 3.8; H – 3.5; CL – perfect; F – conchoidal; M – tabular and prismatic crystals, pulverulent.
Origin and occurrence: Secondary, resulting from the oxidation of Cu sulfides, mainly associated with malachite. Crystals up to 200 mm ($7\frac{7}{8}$ in) long come from Tsumeb, Namibia. Crystals from Touissit, Morocco reach up to 70 mm (2¾ in). Tabular crystals up to 50 mm (2 in) in size found in Chessy near Lyon, France. Famous crystals up to 50 mm (2 in) across occurred in the Copper Queen mine in Bisbee, Arizona, USA. Fine azurite concretions with crystals on the surface come from La Sal, Utah, USA. Crystal rosettes, reaching up to 130 mm ($5\frac{5}{16}$ in) in size were found in the Yang Chweng Mine, Guang Dong, China.
Application: Cu ore.

Malachite

$Cu_2(CO_3)(OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – green; S – light green; L – vitreous, dull, earthy; D – opaque; DE – 4.1; H – 3.5-4; CL – perfect; F – conchoidal to uneven; M – acicular and prismatic crystals, botryoidal aggregates, stalactites, massive.
Origin and occurrence: The most common supergene mineral of Cu, associated with azurite, cuprite and other minerals. Crystals up to 30 mm ($1\frac{3}{16}$ in) in size occur in Kambove, Zaire. Crystals up to 20 mm ($\frac{25}{32}$ in) also found in Rudab<nya, Hungary. Pseudomorphs after azurite crystals up to 100 mm (4 in) in size known from Tsumeb; pseudo-morphs after cuprite crystals up to 50 mm in size come from Onganja, Namibia. The blocks of banded malachite weighing up to 250 tons . occurred in Mednorudnjansk, Ural mountains, Russia. Similar material in huge quantities come from many deposits in Shaba

Malachite, 70 mm, Shaba, Zair





Rosasite, 270 mm, Gleeson, U.S.A.

province, Zaire, where stalactites up to 500 mm (20 in) long were also found.
Application: Cu ore, production of decorative objects and jewelry.

Rosasite
$(Cu,Zn)_2(CO_3)(OH)_2$

MONOCLINIC ● ●

Properties: C – green, blue; S – greenish; D – opaque; DE – 4.0-4.2; H – 4.5; CL – good; M – small acicular crystals, fibrous and botryoidal crusts.
Origin and occurrence: Secondary, forming in the oxidation zone of Cu and Zn deposits, together with other secondary minerals of Cu. Spherical aggregates of acicular crystals up to 10 mm (3/8 in) found in Mina Ojuela, Mapimi, Durango, Mexico. Similar finds were made in Bisbee, Arizona, USA.



Hydrozincite, 65 mm, Tiger, U.S.A.

Hydrozincite
$Zn_5(CO_3)_2(OH)_6$

MONOCLINIC ● ● ●

Properties: C – white, yellowish; S – white; L – pearly to dull; D – opaque; DE – 4; H – 2-2.5; CL – perfect; F – conchoidal; M – tabular crystals, massive, earthy; LU – locally blue.
Origin and occurrence: Secondary, resulting from the oxidation of sphalerite, together with cerussite, smithsonite and hemimorphite. Small crystals are known from Mapimi, Durango, Mexico. Spherical aggregates, several mm in diameter, were found in Sterling Hill, New Jersey, USA. Stalactites and thick crusts occurred in Long-Kieng, Burma. Crusts and stalactites were also described from Bleiberg, Austria; from Mezica, Slovenia and from Raibl, Italy.

Aurichalcite
$(Zn,Cu)_5(CO_3)_2(OH)_6$

ORTHORHOMBIC ● ● ●

Properties: C – light green, blue-green, blue; S – blue-green; L – silky to pearly; D – translucent; DE – 4; H – 1-2; CL – perfect; M – acicular crystals, crusts.
Origin and occurrence: Secondary in the oxidation zone of Cu and Zn deposits in the arid climate, associated with linarite and other minerals. Large prismatic crystals come from Mina Ojuela, Mapimi, Durango, Mexico. Nice rosettes of acicular crystals are known from Bisbee and from the 79 mine, Banner district, Arizona, USA. It also occurred in Monteponi, Sardinia, Italy.



Aurichalcite, 80 mm, Arizona, U.S.A.

Dawsonite, 2 mm aggregate, Recsk, Hungary

Dawsonite

$NaAl(CO_3)(OH)_2$

ORTHORHOMBIC ● ● ●

Properties: C – colorless to white; S – white; L – vitreous; D – transparent; DE – 2.4; H – 3; CL – perfect; M – acicular to blade-like crystals, radial aggregates.
Origin and occurrence: Hydrothermal in low-temperature deposits, associated with calcite, dolomite and other minerals. Fine acicular crystals up to 35 mm ($1\frac{3}{8}$ in) long come from Mont St.-Hilaire, Quebec, Canada. Radial aggregates along the rock cracks were found in Dubník and Zlata Bana, Slovakia.

Bastnäsite-(Ce)

$(Ce,La)(CO_3)F$

HEXAGONAL ● ● ●

Properties: C – yellow to brown; S – yellow-brown; L – vitreous to greasy; D – translucent; DE – 4.8-5.2;

Parisite-(Ce), 71 mm, Boyaca, Colombia

Bastnasite-(Ce), 6 mm x, Ariege, France



H – 4-4.5; CL – good; F – uneven; M – tabular crystals, granular, massive.
Origin and occurrence: Magmatic in pegmatites, also metamorphic, together with allanite-(Ce) and other rare earth elements minerals. Crystals up to 200 x 150 mm (7 7/8 x 6 in) in size occur in Andekatany, Madagascar. Crystals up to 100 mm (4 in) long are known from Karonge, Burundi. Transparent crystals up to 25 mm (1 in) long were found recently in the Trimouns quarry, France. It forms important local deposits, as those of Mountain Pass, California, USA.*Application:* ore of rare earth elements.

Parisite-(Ce)

$CaCe_2(CO_3)_3F_2$

TRIGONAL ● ● ●

Properties: C – brown, yellow-brown, gray-yellow; S – brownish; L – vitreous to resinous; D – transparent to translucent; DE – 4.4; H – 4.5; CL – perfect; F – conchoidal to splintery; M – dipyramidal striated crystals.
Origin and occurrence: Magmatic in pegmatites, also hydrothermal and rarely metamorphic, together with bastnasite-(Ce) and other minerals of rare earth elements. Crystals several cm long come from Quincy, Massachusetts, USA. Crystals up to 80 mm (3 1/8 in) long occurred in pegmatites near Hundholmen, Norway. Crystals up to 23 cm (9 1/16 in) long found in the Snowbird mine, Montana, USA. Transparent crystals up to 15 mm (1 9/32 in) were lately reported in the Trimouns quarry, France. Very unusual association have been described from Muzo, Columbia, where crystals up to 50 mm occur together with emeralds.

Phosgenite

$Pb_2(CO_3)Cl_2$

TETRAGONAL ● ●

Properties: C – colorless, white, yellow-white, gray, brown; S – white; L – adamantine; D – transparent to translucent; DE – 6.1; H – 2-3; CL – good; F – conchoidal; M – short to long prismatic and tabular crystals, granular, massive; LU – sometimes yellow.
Origin and occurrence: Secondary, resulting from the oxidation of galena, associated with cerussite and other secondary Pb minerals. Crystals up to 150 x 100 mm (6 x 4 in) across known from Monteponi, Sardinia, Italy. Crystals from Tsumeb, Namibia reached up to 100 mm. Crystals up to 30 mm (1 3/16 in) in size found in Matlock, Derby, UK. Crystals up to 35 mm (1 3/8 in) long occurred in the Mammoth mine, Tiger, Arizona, USA.

Phosgenite, 28 mm, Monteponi, Italy





Bismutite, 3 mm xx, Brdarka, Slovakia

Bismutite

$Bi_2O_2(CO_3)$

TETRAGONAL ● ● ●

Properties: C – yellow, brown, gray, blue, black; S – white; L – vitreous, pearly to dull; D – translucent to opaque; DE – 6.1-7.7; H – 3.5; CL – good; M – spherical, radial aggregates, massive, pulverulent.
Origin and occurrence: Secondary, originated from the oxidation of Bi minerals, associated with bismuthinite and other minerals. It is common from pegmatites in Madagascar (Ampangabe) and in Mozambique. Large pebbles found in Kivu province, Zaire. It also occurred in Tasna, Bolivia.



Weloganite, 30 mm xx, Francon Quarry, Canada



Gaylussite, 30 mm, Natron Lake, Tanzania

Gaylussite

$Na_2Ca(CO_3)_2 . 5\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, gray, yellowish; S – colorless; L – vitreous; D – transparent to translucent; DE – 2; H – 2.5-3; CL – perfect; F – conchoidal; M – lenticular to prismatic crystals.
Origin and occurrence: Sedimentary, typical a constituent of salt sediments. Crystals up to 80 mm (3$^{1}/_{8}$ in) long come from Searles Lake, California, USA. It also occurs in Borax Lake and Mono Lake, California, USA. Large crystals are known from Amboseli Lake, Kenya.

Weloganite

$Na_2Sr_3Zr(CO_3)_6 . 3\ H_2O$

TRICLINIC ●

Properties: C – white, yellow; S – white; L – vitreous; D – transparent to opaque; DE – 3.2; H – 3.5; CL – perfect; F – conchoidal; M – pseudohexagonal striated crystals.
Origin and occurrence: Hydrothermal in the alkaline rocks, together with zircon, dresserite and other minerals. Crystals up to 50 mm (2 in) come from cavities in the Francon quarry, Montreal; crystals up to 30 mm (1$^{3}/_{16}$ in) are known from St. Michel, Quebec, Canada.

Artinite, 10 mm, Fethiya, Turkey



Artinite

$Mg_2(CO_3)(OH)_2 \cdot 3\ H_2O$

MONOCLINIC ● ● ●

Properties: C – white; S – white; L – silky; D – transparent; DE – 2; H – 2.5; CL – perfect; M – spherical, radial aggregates, veinlets, crusts.
Origin and occurrence: Hydrothermal, originating at low temperatures in serpentinites, associated with magnesite, aragonite and other minerals. Radial aggregates up to 20 mm ($^{25}/_{32}$ in) in size occur in the Gem mine, San Benito County, California, USA. Needles up to 20 mm ($^{25}/_{32}$ in) long come from Val Malenco, Italy. Clusters of acicular crystals were found on Staten Island, New York, USA.

Zaratite, 70 mm, Lancaster Co., U.S.A.



Hydrotalcite, 1 mm xx, Dunabogdany, Hungary



Zaratite

$Ni_3(CO_3)(OH)_4 \cdot 4\ H_2O$

CUBIC ● ● ●

Properties: C – emerald-green; S – light green; L – vitreous to greasy; D – transparent to translucent; DE – 2.6-2.7; H – 3.5; CL – none; F – conchoidal; M – crystalline crusts, stalactites, coatings.
Origin and occurrence: Secondary, originating from the oxidation of Ni minerals, associated with millerite, brucite and other minerals. It occurs as a product of the oxidation of Ni minerals in ultrabasic rocks in Kraubat and Stubachtal, Austria. Large green coatings found in Heazlewood, Tasmania, Australia. It covers millerite needles in the vicinity of Kladno, Czech Republic.

Hydrotalcite

$Mg_6Al_2(CO_3)(OH)_{16} \cdot 4\ H_2O$

TRIGONAL ● ●

Properties: C – white; S – white; L – pearly to waxy; D – transparent; DE – 2.1; H – 2; CL – perfect; M – fibrous and layered aggregates, massive.
Origin and occurrence: : Hydrothermal in ultrabasic and metamorphic rocks. It occurred with serpentine in Nordmark, Norway and also found at Franklin and Sterling Hill, New Jersey, USA.

Stichtite, 35 mm, Rouchovany, Czech Republic



Stichtite

$Mg_6Cr_2(CO_3)(OH)_{16} . 4\ H_2O$

TRIGONAL ● ●

Properties: C – pink to purple; S – white to light purple; L – pearly, waxy to greasy; D – translucent; DE – 2.2; H – 1.5-2; CL – perfect; M – lamellar and fibrous aggregates, massive.
Origin and occurrence: It occurs in serpentinites as scaly aggregates and veinlets in Bou Azzer, Morocco; in Dundas, Tasmania, Australia and in Barberton, South Africa.

Alumohydrocalcite

$CaAl_2(CO_3)_2(OH)_4 . 3\ H_2O$

TRICLINIC ● ●

Properties: C – white, gray; S – white; L – earthy; D – opaque; DE – 2.2; H – 2.5; CL – perfect; M – chalky aggregates, consisting of acicular crystals.
Origin and occurrence: Secondary, associated with alophane and other minerals. It was described from the Khakasy deposit, Siberia, Russia, where it originates from the oxidation of alophane. Nice white radial aggregates occurred along the cracks in shales in L'adomírovo, Slovakia.

Ancylite-(Ce)

$Sr_3(Ce,La)_4(CO_3)_7(OH)_4 . 3\ H_2O$

ORTHORHOMBIC ● ●

Properties: C – colorless, yellow, yellow- brown, light purple, brown; S – white; L – vitreous to greasy; D – transparent to opaque; DE – 4; H – 4-4.5; CL – none; F – splintery; M – short to long prismatic and pseudo-octahedral crystals.
Origin and occurrence: Hydrothermal in alkaline rocks, associated with nepheline and other minerals. Crystals up to 6 mm (¼ in) long are known from

Alumohydrocalcite, 70 mm, Ladomirovo, Slovakia



6. Borates

Ludwigite
$Mg_2Fe^{3+}BO_5$

ORTHORHOMBIC ● ● ●

Properties: C – dark green, black-green, black; S – blue-green; L B silky to dull; D – opaque; DE – 3.9; H – 5; CL – perfect; F B uneven; M – prismatic crystals, fibrous aggregates, granular, massive.
Origin and occurrence: Metamorphic in skarns and dolomitic marbles, locally associated with magnetite and other borates. Rich aggregates are known from Ocna de Fier, Romania; Kamineichi, Japan and the Hol Kol mine, Suan, North Korea.
Application: chemical industry, B ore.

Gaudefroyite
$Ca_4Mn^{3+}_3(BO_3)_3CO_3(O,OH)_3$

HEXAGONAL ●

Properties: C – black; S – black; L – adamantine to dull; D – opaque; DE – 3.4; H – 6; CL – good; F – uneven; M – prismatic crystals, fibrous and acicular aggregates.
Origin and occurrence: Hydrothermal in calcite veins. Prismatic crystals up to 50 mm (2 in) long were found on the mine dumps near Tachgagalt, Morocco and in the N'Chwaning No. 2 mine and the Wessels mine, Kuruman, South Africa.

Gaudefroyite, 40 mm, Kuruman, South Africa
Ludwigite, 120 mm, Ocna de Fier, Romania



Inderite, 230 mm, Boron, U.S.A.



Inderite
$MgB_3O_3(OH)_5 \cdot 5\,H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white to pink in aggregates; S – white; L – vitreous; D – transparent to translucent; DE – 1.8; H – 2.5; CL – good; F – conchoidal to uneven; M – prismatic crystals, acicular and fibrous aggregates, nodules, massive.
Origin and occurrence: Sedimentary in boron deposits, commonly associated with colemanite and other borates. Prismatic crystals up to 100 mm (4 in) long occur in Boron, California, USA. It is also known from Inder, Kazakhstan.
Application: chemical industry, B ore.


Inyoite, 90 mm, Turkey


Borax, 60 mm x, Searles Lake, U.S.A.

Inyoite

$CaB_3O_3(OH)_5 \cdot 4\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white; S – white; L – vitreous; D – transparent to translucent; DE B 1.9; H – 2; CL – good; F – uneven; M – short prismatic to tabular crystals, columnar aggregates, massive.
Origin and occurrence: Sedimentary in boron deposits, commonly associated with colemanite and other borates. Clear tabular crystals up to 100 mm (4 in) long found in Kirka and Emet, Turkey. It also comes from Inder, Kazakhstan and the Corkscrew mine, California, USA.
Application: chemical industry, B ore.


Ulexite, 20 mm aggregate, Death Valley, California, U.S.A.

Borax

$Na_2B_4O_5(OH)_4 \cdot 8 H_2O$

MONOCLINIC ● ● ●

Properties: C – white, colorless, yellowish, gray, greenish; S – white; L B vitreous to dull; D – transparent, translucent to opaque; DE – 1.7; H – 2-2.5; CL – perfect; F – conchoidal; M – short prismatic to tabular crystals, columnar to earthy aggregates, crusts, coatings, granular, massive; R – soluble in water.
Origin and occurrence: Sedimentary in boron deposits, associated with other borates and halite. Prismatic crystals up to 150 mm long are known from Borax Lake, also Searles Lake and Boron, California, USA. It also occurs in Kirka, Turkey.
Application: chemical industry, B ore.

Ulexite

$NaCaB_5O_6(OH)_6 \cdot 5 H_2O$

TRICLINIC ● ● ●

Properties: C – white, colorless, light gray; S – white; L B vitreous to silky; D – transparent to translucent; DE – 2.0; H – 2.5; CL – perfect; F B uneven; M – elongated prismatic to acicular crystals, fibrous aggregates, crusts, nodules, granular, massive.
Origin and occurrence: Sedimentary in boron deposits, associated with other borates. Slabs up to 100 mm (4 in) thick consisting of fibrous aggregates occur in Boron, California; also found in Esmeralda, Nevada, USA; Emet, Turkey and Inder, Kazakhstan.
Application: chemical industry, B ore.

Colemanite

$Ca_2B_6O_{11} \cdot 5 H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, yellowish, light gray; S – white; L – vitreous; D – transparent to translucent; DE – 2.4; H – 4.5; CL – perfect; F B uneven; M – short prismatic and isometric crystals, granular, massive.
Origin and occurrence: Sedimentary in boron deposits, associated with other borates. Perfect crystals up to 200 mm (7⅞ in), come from Emet and Kirka, Turkey. Crystals up to 70 mm (2¾ in) long occur in Gower Gulch, Inyo, California; also known from Esmeralda, Nevada, USA and Inder, Kazakhstan.
Application: chemical industry, B ore.

Kernite, 100 mm, Boron, U.S.A.



Kernite

$Na_2B_4O_6(OH)_2 . 3 H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, light gray; S – white; L – vitreous to dull, silky; D – transparent, translucent to opaque; DE – 1.9; H – 2.5-3; CL – perfect; F – uneven; M – isometric crystals, fibrous aggregates, granular, massive; R – soluble in water.

Rhodizite, 23 mm, Antsirabe, Madagascar



Hambergite, 64 mm, Pamir, Tadzhikistan



Origin and occurrence: Sedimentary in boron deposits, associated with borax and other borates. Platy aggregates and crystals up to 2.5 x 1 m (8 ft x $39\tfrac{3}{8}$ in) found in Boron, California, USA; also known from the Tincalayu mine, Salta province, Argentina.

Hambergite

$Be_2BO_3(OH,F)$

ORTHORHOMBIC ● ●

Properties: C – colorless, white, light gray; S – white; L – vitreous; D – transparent to translucent; DE – 2.4; H – 7.5; CL B perfect; F B uneven; M – tabular to prismatic crystals, granular.

Origin and occurrence: Magmatic in granitic and rarely also in alkaline pegmatites; hydrothermal in cavities within the pegmatites, associated with tourmaline, danburite and beryl. Tabular crystals up to 200 mm ($7\tfrac{7}{8}$ in) from the Little Three mine, Ramona, California, USA. Crystals up to 110 mm ($4\tfrac{5}{16}$ in) also known from several localities in Madagascar, e.g. Imalo and Anjanabonoina; also found in Hyakule, Nepal and Ctidruzice, Czech Republic .

Rhodizite

$(K,Cs)Al_4Be_4(B,Be)_{12}O_{28}$

CUBIC ● ●

Properties: C – colorless, white, yellow, light gray; S – white; L – vitreous to adamantine; D – transparent to translucent; DE – 3.5; H – 8.5; CL – imperfect; F – conchoidal to uneven; M – isometric crystals, granular.

Origin and occurrence: Magmatic in granitic pegmatites, associated with tourmaline, danburite and beryl. Cubic to tetrahedral crystals, reaching up to 30 mm ($1\tfrac{3}{16}$ in) occur in several localities in

Madagascar, e.g. Sahatany and Antandrokomby; also known from the Animikie Red Ace pegmatite, Florence, Wisconsin, USA.

Boracite

$Mg_3B_7O_{13}Cl$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish, light gray, light to dark green; S – white; L – vitreous; D – transparent to translucent; DE – 3.0; H – 7-7.5; CL – none; F – conchoidal to uneven; M – isometric crystals, fibrous aggregates, granular, massive.

Origin and occurrence: Sedimentary in evaporitic deposits, together with halite, gypsum and anhydrite; metamorphic in metamorphosed evaporates. Crystals up to 15 mm (19/32 in) come from Alto Chapare, Cochabamba, Bolivia; crystals about 5 mm (3/16 in) in size, occur in Stassfurt, Hanover and Kahlberg, Germany. Crystals are also known from Choctaw, Louisiana, USA and the Boulby mine, North Yorkshire, England, UK.

Boracite, 12 mm x, Alto Chapare, Bolivia



7. Sulfates

Anglesite

$PbSO_4$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish, gray, greenish; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 6.4; H – 2.5 – 3; CL – dobra; F – conchoidal; M – thick tabular crystals, massive, LU – sometimes yellowish.
Origin and occurrence: Secondary, as a result of the galena oxidation, together with cerussite and other minerals. Beautiful yellowish crystals up to 100 mm (4 in) in size come from Touissit, Morocco. Crystals from Tsumeb, Namibia, reached up to 40 mm ($1^{9}/_{16}$ in). Large crystals are also reported from Phoenixville, Pennsylvania, USA. Crystals up to 20 mm ($^{25}/_{32}$ in) occur in cavities in weathered galena in Sardinia, Italy. Crystals, reaching up to 40 mm ($1^{9}/_{16}$ in) also found in Mezica , Slovenia. Prismatic crystals up to 75 mm (3 in) long known from the Bunker Hill mine, Idaho, USA.

Barite, 17 mm xx, Pöhla, Germany
Anhydrite, 55 mm, Simplon Tunnel, Switzerland



Anglesite, 81 mm, Touissit, Morocco



Anhydrite

$CaSO_4$

ORTHORHOMBIC ● ● ● ●

Properties: C – colorless, white, bluish, purplish, red, brown; S – white; L – pearly to vitreous; PS – transparent to translucent; DE – 2.8-3; H – 3-3.5; CL – good; F – splintery to uneven; M – isometric and prismatic crystals, granular, massive.
Origin and occurrence: Mostly sedimentary, as a result of the evaporation of sea water, associated with gypsum, calcite and other minerals; rare in pegmatites and hydrothermal. It is very common in form of massive aggregates in salt deposits in Stassfurt and Wathlingen, Germany, where small crystals also occur. Folded layers in clays known from Wieliczka, Poland. Purplish crystals up to 20 mm ($^{25}/_{32}$ in) found in cracks in metamorphic rocks near Simplon and St. Gotthard, Switzerland. Fine druses of bluish crystals up to 200 mm ($7^{7}/_{8}$ in) long found in Naica, Chihuahua, Mexico.

↓+

Celestine, 270 mm, Madagascar

Celestite

$SrSO_4$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish, blue; S – white; L – vitreous; D – transparent to translucent; DE – 4; H – 3-3.5; CL – perfect; F – uneven; M – prismatic and tabular crystals, columnar aggregates, concretions.

Origin and occurrence: Rare hydrothermal, mainly sedimentary, together with halite, anhydrite and gypsum. Beautiful blue crystals several cm long occur in cavities of concretions in the Sakoany mine, Madagascar. Prismatic crystals up to 100 mm (4 in) long in sulfur deposits in Poland (Tarnobrzeg) and Italy (Caltanissetta). Fine blue tabular crystals associated with aragonite crystals found in _pania Dolina, Slovakia. Fine crystals are known from marls in Tunisia and Libya.

Barite

$BaSO_4$

ORTHORHOMBIC ● ● ● ●

Properties: C – white, yellow, blue, red, brown, black; S – white; L – vitreous; D – transparent to translucent; DE – 4.3-4.7; H – 3.5; CL – perfect; F – conchoidal to splintery; M – tabular to prismatic crystals, massive; LU – sometimes blue.

Origin and occurrence: Hydrothermal, it originates under medium and low temperatures, also sedimentary, together with fluorite, calcite, cinnabar and other minerals. Beautiful barite crystals up to 50 mm (2 in) found in hydrothermal veins in Pribram, Czech Republic. Blue tabular crystals up to 100 mm (4 in) from Dedova hora, Czech Republic. Beautiful tabular crystals up to 100 mm (4 in) known from Banska Stiavnica, Slovakia; Cavnic and Baia Spric, Romania. Very fine crystals of up to 200 mm (7⅞ in) occurred in Alston Moor, Frizington and Mowbray, Cumbria, UK. Beautiful druses of honey-brown crystals up to 70 mm (2¾ in) long found in Pohla, Germany. Fine druses of prismatic crystals known from Elk Creek, South Dakota, USA; so called

Antlerite, 60 mm, Chuquicamata, Chile

Barite, 100 mm xx, Stoneham Co., U.S.A.

desert roses (crystals with inclusion of sand grains) originating in desert climate occur in the vicinity of Norman, Oklahoma, USA. Shiny crystals come from Freiberg and Halsbrucke, Germany.
Application: an ingredient of drilling fluids, chemical, glass, paper and rubber industries.

Antlerite

$Cu_5(SO_4)_2(OH)_6 \cdot 3\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – green; S – light green; L – vitreous; D – translucent; DE – 3.9; H – 3.5; CL – perfect; F – conchoidal to uneven; M – short prismatic and acicular crystals, crusts and earthy aggregates.
Origin and occurrence: Secondary, resulting from weathering of Cu ores, associated with other secondary Cu minerals. It is a principal mineral of the oxidation zone in Chuquicamata, Chile, where it forms crystals up to 5 mm (3/16 in). Acicular crystals, up to 20 mm (25/32 in) long, occurred in Bisbee, Arizona, USA. Crystalline crusts are known from Spania Dolina and Piesky, Slovakia.

Brochantite, 14 mm aggregate, Bingham, U.S.A.



Brochantite

$Cu_4(SO_4)(OH)_6$

MONOCLINIC ● ● ●

Properties: C – green; S – light green; L – vitreous, in cleavage planes pearly; D – translucent to transparent; DE – 4; H – 3.5-4; CL – good; F – conchoidal to uneven; M – long prismatic to acicular crystals, granular.
Origin and occurrence: Secondary, as a result of the oxidation of Cu ores usually in the arid climate, together with other secondary Cu minerals. Crystals up to 70 mm (2¾ in) long found in Bisbee, together with pseudo-morphs of malachite after brochantite. Crystals are also known from Tsumeb, Namibia. Prismatic crystals up to 50 mm (2 in) long from Cerro Verde, Peru. Emerald-green crusts occur in L'ubietova, Slovakia.

Linarite, 23 mm xx, Graham Co., U.S.A.



Linarite

$PbCu(SO_4)(OH)_2$

MONOCLINIC ● ●

Properties: C – azure-blue; S – light blue; L – vitreous to adamantine; D – translucent; DE – 5.3-5.5; H – 2.5; CL – good; F – conchoidal; M – tabular and prismatic crystals, coatings.
Origin and occurrence: Secondary, as a result of the oxidation of Cu and Pb sulfides at low pH. The largest crystals, reaching up to 80 mm ($3^{1}/_{8}$ in), come from the Mammoth mine, Tiger, Arizona, USA. Crystals from the Grand Reef mine in Arizona up to 50 mm (2 in) long. Very fine crystals, up to 30 mm ($1^{3}/_{16}$ in) were found in Keswick, Cumbria, England, UK. Large crystals were also described from Tsumeb, Namibia and from Broken Hill, New South Wales, Australia.

Alunite

$KAl_3(SO_4)_2(OH)_6$

TRIGONAL ● ● ●

Properties: C – white, yellowish, gray; S – white; L – vitreous to pearly; D – transparent to opaque; DE – 2.8; H – 3.5-4; CL – perfect; F – conchoidal; M – rhombohedral crystals, porous aggregates, granular.
Origin and occurrence: Secondary, as a result of reactions of sulfuric acid with Al-rich rocks, associated with gypsum. Small crystals are known in Berehovo, Ukraine. Massive aggregates occur together with turquoise in Cu deposits in Arizona, USA. (New Cornelia mine and others). Huge alunite deposits, like Zaglik, Azerbaijan, are mined for Al.
Application: Al ore.

Alunite, 1 mm xx, Nagyegyhaza, Hungary



Natrojarosite, 50 mm, Laurion, Greece



Natrojarosite

$NaFe^{3+}_3(SO_4)_2(OH)_6$

TRIGONAL ● ●

Properties: C – yellow, brown; S – light yellow; L – vitreous; D – transparent to translucent; DE – 3.2; H – 3; CL – good; F – conchoidal; M – tabular to rhombohedral crystals, earthy aggregates..
Origin and occurrence: Secondary, as a result of weathering Fe sulfides, associated with fibroferrite, alunite and other minerals. It occurs in Modum, Norway; Soda Springs Valley, Nevada, USA; Chuquicamata, Chile and elsewhere.

Jarosite

$KFe^{3+}_3(SO_4)_2(OH)_6$

TRIGONAL ● ● ●

Properties: C – yellow; S – light yellow; L – adamantine to dull; D – translucent; DE – 2.9-3.3; H – 2.5-3.5; CL – good; F – conchoidal to uneven; M – rhombohedral to tabular crystals, granular, massive.
Origin and occurrence: : Secondary, as a result of weathering Fe sulfides, usually associated with natrojarosite and other sulfates. The world's best specimens come from Pena Blanca Uranium mine, near Aldama, Chihuahua, Mexico, where crystals, up to 20 mm (25/32 in) were found. Crystals, up to 10 mm (3/8 in), were found in Tombstone, Arizona, USA. Crystals, together with pseudo-morphs of jarosite after alunite, occurred in Chuquicamata, Chile. Tabular crystals also were described from Horni Slavkov, Czech Republic.

Jarosite, 2 mm xx, Gyongyösoroszi, Hungary



Beudantite

$PbFe^{3+}_3(AsO_4)(SO_4)(OH)_6$

TRIGONAL ● ●

Properties: C – dark green, brown, red-brown; S – greenish, gray-yellow; L – vitreous to resinous; D – transparent to translucent; DE – 4; H – 3.5-4.5; CL – good; M – rhombohedral crystals, crusts.
Origin and occurrence: Secondary, occurring in the oxidation zone of Pb deposits, together with scorodite and other minerals. Crystals, several mm in size, found in Tsumeb, Namibia, are the best in the world. Small crystals are known from Bisbee, Arizona, USA; Ashburton Downs, Western Australia, Australia and Kamarcza near Laurion, Greece.

Beudantite, 70 mm, Moldava, Czech Republic



Hanksite

$Na_{22}K(SO_4)_9(CO_3)_2Cl$

HEXAGONAL ● ●

Properties: : C – colorless, yellowish; S – colorless; L – vitreous to dull; D – transparent to translucent; DE – 2.6; H – 3.5; CL – good; F – uneven; M – tabular to short prismatic crystals.
Origin and occurrence: Sedimentary in salt lake sediments, together with halite, borax and other minerals. Crystals up to 200 mm ($7^{7}/_{8}$ in) found in Searles Lake, California, USA. It is also known from borax deposits in the Death Valley, California, USA.

Caledonite

$Cu_2Pb_5(SO_4)_3(CO_3)(OH)_6$

ORTHORHOMBIC ● ●

Properties: C – green to blue-green; S – light green; L – resinous; D – transparent to translucent; DE – 5.6; H – 2.5-3; CL – perfect; F – uneven; M – prismatic crystals, radial aggregates.

Origin and occurrence: Secondary, occurring in the oxidation zone of Cu and Pb deposits, associated with linarite and other minerals. Crystals up to 20 mm ($^{25}/_{32}$ in) come from Leadhills, Scotland, UK. Crystals, up to 15 mm ($^{19}/_{32}$ in), were found in the Mammoth mine, Tiger, Arizona, USA. Rich druses are known from Anarak, Iran. Crystals reaching up to 20 mm ($^{25}/_{32}$ in) occurred in the Blue Bell mine, California, USA.

Leadhillite

$Pb_4(SO_4)(CO_3)_2(OH)_2$

MONOCLINIC ● ●

Properties: C – colorless, yellowish, gray; S – colorless; L – resinous to adamantine; D – transparent to translucent; DE – 6.5; H – 2.5-3; CL – perfect; F – conchoidal; M – pseudo-hexagonal tabular crystals.
Origin and occurrence: Secondary mineral from the oxidation zone of Pb deposits, associated with cerussite, anglesite, linarite and other minerals. The largest crystals, measuring up to 15 cm, come from Tsumeb, Namibia. Crystals up to 25 mm (1 in) found in the Mammoth mine, Tiger, Arizona, USA. Crystals in Leadhills, Scotland, UK were of similar size.

Chalcantite

$CuSO_4 . 5 H_2O$

TRICLINIC ● ● ●

Properties: C – deep blue; S – white; L – vitreous to resinous; D – transparent to translucent; DE – 2.3; H – 2.5; CL – imperfect; F – conchoidal; M – short prismatic to tabular crystals, stalactites, films; R – soluble in water.

Hanksite, 50 mm, Searles Lake, U.S.A.



Caledonite, 5 mm x, Graham Co., U.S.A.





Origin and occurrence: Secondary, as a product of the oxidation of Cu sulfides, stable only in arid climate. Crystals up to 40 mm (1⁹/₁₆ in) in size, and stalactites, up to 1 m (39³/₈ in) long are known from Bisbee, Arizona, USA. Crystals were also found in the oxidation zone in Chuquicamata, Chile. Beautiful stalactites come from Rio Tinto, Spain.
Application: rarely mined as Cu ore.

Melanterite, 80 mm, Harz Mts., Germany



Melanterite

$FeSO_4 . 7 H_2O$

MONOCLINIC ● ● ● ●

Varieties: pisanite (with Cu contents), kirovite (with Mg contents)

Properties: C – light green; S – colorless; L – vitreous; D – translucent; DE – 1.9; H – 2; CL – perfect; F – conchoidal; M – granular crusts, botryoidal and stalactitic aggregates, films; R – soluble in water.
Origin and occurrence: Secondary, as a result of the oxidation of Fe sulfides, together with other sulfates. It is unstable under atmospheric conditions. Crystals up to 20 mm (²⁵/₃₂ in) long are known from Bisbee, Arizona and from the Boyd mine, Tennessee, USA. Stalactites, up to 50 cm (20 in) long, occurred in Chvaletice, Czech Republic. It is also common in Rio Tinto, Spain and Banska Stiavnica, Slovakia.

Epsomite

$MgSO_4 . 7 H_2O$

ORTHORHOMBIC ● ● ● ●

Properties: C – colorless to white; S – colorless; L – vitreous to silky; D – transparent to translucent; DE – 1.7; H – 2; CL – perfect; F – conchoidal; M – small crystals, granular, stalactitic aggregates; R – soluble in water, decomposing under atmospheric conditions.
Origin and occurrence: Secondary, as a result of the oxidation of Fe sulfides, also from crystallization of the salt lake water, associated with halite and other minerals. Crystals up to 1 m (39⅜ in) long were found on Mount Kruger, Washington; prismatic crystals up to 50 mm (2 in) long also occur in Bisbee, Arizona and needles of a similar size come from the White Caps mine, Nevada, USA. It is also known as a product of the activity of fumaroles in Mount Vesuvius, Italy.

Morenosite

$NiSO_4 . 7 H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – green, green-white; S – greenish; L – vitreous; D – transparent to translucent; DE – 2; H – 2-2.5; CL – good; F – conchoidal; M – stalactitic crusts and efflorescences; R – soluble in water.
Origin and occurrence: Secondary, as a product of the oxidation of Ni minerals, stable mainly in the arid regions. It is very common in Sudbury, Ontario, Canada; also in Richelsdorf, Germany and Potucky, Czech Republic.

Coquimbite

$Fe^{3+}{}_2(SO_4)_3 . 9 H_2O$

TRIGONAL ● ● ●

Properties: C – purple, yellow, green, colorless; S – colorless; L – vitreous; D – transparent; DE – 2.1; H – 2; CL – imperfect; F – conchoidal to uneven; M – prismatic to tabular crystals, granular, massive; R – soluble in water.
Origin and occurrence: Secondary, associated with other sulfates. Crystals, several cm long, were found in the Dexter No.7 mine, Calf Mesa, Utah, USA. Small prismatic crystals are known from Zelezník , tabular crystals occurred in Banska Stiavnica, Slovakia. It is very common in Chilean deposits, like Chuquicamata and Tierra Amarilla.

Alunogen

$Al_2(SO_4)_3 . 17 H_2O$

TRICLINIC ● ● ●

Properties: C – colorless, white, gray-yellow; S – colorless; L – silky; PS – transparent; DE – 1.8; H – 1.5; CL – perfect; M – pseudo-hexagonal crystals, granular; R – soluble in water.
Origin and occurrence: Secondary, as a result of the pyrite oxidation, also a product of sublimation on volcanoes and burning dumps, associated with other sulfates. Large crystals are known from the Dexter No.7 mine, Calf Mesa, Utah, crusts, over 1 m (39⅜ in) thick were found on Mount Alum, New Mexico,

Epsomite, 10 mm xx, Stassfurt, Germany



Morenosite, 60 mm, Potucky, Czech Republic



Coquimbite, 110 mm, Cerritos Bajos, Chile



USA. Fine aggregates occur on the walls of underground workings in the old opal mines in Dubník, Slovakia.

Halotrichite

$FeAl_2(SO_4)_4 . 22 H_2O$

MONOCLINIC ● ● ●

Properties: C – white, greenish; S – colorless; L – vitreous; PS – transparent to translucent; DE – 1.9-2.1; H – 1.5-2; CL – imperfect; F – conchoidal; M – acicular crystals, fibrous aggregates, efflorescences; R – soluble in water.
Origin and occurrence: Secondary, as a result of the pyrite oxidation, also a product of the activity of hot springs ans solfataras, associated with other sulfates. Common fibrous crusts occur in Dubnik, Slovakia. It looks similar in Rio Marina, Elba, Italy and in Chuquicamata, Chile. It is known from solfataras in Pozzuoli, Italy. It is a product of hot springs activity in the Lassen Peak National Park, California, USA.

Apjohnite

$MnAl_2(SO_4)_4 . 22 H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, pink, greenish, yellow; S – colorless; L – silky; D – transparent; DE – 1.9; H – 1.5; M – fibrous aggregates, coatings, massive; R – soluble in water.
Origin and occurrence: Secondary, occurring together with other sulfates. Large accumulations are known from Little Pigeon Creek, Alum Cave, Tennessee, USA. It also occurs in Delagona Bay, Mozambique.

Alunogen, 80 mm, Dubnik, Slovakia



Halotrichite, 90 mm, Recsk, Hungary



Apjohnite, 60 mm, Smolnik, Slovakia



Bilinite, 60 mm, Bilina, Czech Republic



Bilinite

$Fe^{2+}Fe^{3+}{}_2(SO_4)_4 \cdot 22\ H_2O$

MONOCLINIC ● ●

Properties: C – white to wellowish; S – white; L – silky; D – opaque; DE – 1.9; H – 2; M – fibrous aggregates; R – soluble in water.
Origin and occurrence: Secondary, as a result of the pyrite oxidation, associated with other sulfates. Fibrous aggregates are known from Svitec near Bilina, Czech Republic. Also described from Bisbee, Arizona, USA.

Tschermigite

$(NH_4)Al(SO_4)_2 \cdot 12\ H_2O$

CUBIC ● ● ●

Properties: : C – colorless; S – colorless; L – vitreous; D – transparent; DE – 1.6; H – 1.5; F – conchoidal; M – octahedral crystals, fibrous and columnar aggregates; R – soluble in water.

Tschermigite, 50 mm, Mogyororosbanya, Hungary



Origin and occurrence: Secondary in the brown coal, also on burning dumps and as a product of solfataras. Skeletal crystals up to 10 mm ($^3/_8$ in) in size are known from the brown coal basin near Most and Bilina, Czech Republic. Original locality Eermniky, Czech Republic yielded fibrous crusts, up to 50 mm (2 in) thick. Fine octahedra, up to 10 mm ($^3/_8$ in) come from burning dumps near Zastavka near Brno, Czech Republic. Octahedra occur also in Geysers, California, USA. Small crystals on Etna, Sicily, Italy are of volcanic origin.

Polyhalite

$KCa_2Mg(SO_4)_4 \cdot 2\ H_2O$

TRICLINIC ● ● ●

Properties: C – colorless, brown, red-brown; S – colorless; L – vitreous; D – transparent to translucent; DE – 2.8; H – 3-3.5; CL – perfect; M – acicular to prismatic crystals, columnar, scaly and fibrous aggregates.
Origin and occurrence: Sedimentary, as a constituent of salt deposits, also as a product of volcanic activity. Tabular and prismatic crystals are found rarely together with massive polyhalite aggregates in Stassfurt, Germany. Fibrous aggregates come from Halstatt, Austria. Large deposits of polyhalite are located near Carlsbad, New Mexico, USA. Coatings occur on Mount Vesuvius, Italy.

Görgeyite

$K_2Ca_5(SO_4)_6 \cdot H_2O$

MONOCLINIC ● ●

Properties: C – colorless, yellowish; S – colorless; L – vitreous; D – translucent; DE – 3; H – 3.5;

Polyhalite, 54 mm, Carlsbad, U.S.A.



Gypsum, 62 mm, Carneville, Utah, U.S.A.



CL – good; F – conchoidal; M – tabular crystals. *Origin and occurrence:* Sedimentary in salt deposits, associated with halite and other minerals. Fine crystals up to 80 mm (3⅛ in) long found near Inder Lake, Kazakhstan; also known from Bad Ischl, Austria.

Gypsum

$CaSO_4 . 2 H_2O$

MONOCLINIC ● ● ● ● ●

Varieties: Maria-glass, alabaster, satin spar, selenite. *Properties:* C – colorless, white, gray, yellowish; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 2.3; H – 1.5-2; CL – perfect; F – conchoidal; M – typical monoclinic crystals, often twins, fibrous and platy aggregates, granular, massive; LU – crystals with inclusions sometimes bluish to yellowish.

Gorgeyite, 80 mm, Inder Lake, Kazakhstan



Origin and occurrence: Rare primary hydrothermal, mostly sedimentary and as a weathering product, associated with anhydrite, halite and other minerals. Crystals up to 50 mm from Cavnic, Romania are probably hydrothermal. Huge crystals up to 1.5 m (5 ft) long found in karst cavities (Cave of Swords) in gossan in the PbBZn deposit Naica, Chihuahua, Mexico. Crystals up to 9 m (29 ft 6 in) long from Santa Eulalia, Chihuahua, Mexico, where they were found combined with interesting aggregates, called 'ram's horns' from their shape. Crystals up to 4 m (13 ft) long occurred in Tarnobrzeg, Poland. Common crystals are also known from Gorguel, Spain. The 'desert roses' or crystal druses, from Sahara desert in Tunisia and Algeria, with sand grain inclusions are mineralogically interesting. Large slabs of the transparent variety, called Maria-glass, found in Friedrichsrode, Germany. Fine-grained variety alabaster occurs e.g. in Italy. Fibrous variety selenite (sometimes also called satin spar) comes from the Sylva river basin, Perm, Russia.
Application: building, chemical and medical industries.

Langite

$Cu_4(SO_4)(OH)_6 . 2 H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – blue, blue-green; S – light blue; L – vitreous to silky; D – translucent; DE – 3.3; H – 2.5-3; CL – perfect; M – small isometric crystals, fine-grained crusts, earthy aggregates..
Origin and occurrence: Secondary, as a product of the oxidation of Cu ores, associated with gypsum and other minerals. Crystals known from St. Just, Cornwall, UK. Crystals occurred in Tsumeb, Namibia. Fine specimens come from Spania Dolina and L'ubietova, Slovakia and from Borovec, Czech Republic. It is also common in Ely, Nevada, USA and in El Cobre, Chile.

Langite, 49 mm, Allihies, Cork, Ireland



Fibroferrite, 70 mm, Dubnik, Slovakia



Fibroferrite

$Fe^{3+} (SO_4)(OH) . 5 H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – yellowish, greenish, gray; S – white; L – silky; D – opaque; DE – 1.9; H – 2.5; CL – perfect; M – small crystals, fibrous and botryoidal crusts; R – soluble in water.

Origin and occurrence: Secondary as a product of the pyrite oxidation, together with other sulfates. Crystals in cavities in melanterite found in the Dexter No.7 mine, Calf Mesa, Utah, USA. Vein fillings up to 3 m (10 ft) thick come from the Santa Elena mine, La Alcaparrosa, Argentina. Fine fibrous aggregates occur in Dubnik, Slovakia. It is common in many localities in Chile (Tierra Amarilla, Chuquicamata).

Aluminite

$Al_2(SO_4)(OH)_4 . 7 H_2O$

MONOCLINIC ● ● ●

Properties: C – white; S – white; L – dull; D – opaque; DE – 1.7-1.8; H – 1-2; CL – none; M – earthy nodules, consisting of microscopic needles.

Origin and occurrence: Secondary, resulting from the reaction of sulfuric acid with Al in Al-rich rocks. Large nodule, 30 cm (12 in) in diameter, known from Newhaven, Sussex, UK. Fine white nodules described from Mala Chuchle, Prague, Czech Republic. It also occurs near Halle, Germany and covers limestone in the vicinity of Joplin, Missouri, USA.

Aluminite, 60 mm, Bicske-Csordakut, Hungary



Botryogen

$MgFe^{3+} (SO_4)_2(OH) . 7 H_2O$

MONOCLINIC ● ● ●

Properties: C – orange-red; S – yellow; L – vitreous; D – transparent to translucent; DE – 2.1; H – 2-2.5; CL – perfect; F – conchoidal; M – prismatic striated crystals, racemose and spherical aggregates with radial structure.

Origin and occurrence: Secondary, as a result of the pyrite oxidation in arid regions, together with other sulfates. Crystals up to 35 mm ($1^{5}/_{16}$ in) long from the Libiola mine near Genoa, Italy. It is common in Chuquicamata and Quetena in Chile; also known from Rammelsberg, Germany.

Botryogen, 3 mm xx, Knoxville, U.S.A.




Devilline, 10 mm xx, Spania Dolina, Slovakia

Copiapite
$(Fe^{2+},Mg)Fe^{3+}{}_4(SO_4)_6(OH)_2 \cdot 20\ H_2O$

TRICLINIC ● ● ●

Properties: C – yellow, green-yellow, orange; S – yellow; L – pearly; D – transparent to translucent; DE – 2.1-2.2; H – 2.5; CL – perfect; M – thin tabular crystals, scaly and pulverulent aggregates, earthy.
Origin and occurrence: Secondary, originated from the pyrite oxidation, together with other sulfates.
Tabular crystals come from the Dexter No.7 mine, Calf Mesa, Utah, USA and also from Zeleznik , Slovakia. Fine crystals were found in many localities in Chile (Tierra Amarilla, Chuquicamata). It also occurs in Rammelsberg, Germany.


Copiapite, 96 mm, Copiapó, Chile


Serpierite, 80 mm, Příbram, Czech Republic

Devilline
$CaCu_4(SO_4)_2(OH)_6 \cdot 3\ H_2O$

MONOCLINIC ● ●

Properties: C – emerald-green; S – white to light green; L – vitreous to pearly; D – transparent to translucent; DE – 3.1; H – 2.5; CL – perfect; M – thin tabular pseudo-hexagonal crystals and coatings.
Origin and occurrence: Secondary, as a result of the oxidation of Cu sulfides, associated with other secondary Cu minerals. The world's best specimens come from Spania Dolina, Slovakia, where crystal rosettes up to 10 mm (⅜ in) in diameter were found in the past century; also known from Botallack, Cornwall, UK and Tsumeb, Namibia.

Serpierite
$Ca(Cu,Zn)_4(SO_4)_2(OH)_6 \cdot 3\ H_2O$

MONOCLINIC ● ●

Properties: C – blue; S – white; L – vitreous; D – transparent to translucent; DE – 3.1; H – 2.5; CL – perfect; M – tabular crystals, coatings.
Origin and occurrence: Secondary, originated in the oxidation zone of Cu-Zn deposits, together with smithsonite and other minerals. Its small crystals and aggregates occurred in Laurion, Greece. Recently confirmed at Příbram, Czech Republic.

Ettringite, 45 mm, Kuruman, South Africa



Ettringite

$Ca_6Al_2(SO_4)_3(OH)_{12} \cdot 26\ H_2O$

HEXAGONAL ● ●

Properties: C – colorless, yellow; S – white; L – vitreous to silky; D – transparent; DE – 1.8; H – 2.5; CL – perfect; M – prismatic crystals, fibrous aggregates.
Origin and occurrence: Metamorphic, associated with sturmanite. The world's best crystals reaching up to 100 mm (4 in) come from the N'Chwaning mine, Kuruman, South Africa. Crystals up to 4 mm (5/32 in) occurred in Franklin, New Jersey, USA. Also known from the contact metamorphic conditions in Crestmore, California, USA.

Sturmanite

$Ca_6Fe^{3+}{}_2(SO_4)_2[B(OH)_4], (OH)_{12} \cdot 25\ H_2O$

TRIGONAL ●

Properties: C – yellow, yellow-green; S – white; L – vitreous; D – transparent to translucent; DE – 1.9; H – 2.5; CL – perfect; M – flat dipyramidal crystals.
Origin and occurrence: : Probably metamorphic, associated with barite, hematite and ettringite. Crystals up to 140 mm (5½ in) long come from the N'Chwaning mine, Kuruman, South Africa.

Sturmanite, 35 mm xx, Kuruman, South Africa



Johannite

$Cu(UO_2)_2(SO_4)_2(OH)_2 \cdot 8\ H_2O$

TRICLINIC ● ●

Properties: C – green; S – light green; L – vitreous; D – transparent to translucent; DE – 3.3; H – 2-2.5; CL – good; M – prismatic to thick tabular crystals, scaly aggregates, coatings; R – radioactive.
Origin and occurrence: Secondary, as a result of the uraninite oxidation, together with other secondary U minerals. Crystals are known from Jachymov, Czech Republic and Johanngeorgenstadt, Germany. It was common with zippeite in Central City, Colorado, USA and also reported from Mounana, Gabon.

Zippeite

$K_4(UO_2)_6(SO_4)_3(OH)_{10} \cdot 4\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – orange-yellow; S – yellow; L – dull to earthy; D – opaque; DE – 3.7; H – not determined; CL – perfect; M – acicular and tabular crystals, pulverulent and acicular aggregates, coatings; LU – green; R – radioactive.
Origin and occurrence: Secondary, forming during the uraninite oxidation, associated with other secondary U minerals. Small tabular crystals come from Drmoul, Czech Republic. Coatings and

Johannite, 70 mm, Jachymov, Czech Republic



Zippeite, 40 mm, Lodeve, France



acicular aggregates are known from Jachymov, Czech Republic and Central City, Colorado, USA; also occurs in Shinkolobwe, Zaire.

Scheelite

$CaWO_4$

TETRAGONAL ● ● ● ●

Properties: C – colorless, gray-white, yellow-brown, orange, red, greenish; S – white; L – greasy to adamantine; D – translucent; DE – 6.1; H – 4.5-5; CL – good; F – conchoidal to uneven; M – pseudo-octahedral crystals, granular, massive; LU – blue-white.
Origin and occurrence: Magmatic in pegmatites, hydrothermal in greisens and metamorphic; parageneses vary significantly according to the origin. Beautiful brownish crystals up to 100 mm (4 in) in size come from Taewha and Tongwha in Korea. Similar crystals were recently found in China. Orange crystals up to 40 mm ($1\,^{9}/_{16}$ in) in size are associated with cassiterite crystals on quartz crystals from Iultin and Tenkergin, Russia. Clear crystals, weighing up to 50 kg (110 lb), occurred in pegmatites near Natas, Namibia. Crystals up to 70 mm (2¾ in) reported from several mines near Traversella, Italy. Beautiful red crystals up to 20 mm ($^{25}/_{32}$ in) were very rare in Pøibram, Czech Republic. Yellow crystals up to 40 mm ($1\,^{9}/_{16}$ in) are known from quartz veins with pumpellyite in Obøi Dsl, Czech Republic.
Application: W ore.

Scheelite, 77 mm, Sichuan, China



Stolzite, 20 mm, Arizona, U.S.A.



Stolzite

$PbWO_4$

TETRAGONAL ● ●

Properties: C – gray-brown, orange-yellow, red, green; S – colorless; L – adamantine to resinous; D – transparent to translucent; DE – 7.9-8.3; H – 2.5-3; CL – imperfect; F – conchoidal to uneven; M – dipyramidal and thick tabular, striated crystals.
Origin and occurrence: Secondary, as a product of the oxidation of primary W minerals. Crystals up to 60 mm ($2^{3}/_{8}$ in) from St Leger-de-Peyre, France. Prisms and needles up to 25 mm (1 in) long found in Broken Hill, New South Wales, Australia. Crystals up to 25 mm (1 in) also known from Tsumeb, Namibia. Crystals up to 20 mm ($^{25}/_{32}$ in) reported from Cínovec, Czech Republic and from the Black Pine mine, Montana, USA.

Ferrimolybdite, 60 mm, Hurky, Czech Republic



Crocoite, 44 mm, Dundas, Australia



Crocoite

$PbCrO_4$

MONOCLINIC ● ●

Properties: C – orange, red; S – orange-yellow; L – adamantine to greasy; D – translucent; DE – 6; H – 3; CL – good; F – conchoidal to uneven; M – long prismatic to acicular crystals, crusts..
Origin and occurrence: Secondary, as a result of the galena oxidation in basic rocks. The world' best specimens come from the Dundas district, Tasmania, Australia where crystals up to 100 mm (4 in) long were found in several mines. Fine crystals up to 40 mm ($1^{9}/_{16}$ in) long are known from Berezovsk, Ural mountains, Russia. Crystals up to 20 mm ($^{25}/_{32}$ in) were recently found in Callenberg, Germany.

Betpakdalite, 70 mm, Bayan Tsogdo, Mongolia



Ferrimolybdite

$Fe_2(MoO_4)_3 . 8 H_2O$

ORTHORHOMBIC ● ●

Properties: C – yellow, whitish; S – light yellow; L – adamantine, silky, earthy; D – opaque; DE – 4.4; H – 1-2; M – small acicular crystals, fibrous and radial aggregates, earthy.
Origin and occurrence: Secondary, as a product of the molybdenite oxidation. Microscopic crystals were found in Glen Innes, New South Wales, Australia. It occurred as yellow coatings in Climax and Telluride, Colorado, in the Getchell mine, Nevada, USA; also in Hsrky near Eista, Czech Republic.

Betpakdalite

$CaFe^{3+}H_8(MoO_4)_5(AsO_4)_2 . 8 H_2O$

MONOCLINIC ●

Properties: C – lemon-yellow; S – yellow; L – vitreous, waxy, dull; D – opaque; DE – 3; H – 3; CL – good; M – short prismatic microscopic crystals, pulverulent.
Origin and occurrence: Secondary mineral. Originally described from Kara-Oba, Kazakhstan. It also occurred in Tsumeb, Namibia and in Krupka, Czech Republic.

Wulfenite

$PbMoO_4$

TETRAGONAL ● ● ●

Properties: C – yellow, orange, brownish, red, greenish; S – white; L – greasy to adamantine; D – transparent to translucent; DE – 6.3-7; H – 3; CL – good; F – uneven to conchoidal; M – thin tabular and dipyramidal crystals, granular, massive.
Origin and occurrence: Secondary, as a result of the galena oxidation, together with cerussite, vanadinite and other minerals. The best specimens are known from the Red Cloud mine near Yuma, Arizona, where red tabular crystals found up to 50 mm (2 in) diameter. Yellow-brown crystals up to 100 mm (4 in) come from the Glove mine, Arizona, USA. Thick tabular orange crystals up to 20 mm ($^{25}/_{32}$ in) in diameter found in the Erupcion mine, Villa Ahumada, Los Lamentos, Chihuahua. Beautiful yellow plates up to 60 mm (2$^{3}/_{8}$ in) with orange mimetite spheres occurred in the San Francisco mine, Magdalena, Sonora, Mexico. Rare tabular crystals up to 70 mm (2¾ in) across come from Tsumeb, Namibia. Fine orange-yellow tabular crystals up to 20 mm ($^{25}/_{32}$ in) across, and pyramidal crystals are known from Bleiberg, Austria and Mežica , Slovenia. Crystals up to 100 mm (4 in) were found recently in Touissit, Morocco.

Wulfenite, 38 mm, Los Lamentos, Mexico



8. Phosphates

Lithiophosphate

Li_3PO_4

ORTHORHOMBIC ●

Properties: C – colorless, white, pinkish; S – white; L – vitreous; D – transparent to translucent; DE – 2.5; H – 4; CL – perfect; F – uneven; M – prismatic crystals, granular.
Origin and occurrence: Hydrothermal in granitic pegmatites, where it forms by replacement of spodumene and montebrasite. Cleavable aggregates up to 100 mm (4in) across occur in the Tanco Mine, Bernic Lake, Manitoba, Canada; crystals up to 25 mm (1 in) across in the Foote mine, Kings Mountain, North Carolina, USA.

Beryllonit

$NaBePO_4$

MONOCLINIC ● ●

Properties: C – colorless, white, yellowish; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 5.5-6; CL – perfect; F – uneven; M – short prismatic to tabular crystals, granular.
Origin and occurrence: Hydrothermal in cavities in granitic pegmatites where it is associated with herderite, albite and tourmaline. Crystals and their twins, up to 150 mm (6 in) across come from Stoneham and Newry, Maine, USA; also from Viitaniemi, Finland and Paprok, Afghanistan.

Adamite, 52 mm, Mapimi, Mexico
Lithiophosphate, 30 mm, Tanco, Canada



Beryllonite, 31 mm, Paprok, Afghanistan



Triphyllite

$LiFePO_4$

ORTHORHOMBIC ● ● ●

Properties: C – gray-green, gray-blue, gray, brown; S – gray-white; L – greasy to vitreous; D – transparent to translucent; DE – 3.4; H – 4-5; CL – good; F – uneven; M B short prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites, associated with graftonite, sarcopside and many secondary phosphates. Large triphyllite crystals up to 1.5 m (5 ft) across are known from Hagendorf, Germany; from the Tip Top mine, Custer, South Dakota and Palermo No. 1 mine, North Groton, New Hampshire, USA; also from Hühnerkobel, Germany.

Triphylite, 70 mm, Hagendorf, Germany





Lithiophilite, 120 mm, Viitaniemi, Finnland

Lithiofilit

$LiMnPO_4$

ORTHORHOMBIC ● ●

Properties: C – pink, red-brown, brown; S – white; L – vitreous; D – transparent to translucent; DE – 3.3; H – 4-5; CL – good; F – uneven; M – short prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites. It is sometimes associated with triplite and triphyllite, typically replaced by many secondary phosphates. Large masses of lithiophillite, reaching up to 1 m (39⅜ in), occur in Karibib, Namibia; Kitumbe, Rwanda. Other localities are Mangualde, Portugal; Tanco mine, Bernic Lake, Manitoba, Canada; Stewart Lithia Mine, Pala, California, USA.



Purpurite, 40 mm, Usakos, Namibia



Berzeliite, 120 mm, Langban, Sweden

Purpurite

$Mn^{3+}PO_4$

ORTHORHOMBIC ● ●

Properties: C – pink, purple, dark brown; S B red-purple; L – dull to velvet; D – translucent to opaque; DE – 3.7; H – 4-4.5; CL – good; F – uneven; M B granular, massive.
Origin and occurrence: Hydrothermal, as a product of lithiophillite replacement in granitic pegmatites. It is usually associated with many secondary phosphates. It is known from Kitumbe, Rwanda; Usakos and Sandamab, Namibia; the Tip Top and Bull Moose mines, Custer, South Dakota and Branchville, Connecticut, USA.

Berzeliite

$(Ca,Na)_3 (Mg,Mn)_2 (AsO_4)_3$

CUBIC ● ●

Properties: C – yellow, orange; S – red-purple; L – resinous; D – transparent to translucent; DE – 4.1; H – 4-4.5; CL – none; F – conchoidal to uneven; M – isometric crystals, granular, massive.
Origin and occurrence: Metamorphic, together with haussmanite, rhodonite and tephroite. It occurs as massive in Langban and Nordmark, Sweden.

Whitlockite

$Ca_9(Mg,Fe)H(PO_4)_7$

TRIGONAL ● ●

Properties: C – colorless, white, yellowish, pinkish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 5; CL – none; F – conchoidal to uneven; M – rhombohedral crystals, granular, massive.

Origin and occurrence: Hydrothermal, as a product of replacement of primary phosphates in granitic pegmatites, rare in sedimentary rocks – phosphorites: very rare magmatic in meteorites. Mainly associated with apatite and carbonates. Imperfect crystals around 10 mm (3/8 in) across, occur in the Palermo No. 1 mine, North Groton, New Hampshire; also in the Tip Top mine, Custer, South Dakota, USA.

Whitlockite, 10 mm xx, New Hampshire, U.S.A.



Xenotime-(Y)

YPO_4

TETRAGONAL ● ● ●

Properties: C – brown, yellow, gray, greenish; S – white; L – vitreous to resinous; D – transparent, translucent to opaque; DE – 4.5; H – 4.5; CL – good; F – conchoidal to uneven; M – long prismatic to tabular crystals, granular; R – sometimes weakly radioactive and metamict.

Origin and occurrence: Magmatic in granitic and alkaline pegmatites, granites and syenites; hydrothermal in the Alpine-type veins; metamorphic in gneisses; common in placers. It is associated with monazite-(Ce) and zircon. Perfect prismatic crystals up to 100 mm (4in) across occur mainly in pegmatites in Kragero and Hitterö, Norway; Ytterby, Sweden; in several places in Madagascar; in Ichikawa, Japan. Crystals about 20 mm (25/32 in) are known from the Alpine-type veins in Binntal, Switzerland.

Application: ore of rare earth elements.

Xenotime-(Y), 14 mm x, Washington Co., U.S.A.



Monazite-(Ce)

$CePO_4$

MONOCLINIC ● ● ●

Properties: C – yellow, brown, red-brown, orange, gray-green; S – white; L – vitreous to resinous; D – transparent, translucent to opaque; DE – 4.6; H – 5-5.5; CL – good; F – conchoidal to uneven; M – long prismatic to tabular crystals, granular; R – sometimes weakly radioactive and metamict.
Origin and occurrence: Magmatic in granitic and alkaline pegmatites, granites, syenites, carbonatites; hydrothermal in the Alpine-type veins and greisens; metamorphic in gneisses; common in placers.
It is associated with apatite, xenotime-(Y) and zircon. Perfect prismatic crystals up to 200 mm ($7\frac{7}{8}$ in) come from Mars Hill, North Carolina, Trout Creek Pass, Colorado, USA; also from Arendal, Norway; Ambatofotsikely and Ampangabe, Madagascar, where masses weighing several kg are common; crystals, up to 200 mm ($7\frac{7}{8}$ in) across found in Minas Gerais, Jaguaraçu, Brazil.
Application: ore of rare earth elements.



Monazite-(Ce), 31 mm, Felicio, Brazil

Hydroxylherderite

$CaBe(PO_4)(OH,F)$

MONOCLINIC ● ●

Properties: C – colorless, white, yellowish, greenish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 5-5.5; CL – good; F – conchoidal to uneven; M – prismatic to tabular crystals, radial aggregates, granular.
Origin and occurrence: Hydrothermal in cavities in granitic pegmatites and in greisens. Perfect crystals, up to 120 mm ($4\frac{11}{16}$ in) long come from Marilaca and together with colored tourmalines from Virgem da Lapa, Minas Gerais, Brazil; also known from Topsham and Stoneham, Maine, USA.

Amblygonite

$LiAl(PO_4)(F,OH)$

TRICLINIC ● ● ●

Properties: C – colorless, white, yellowish, bluish, gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 5.5-6; CL – good; F – conchoidal to uneven; M – short prismatic crystals, granular, massive.



Hydroxylherderite, 22 mm, Anza, California, U.S.A.

Montebrasite, 80 mm, White Picacho, Arizona, U.S.A.



Origin and occurrence: Magmatic in granitic pegmatites and some granites; rare hydrothermal in greisens and in ore veins. Large amblygonite masses, several meters across, come from pegmatites, like the Beecher, Custer and Hugo mines, Keystone, South Dakota, USA, where its blocks weighed up to 200 tons; also known from Viitaniemi, Finland; Uto, Sweden. Typical representative of the quartz-amblygonite veins is Vernerov, Czech Republic.
Application: Li ore and raw material for ceramics.

Montebrasite
LiAl(PO$_4$)(OH,F)

TRICLINIC ● ● ●

Properties: C – colorless, white, yellowish, yellow, bluish, gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 5.5-6; CL – good; F – conchoidal to uneven; M – short prismatic to tabular crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites and granites; hydrothermal in granitic pegmatites. It occurs very frequently with amblygonite, which it replaces. Large masses are known from Montebras, France; also from the Tin Mountain mine, Custer, South Dakota, USA.. Perfect tabular crystals up to 150 mm (6 in) across found in Taquaral, Minas Gerais, Brazil.

Wagnerite
Mg$_2$(PO$_4$)(F,OH)

MONOCLINIC ● ● ●

Properties: C – light yellow, yellow-green, yellow-brown, green; S – white; L – vitreous to greasy; D – transparent, translucent to opaque; DE – 3.2; H – 5-5.5; CL – imperfect; F – conchoidal to uneven; M – short prismatic crystals, granular, massive.

Wagnerite, 18 mm x, Werfen, Austria



Origin and occurrence: Magmatic in granitic pegmatites; metamorphic in gneisses and eclogites; hydrothermal in quartz veins and in salt deposits. The most famous finds come from the quartz veins in Hollgraben and Radelgraben, the Alps, Austria, where wagnerite occur together with lazulite and forms crystals up to 30 mm ($1^{3}/_{16}$ in) across; also known from Mangualde, Portugal and Bodenmais, Germany.

Amblygonite, 55 mm, Minas Gerais, Brazil



Zwieselite, 30 mm grain, Dolni Bory, Czech Republic



Zwieselite

$Fe_2(PO_4)(F,OH)$

MONOCLINIC ● ● ●

Properties: C – dark brown to black-brown; S – light brown; L – vitreous to greasy; D – translucent to opaque; DE – 4.0; H – 5-5.5; CL – imperfect; F – conchoidal to uneven; M – short prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites; rare hydrothermal in greisens. It is associated with apatite, triplite and secondary phosphates. Imperfect crystals and granular aggregates are known from pegmatites near Zwiesel, Germany; Dolni Bory, Czech Republic.

Libethenite, 80 mm, L'ubietova, Slovakia



Triplite, 70 mm, Viitaniemi, Finnland



Triplite

$Mn_2(PO_4)(F,OH)$

MONOCLINIC ● ● ●

Properties: C – pink, light brown; S – light brown; L – vitreous to greasy; D – translucent to opaque; DE – 3.8; H – 5-5.5; CL – imperfect; F – conchoidal to uneven; M – short prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites and granites; hydrothermal in greisens and in quartz veins. It is usually hydrothermally altered and replaced by secondary phosphates. Huge masses several meters in size come from pegmatites in Karibib, Namibia; it also occurs in Mangualde, Portugal and in Sukula, Finland.

Libethenit

$Cu_2(PO_4)(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – black-green to light green; S – olive-green; L – greasy; D – translucent; DE – 3.9; H – 4; CL – imperfect; F – conchoidal to uneven; M – short prismatic and dipyramidal crystals, botryoidal aggregates, granular, massive.
Origin and occurrence: Secondary in Cu deposits, where it occurs together with malachite, pseudomalachite and brochantite. Perfect crystals, up to 30 mm ($1\,^{3}/_{16}$ in) across, come from the Rokana mine, Zambia; crystals, up to 10 mm ($^{3}/_{8}$ in), are known from Kambove, Zaire; L'ubietova . Slovakia; Nizhniy Tagil, Ural Mts., Russia.

Olivenite, 80 mm, Tsumeb, Namibia



Olivenite

$Cu_2(AsO_4)(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – olive-green, green-brown, gray-green to gray; S – light green; L – greasy; D – translucent to opaque; DE – 4.4; H – 3; CL – imperfect; F – conchoidal to uneven; M – long to short prismatic and dipyramidal crystals, acicular and radial aggregates, massive.

Origin and occurrence: Secondary in Cu deposits. It is associated with other secondary Cu minerals, malachite, azurite and scorodite. Perfect crystals up to 10 mm (⅜ in) across occurred in Wheal Gorland, Cornwall, and Tavistock, Devon UK; also in Tsumeb, Namibia and Ashburton Downs, Western Australia, Australia.

Adamine

$Zn_2(AsO_4)(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – yellow-green, yellow, green, colorless, purple; S – white; L – vitreous; D – transparent to translucent; DE – 4.4; H – 3.5; CL – imperfect; F – conchoidal to uneven; M – long to short prismatic and dipyramidal crystals, acicular and radial aggregates, massive; LU – yellow-green.

Origin and occurrence: Secondary in Zn deposits, associated with hemimorphite, goethitee and smithsonite. Rich druses of green and rare purple crystals up to 70 mm (2¾ in) across come from Mina Ojuela, Mapimi, Durango, Mexico; also known from Tsumeb, Namibia; Laurion, Greece and Cap Garonne, France.

Adamite, 34 mm, Mapimi, Mexico



Lazulite, 11 mm x, Lincoln Co., U.S.A.



Lazulite

$MgAl_2(PO_4)_2(OH)_2$

MONOCLINIC ● ● ●

Properties: C – dark to light blue, blue-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.1; H – 5.5-6; CL – imperfect; F – conchoidal to uneven; M – short prismatic and dipyramidal crystals, granular, massive.
Origin and occurrence: Hydrothermal in quartz veins and granitic pegmatites, where it is formed by decomposition of primary phosphates; metamorphic in quartzites.
Imperfect crystals up to 100 mm (4 in) across come from Horrsjoberg, Sweden; perfect crystals about 50 mm found in Ashudi, Pakistan; also known from Big Fish River, Yukon, Canada and near Werfen, Austria.

Scorzalite

$FeAl_2(PO_4)_2(OH)_2$

MONOCLINIC ● ● ●

Properties: C – dark blue, blue-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.3; H – 6; CL – imperfect; F – conchoidal to uneven; M – prismatic crystals, granular, massive.
Origin and occurrence: Hydrothermal in granitic pegmatites, as a replacement product of primary phosphates, rare in quartz veins. Dark blue, granular aggregates up to 100 mm (4in) across occur in the Palermo No. 1 and No. 2 mines, North Groton, New Hampshire and the Victory mine, Custer, South Dakota, USA.

Rockbridgeite

$Fe^{2+}Fe^{3+}{}_4(PO_4)_3(OH)_5$

ORTHORHOMBIC ● ● ●

Properties: C – dark and light green, black-green; S – green; L – dull; D – translucent to opaque; DE – 3.4; H – 4.5; CL – good; F – uneven; M – acicular crystals, radial aggregates and crusts, granular, massive.
Origin and occurrence: Secondary in granitic pegmatites and in Fe deposits. It mostly originates from the hydrothermal alteration of primary phosphates, mainly triphyllite, and it is associated with other secondary phosphates. Rich radial aggregates up to 50 mm (2 in) across come from Hagendorf, Germany; the Tip Top mine, Custer, South Dakota and the Fletcher mine, Groton, New Hampshire, USA.

Scorzalite, 80 mm, Palermo No.2 Mine, U.S.A.



Rockbridgeite, 70 mm, Hagendorf, Germany



Frondelite, 15 mm xx, Custer, U.S.A.



Frondelite

$MnFe^{3+}_4(PO_4)_3(OH)_5$

ORTHORHOMBIC ● ● ●

Properties: C – light olive-green, brown, black-green; S – green; L – dull; D – translucent to opaque; DE – 3.5; H – 4.5; CL – good; F – uneven; M – acicular crystals, radial aggregates and crusts, granular, massive.

Origin and occurrence: Secondary in granitic pegmatites, where it forms as a result of the hydrothermal alteration of primary phosphates, mainly lithiophillite. Radial aggregates occur in the Fletcher mine, Groton, New Hampshire, USA; also in Sapucaia, Minas Gerais, Brazil.

Dufrenite

$Fe^{2+}Fe^{3+}_4(PO_4)_3(OH)_5 \cdot 2\,H_2O$

MONOCLINIC ● ● ●

Properties: C – dark green, black-green, black; S – green; L – vitreous to dull; D – translucent to opaque; DE – 3.4; H – 3.5-4.5; CL – good; F – uneven; M – radial aggregates and crusts, granular, massive.

Origin and occurrence: Secondary in granitic pegmatites and in the oxidation zone of Fe deposits: it forms in pegmatites as a result of the hydrothermal alteration of primary phosphates. Radial aggregates occur in pegmatites in Hagendorf and Hühnerkobel, Germany; also in gossan in the Wheal Phoenix mine, Cornwall, UK.

Dufrenite, 9 mm, Lancaster, U.S.A.



Pseudomalachite

$Cu_5(PO_4)_2(OH)_4$

MONOCLINIC ● ● ●

Properties: C – green, black-green; S – green; L – vitreous to dull; D – translucent to opaque; DE – 4.3; H – 4.5-5; CL – good; F – uneven; M – short prismatic crystals, botryoidal aggregates with radial structure, massive.

Origin and occurrence: Secondary in Cu deposits, associated with malachite, chrysocolla, libethenite and goethite. Beautiful botryoidal aggregates and large masses come from Nizhniy Tagil, Ural mountains, Russia; also from Ehl and Virneberg, Germany; from L'ubietova , Slovakia; and also from many localities in Shaba province, Zaire.

Pseudomalachite, 80 mm, L'ubietova, Slovakia



Cornubite, 30 mm, Farbiste, Slovakia



Cornubite

$Cu_5(AsO_4)_2(OH)_4$

TRICLINIC ●

Properties: C – light to dark green; S – light green; L – vitreous to dull; D – translucent; DE – 4.8; H – not determined; CL – not determined; F – uneven; M – botryoidal aggregates, massive.
Origin and occurrence: Secondary in Cu deposits. It was found together with olivenite and clinoclase in the Bedford United quarry, Cornwall, UK; also in Ashburton Downs, Western Australia, Australia and Farbiste, Slovakia.

Cornetite, 10 mm aggregate, Lumumbashi, Zair



Augelite, 34 mm, Yukon Territory, Canada



Augelite

$Al_2(PO_4)(OH)_3$

MONOCLINIC ● ● ●

Properties: C – colorless, white, yellowish, pinkish; S- white; L – vitreous to dull; D – transparent to translucent; DE – 2.7; H- 4.5-5; CL – good; F – uneven; M – thick tabular to prismatic crystals, granular, massive.
Origin and occurrence: Hydrothermal in granitic pegmatites as a product of primary phosphates replacement; rare metamorphic in quartzites. Massive aggregates several decimeters across occur in pegmatites in Burango, Rwanda; also in the Hugo mine, Custer, South Dakota and Mount White, California, USA. Crystals up to 20 mm ($^{25}/_{32}$ in) across come from Rapid Creek, Yukon, Canada and from the Champion mine, California; rare small crystals found in the Palermo No. 1 mine, North Groton, New Hampshire, USA.

Cornetite

$Cu_3(PO_4)(OH)_3$

ORTHORHOMBIC ●

Properties: C – dark blue to blue-green; S – light blue; L – vitreous; D – transparent to translucent; DE – 4.1; H – 4.5; CL – none; F – conchoidal to uneven; M – short prismatic crystals, coatings.
Origin and occurrence: Secondary in Cu deposits. It is rare in the Etoile mine near Lumumbashi and in Kalagi, Shaba province, Zaire; also occurs in Yerington, Nevada and in Saginaw Hill, Arizona, USA.

Clinoclase, 40 mm, Cornwall, UK



Clinoclase

$Cu_3(AsO_4)(OH)_3$

MONOCLINIC ● ●

Properties: C – dark green-blue to black-green; S – blue-green; L – vitreous; D – transparent to translucent; DE – 4.4; H – 2.5-3; CL – perfect; F – uneven; M – prismatic and tabular crystals, botryoidal aggregates.
Origin and occurrence: Secondary in Cu deposits, often associated with malachite, azurite and other secondary Cu minerals. Spherical aggregates up to 10 mm (⅜ in) known from the Majuba Hill mine, Nevada, USA; occurs rarely near Tavistock, Devon, UK; also in Novoveska Huta, Slovakia.

Conichalcite

$CuCa(AsO_4)(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – yellow-green to emerald-green; S – light green; L – vitreous to greasy; D – transparent to translucent; DE – 4.3; H – 4.5; CL – none; F – uneven; M – short prismatic crystals, botryoidal aggregates with radial structure, massive.
Origin and occurrence: Secondary in Cu deposits. It occurs as rich botryoidal aggregates in Otavi, Namibia; Tintic, Utah, in the Higgins mine, Bisbee, Arizona and Yerington, Nevada, USA.

Conichalcite, 70 mm, Tintic, U.S.A.



Duftite

$PbCu(AsO_4)(OH)$

ORTHORHOMBIC ● ●

Properties: C – yellow-green, olive-green to gray-green; S – light green; L – vitreous to greasy; D – translucent; DE – 6.5; H – 3; CL – not determined; F – uneven; M – small crystals, botryoidal aggregates and coatings.
Origin and occurrence: Secondary in base metals deposits. It is associated with malachite and azurite in Tsumeb, Namibia; in Mina Ojuela, Mapimi, Durango, Mexico; in Moldava, Czech Republic.

Duftite, 90 mm, Tsumeb, Namibia



Descloizite, 38 mm, Grootfontein, Namibia



Descloizite

$PbZn(VO_4)(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – red-orange, red-brown to brown-black, gray-green; S – light yellow-brown; L – greasy; D – transparent, translucent to opaque; DE – 6.1; H – 3-3.5; CL – none; F – conchoidal to uneven; M – crystals of different habits, mostly pyramidal or prismatic, botryoidal and skeletal aggregates, massive.

Origin and occurrence: Secondary in base metals deposits. It is mainly associated with pyromorphite, mimetite, vanadinite and other secondary Pb minerals. Occurs as crystals up to 30 mm ($1\frac{3}{16}$ in) long in Tsumeb and Berg Aukas, Namibia; also Broken Hill, Zambia; and the Mammoth mine, Tiger, Arizona, USA.

Arsendescloizite

$PbZn(AsO_4)(OH)$

ORTHORHOMBIC ●

Properties: C – light yellow; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 6.1; H – 4; CL – none; F – conchoidal to uneven; M – tabular crystals, rosette-like aggregates.

Arsendescloizite, 95 mm, Mapimi, Mexico



Origin and occurrence: Secondary in base metals deposits, associated with mimetite and goethite. Found rarely as crystals of 1 mm (1/32 in) in size in Tsumeb, Namibia; also Mina Ojuela, Mapimi, Durango, Mexico.

Mottramite

$PbCu(AsO_4)(OH)$

ORTHORHOMBIC ● ●

Properties: C – grass-green to black-green; S – light green; L – vitreous to dull; D – transparent to opaque; DE – 5.9; H – 3-3.5; CL – none; F – conchoidal to uneven; M – crystals of different habits, botryoidal and dendritic aggregates, crusts and coatings, massive.
Origin and occurrence: Secondary in base metals deposits, associated with mimetite, descloizite and vanadinite. It occurs in Mottram, Cheshire, UK; in Tsumeb, Namibia; Mammoth mine, Tiger, Arizona, USA.

Brazilianite

$NaAl_3(PO_4)_2(OH)_4$

MONOCLINIC ● ● ●

Properties: C – colorless, white, yellowish, yellow-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.0; H – 5.5; CL – good; F – uneven; M – short prismatic to isometric crystals, radial aggregates, granular.
Origin and occurrence: Hydrothermal in cavities in granitic pegmatites, where it is associated with fluorapatite, albite and tourmaline. It occasionally originates as a product of amblygonite replacement. Perfect yellow-green crystals up to 150 mm (6 in) across found in cavities in pegmatites in Conselheira Pena and Corrego Frio, Linopolis, Minas Gerais and from Pietras Lavradas, Paraiba, Brazil.

Mottramite, 60 mm, Tiger, Arizona, U.S.A.

Cafarsite, 9 mm x, Binntal, Switzerland

Cafarsite

$Ca_8(Ti,Fe^{2+},Fe^{3+},Mn)(As^{3+}O_3)_{12} \cdot 4\ H_2O$

CUBIC ●

Properties: C – dark brown; S – yellow-brown; L – submetallic; D – translucent; DE – 3.9; H – 5.5-6; CL – none; F – conchoidal; M – isometric crystals.
Origin and occurrence: Hydrothermal along cracks in Alpine-type veins. Cubic crystals up to 30 mm (1 1/16 in) across come from Binntal, Switzerland and Pizzo Cervandone, Italy.

Brazilianite, 47 mm, Conselheira Pena, Brazil

Carminite

$PbFe^{3+}_2(AsO_4)_2(OH)_2$

ORTHORHOMBIC ● ●

Properties: C – crimson-red, red-brown; S – red-yellow; L – adamantine to pearly; D – translucent; DE – 5.5; H – 3.5; CL – good; F – conchoidal to uneven; M – prismatic crystals, acicular, radial, felt-like to porous aggregates, coatings and crusts.
Origin and occurrence: Secondary in base metals deposits, associated with mimetite and scorodite. Crystals up to 10 mm (3/8 in) across occur in Tsumeb, Namibia; in Mina Ojuela, Mapimi, Durango, Mexico; in Calstock, Cornwall, UK.

Carminite, 2 mm xx, Nadap, Hungary



Bayldonite, 34 mm, Tsumeb, Namibia



Bayldonite

$PbCu_3(AsO_4)_2(OH)_2 \cdot H_2O$

MONOCLINIC ● ●

Properties: C – yellow-green, olive-green; S – light green; L – resinous; D – translucent; DE – 5.5; H – 4.5; CL – not determined; F – uneven; M – earthy aggregates, coatings, massive.
Origin and occurrence: Secondary in the oxidation zone in hydrothermal Cu deposits and in greisens. It occurs as common yellow-green coatings and crystals up to 10 mm (3/8 in) across, associated with large azurite and mimetite crystals in Tsumeb, Namibia; also as coatings in St. Day, Cornwall, UK; in Moldava, Czech Republic.

Vesignieite

$BaCu_3(VO_4)_2(OH)_2$

MONOCLINIC ● ●

Properties: C – yellow-green, olive-green; S – light yellow-green; L – vitreous to dull; D – translucent;

Vesigneite, 80 mm, Vrancice, Czech Republic



DE – 4.1; H – 3-4; CL – good; F – uneven; M – earthy and pulverulent aggregates and coatings, massive.

Origin and occurrence: Secondary in base metals deposits and in sediments, containing Cu sulfides. It occurs as yellow-green coatings in sediments in Horni Kalna, Czech Republic; also in the Mashamba West mine, Zaire; together with barite and psilomelane in Friedrichsroda, Germany.

Arsentsumebite

$Pb_2Cu(AsO_4)(SO_4)(OH)$

MONOCLINIC ●

Properties: C – bluish-green to light green; S – light green; L – dull; D – translucent; DE – 6.5; H – 3; CL – good; F – uneven; M – earthy aggregates, coatings, massive.

Origin and occurrence: Secondary in the oxidation zone, where it forms as a result of mimetite replacement. Found rarely in Moldava, Czech Republic; in Tsumeb, Namibia, where it forms pseudo-morphs after azurite crystals.

Arsentsumebite, 40 mm, Moldava, Czech Republic



Fluorapatite. 50 mm. Dusso. Pakistan



Fluorapatite

$Ca_5(PO_4)_3F$

HEXAGONAL ● ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish, blue, purple, green, brown with various hues; S – white; L – vitreous to dull; D – transparent to translucent, sometimes opaque; DE – 3.2; H – 5; CL – imperfect; F – conchoidal to uneven; M – long prismatic to tabular crystals, botryoidal, earthy and fibrous aggregates, massive; LU – yellow.

Origin and occurrence: Magmatic in granites, syenites, diorites, gabbros and various types of pegmatites, also in volcanic rocks; hydrothermal in quartz veins, ore veins, greisens and Alpine-type veins; metamorphic in different types of gneisses, migmatites, mica schists, skarns and amphibolites; in different types of sedimentary rocks. Perfect, short prismatic, purple transparent crystals up to 40 x 40 mm ($1\frac{9}{16}$ x $1\frac{9}{16}$ in) are renowned from pegmatite in the Pulsifer quarry, Mount Apatite, Auburn, Maine, USA; pink crystals from Dusso, Pakistan. Perfect crystals about 100 mm (4in) across also from Alpine-type veins, e.g. in Fiesch, Switzerland; also known from the quartz veins in greisens, associated with wolframite, in Panasqueira, Portugal; in Horni Slavkov, Czech Republic; Ehrenfriedersdorf, Germany. Also found in skarns at Cerro de Mercado, Durango, Mexico. Large deposits of mas-

Chlorapatite. 20 mm x. Bob's Lake. Ontario. Canada

sive apatite located in Kola Peninsula, Russia; crystals weighing up to 300 kg (660 lb) from the vicinity of Clear Lake, Ontario, Canada.
Application: main source of P, chemical industry, fertilizer.

Chlorapatite

$Ca_5(PO_4)_3Cl$

HEXAGONAL ● ● ●

Properties: C – white, various hues of yellow; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 5; CL – imperfect; F – conchoidal to uneven; M – long prismatic to tabular crystals, granular.
Origin and occurrence: Magmatic in nepheline syenites and their pegmatites, some gabbros and volcanic rocks, also in meteorites; metamorphic in skarns. It is usually associated with scapolite, amphibole, titanite and magnetite. Perfect prismatic crystals up to 35 cm ($13^{13}/_{16}$ in) long, come from pegmatites in Bamle, Norway; also from Kurokura, Japan.

Hydroxylapatite

$Ca_5(PO_4)_3(OH)$

HEXAGONAL ● ● ●

Properties: C – white, yellow, various hues of gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 5; CL – imperfect; F – conchoidal to uneven; M – short prismatic to tabular crystals, acicular aggregates, granular.
Origin and occurrence: Metamorphic in talc schists and serpentinites; hydrothermal in granitic pegmatites; sedimentary in organic remnants. Crystals up to 30 mm ($1^{3}/_{16}$ in) across known from Snarum, Norway; Hospental, Switzerland; Eagle, Colorado, USA.

Carbonate-fluorapatite

$Ca_5(PO_4, CO_3)_3F$

HEXAGONAL ● ● ●

Properties: C – white, gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 5; CL – imperfect; F – conchoidal to uneven; M B spherical and botryoidal aggregates, massive.
Origin and occurrence: Hydrothermal in ore veins and along the cracks in volcanic rocks. Rich botryoidal aggregates are known together with hyalite opal from Valec, Czech Republic; the Wheal Franco mine, Tavistock, Devon, UK.

Hydroxylapatite, 2 mm xx, Tornaszentandrás, Hungary



Carbonate-fluorapatite, 80 mm, Staffel, Germany



Pyromorphite, 41 mm, Les Farges, France



Pyromorfite

$Pb_5(PO_4)_3Cl$

HEXAGONAL ● ● ● ●

Properties: C – green, brown, yellow, orange, white, gray; S -white; L – adamantine to greasy; D – transparent to translucent; DE – 7.1; H – 3.5-4; CL – imperfect; F – conchoidal to uneven; M – long prismatic to tabular and pyramidal crystals, botryoidal aggregates with radial structure, acicular and earthy aggregates, massive.

Origin and occurrence: Secondary in the oxidation zone of Pb deposit, associated with cerussite, goethitee and other secondary minerals. Perfect crystals up to 40 mm ($1\frac{9}{16}$ in) long come from many localities, e.g. green and brown ones from Bad Ems and Zschopau, Germany; yellow-brown ones from Les Farges, France; green, brown and yellow ones from Mina Ojuela, Mapimi, Durango, Mexico. Green, orange and brown crystals, up to 60 mm ($2\frac{3}{8}$ in) long, are known from the Bunker Hill mine, Idaho, USA.

Pyromorphite, 62 mm, Les Farges, France



Mimetite, 14 mm x, Johanngeorgenstadt, Germany



Mimetite

$Pb_5(AsO_4)_3Cl$

HEXAGONAL ● ● ●

Varieties: campylite

Properties: C – yellow, orange, brown, yellow-brown, white, gray; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 7.3; H – 3.5-4; CL – imperfect; F – conchoidal to uneven; M – long to short prismatic and pyramidal crystals, botryoidal aggregates with radial structure, acicular and earthy aggregates, granular.
Origin and occurrence: Secondary in Pb deposits, associated with pyromorphite and goethite. Perfect crystals up to 20 mm ($\tfrac{25}{32}$ in) long come from Johanngeorgenstadt, Germany; campylite occurs in Drygill, UK; crystals up to 50 mm (2 in) across found in Tsumeb, Namibia; Santa Eulalia and San Pedro, Chihuahua, Mexico. Beautiful yellow crystals up to 30 mm ($1\tfrac{3}{16}$ in) found recently in Hat Yai province, Thailand.

Vanadinite

$Pb_5(VO_4)_3Cl$

HEXAGONAL ● ● ●

Properties: C – yellow, orange, red, brown, yellow-brown; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 6.9; H – 2.5-3; CL – none; F – conchoidal to uneven; M – long to short prismatic and pyramidal crystals, botryoidal aggregates with radial structure, acicular and earthy aggregates, granular.
Origin and occurrence: Secondary in Pb deposits, associate with pyromorphite, wulfenite and goethite. Perfect crystals up to 130 mm ($5\tfrac{3}{16}$ in) long come from Djebel Mahseur and Mibladen, Morocco. Prismatic crystals were also found in Tsumeb, Namibia; in the Old Yuma, Red Cloud, Apache and Mammoth mines, Arizona, USA.

Vanadinite, 64 mm, Mibladen, Morocco



Atelestite, 70 mm, Schneeberg, Germany



Atelestite

$Bi_2(AsO_4)O(OH)$

MONOCLINIC ●

Properties: C – yellow, yellow-green; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 7.0; H – 4.5-5; CL – imperfect; F – conchoidal to uneven; M – small tabular crystals, spherical aggregates.
Origin and occurrence: Secondary in the oxidation zone of Bi deposits. It was found in Schneeberg, Germany.

Hureaulite

$Mn_5(PO_4)_2[PO_3(OH)]_2 \cdot 4\ H_2O$

MONOCLINIC ● ● ●

Properties: C – orange-red, pink, purplish, white, gray; S – white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 3.5; CL – good; F – uneven; M – prismatic to tabular crystals, coatings, granular, massive.

Origin and occurrence: Secondary in granitic pegmatites, as a result of alteration of the primary phosphates, mostly lithiophillite, triphyllite and graftonite. Purplish crystals up to 50 mm (2 in) across come from Shingus, Pakistan. Similar crystals found in Hagendorf, Germany. Also known from Mangualde, Portugal; Sao Jose da Safira, Minas Gerais, Brazil; from the Tip Top mine, Custer, South Dakota, USA.

Hureaulite, 53 mm, Shingus, Pakistan



Variscite, 30 mm, Fairfield, U.S.A.



Variscite

$Al(PO_4) \cdot 2\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, greenish, blue-green; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 3.5-4.5; CL – good; F – uneven; M – isometric crystals, botryoidal aggregates, nodules, coatings, massive.
Origin and occurrence: : Hydrothermal in cracks in sedimentary rocks, rich in Al and P, also in phosphates deposits. It is associated with apatite, wavellite and other phosphates. Renowned greenish nodules up to 30 cm (12 in) in diameter come from Clay Canyon, Fairfield, Utah, USA; also known from Ronneburg, Germany and Jivina near Beroun, Czech Republic.

Strengite

$Fe^{3+}(PO_4) \cdot 2\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, pinkish, red-purple; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 3.5-4.5; CL – good; F – conchoidal; M – isometric, tabular to short prismatic crystals, botryoidal aggregates with radial structure, coatings.
Origin and occurrence: Secondary in granitic



Strengite, 34 mm, Svappavaara, Sweden

pegmatites where it forms as a result of hydrothermal replacement of primary phosphates; in the oxidation zone of Fe deposit together with goethite. Purple crystals up to 5 mm (3/16 in) across, come from the Bull Moose mine, Custer, South Dakota, USA; also known from Pleystein, Germany and from Teskov, Czech Republic.

Scorodite

$Fe^{3+}(AsO_4) . 2 H_2O$

ORTHORHOMBIC ● ● ●

Properties: B – light green, gray-green, olive-green, colorless, blue, yellow-brown; S – light green; L – vitreous to resinous; D – transparent to translucent; DE – 3.3; H – 3.5-4; CL – imperfect; F – conchoidal; M – dipyramidal to short prismatic crystals, botryoidal and earthy aggregates, coatings, granular, massive.

Origin and occurrence: Secondary in the oxidation zone of ore deposits, associated with arsenopyrite, lollingite and other arsenides; in granitic pegmatites; hydrothermal in the hot springs.

Perfect crystals up to 50 mm (2 in) across come from Tsumeb, Namibia; the Kiura mine, Oita, Japan; Mina Ojuela, Mapimi, Durango, Mexico; green crusts, several cm thick, were found in Djebel Debar, Algeria.



Scorodite, 10 mm x, Zacatecas, Mexico

Phosphophyllite, 18 mm x, Potosí, Bolivia



Phosphophyllite

$Zn_2Fe(PO_4)_2 \cdot 4\ H_2O$

MONOCLINIC ● ●

Properties: C – colorless, blue-green, blue; S – white; L – vitreous; D – transparent to translucent; DE – 3.1; H – 3-3.5; CL – good; F – uneven; M – long to short prismatic and thick tabular crystals, granular.
Origin and occurrence: Secondary in the oxidation zone of ore deposits; in granitic pegmatites, where it replaces primary phosphates. Perfect crystals, up to 140 mm (5½ in) across come from sulfide cavities in the Unificada mine, Potosí, Bolivia. Also occurs at Hagendorf, Germany.

Ludlamite

$Fe_3(PO_4)_2 \cdot 4\ H_2O$

MONOCLINIC ● ●

Properties: C – light green, green; S – white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 3.5; CL – perfect; F – uneven; M – thin to thick tabular crystals, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of ore deposits; in granitic pegmatites, where it replaces primary phosphates. Perfect crystals up to 90 mm ($3\frac{9}{16}$ in) across known from the San Antonio mine, Santa Eulalia, Chihuahua, Mexico; also from Morococala, Bolivia and the Blackbird district, Idaho, USA.

Ludlamite, 36 mm, Morococala, Bolivia



Anapaite

$Ca_2Fe(PO_4)_2 \cdot 4\ H_2O$

TRICLINIC ● ●

Properties: C – light to dark green, colorless; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 3.5; CL – perfect; F – uneven; M – thin to thick tabular crystals, rosette-like aggregates, granular.
Origin and occurrence: Secondary in the oxidation zone of Fe deposits and in sedimentary rocks, rich in P. Tabular crystals several mm across and spherical aggregates, up to 30 mm ($1\frac{3}{16}$ in) across, come from the cracks within oolitic ores near Anapa and Kerch, Crimea, Ukraine; also known from Bellaver de Cerdena, Spain.

Vivianite

$Fe_3(PO_4)_2 \cdot 8\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless when fresh, quickly oxidizes to blue, green, purple, black-blue; S – white to bluish; L – vitreous; D – transparent, translucent to opaque; DE – 2.7; H – 1.5-2; CL – perfect; F – uneven; M – long prismatic to acicular crystals, fibrous, earthy to pulverulent aggregates, coatings, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of Fe deposits; in granitic pegmatites, where it forms by the replacement of primary phosphates and in sedimentary rocks in proximity of organic

Anapaite, 18 mm aggregates, Anapa, Ukraine



material; hydrothermal in the ore deposits. Crystals up to 1.5 m (5 ft) long found in clay sediments in Anloua, Cameroon; crystals up to 200 mm ($7^{7}/_{8}$ in) across known from Morococala, Bolivia. Smaller crystals come from Trepca, Serbia; Leadville, Colorado, Bingham Canyon, Utah, USA; also from Kerch and Anapa, Crimea, Ukraine.

Erythrine

$Co_3(AsO_4)_2 \cdot 8\ H_2O$

MONOCLINIC ● ● ●

Properties: C – dark purple, pink, colorless; S – light pink to white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 1.5-2.5; CL – perfect; F – uneven; M – long prismatic, acicular to tabular crystals, earthy aggregates, coatings, granular, massive.

Origin and occurrence: Secondary in the oxidation zone of Co, Ni and U deposits. Tabular crystals up to 60 mm ($2^{3}/_{8}$ in) long come from Bou Azzer, Morocco. Other important localities are Schneeberg, Germany; Talmessi, Iran; Cobalt, Ontario, Canada; Mount Cobalt, Queensland, Australia.

Erythrite, 29 mm, Mexico



Vivianite, 48 mm, Morococala, Bolivia



Phosphophyllite, 18 mm x, Potosi, Bolivia



Phosphophyllite

$Zn_2Fe(PO_4)_2 \cdot 4\ H_2O$

MONOCLINIC ● ●

Properties: C – colorless, blue-green, blue; S – white; L – vitreous; D – transparent to translucent; DE – 3.1; H – 3-3.5; CL – good; F – uneven; M – long to short prismatic and thick tabular crystals, granular.

Origin and occurrence: Secondary in the oxidation zone of ore deposits; in granitic pegmatites, where it replaces primary phosphates. Perfect crystals, up to 140 mm (5½ in) across come from sulfide cavities in the Unificada mine, Potosi, Bolivia. Also occurs at Hagendorf, Germany.

Ludlamite

$Fe_3(PO_4)_2 \cdot 4\ H_2O$

MONOCLINIC ● ●

Properties: C – light green, green; S – white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 3.5; CL – perfect; F – uneven; M – thin to thick tabular crystals, granular, massive.

Origin and occurrence: Secondary in the oxidation zone of ore deposits; in granitic pegmatites, where it replaces primary phosphates. Perfect crystals up to 90 mm ($3\frac{9}{16}$ in) across known from the San Antonio mine, Santa Eulalia, Chihuahua, Mexico; also from Morococala, Bolivia and the Blackbird district, Idaho, USA.

Ludlamite, 36 mm, Morococala, Bolivia



Anapaite

$Ca_2Fe(PO_4)_2 \cdot 4\ H_2O$

TRICLINIC ● ●

Properties: C – light to dark green, colorless; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 3.5; CL – perfect; F – uneven; M – thin to thick tabular crystals, rosette-like aggregates, granular.

Origin and occurrence: Secondary in the oxidation zone of Fe deposits and in sedimentary rocks, rich in P. Tabular crystals several mm across and spherical aggregates, up to 30 mm ($1\frac{3}{16}$ in) across, come from the cracks within oolitic ores near Anapa and Kerch, Crimea, Ukraine; also known from Bellaver de Cerdena, Spain.

Vivianite

$Fe_3(PO_4)_2 \cdot 8\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless when fresh, quickly oxidizes to blue, green, purple, black-blue; S – white to bluish; L – vitreous; D – transparent, translucent to opaque; DE – 2.7; H – 1.5-2; CL – perfect; F – uneven; M – long prismatic to acicular crystals, fibrous, earthy to pulverulent aggregates, coatings, granular, massive.

Origin and occurrence: Secondary in the oxidation zone of Fe deposits; in granitic pegmatites, where it forms by the replacement of primary phosphates and in sedimentary rocks in proximity of organic

Anapaite, 18 mm aggregates, Anapa, Ukraine



material; hydrothermal in the ore deposits. Crystals up to 1.5 m (5 ft) long found in clay sediments in Anloua, Cameroon; crystals up to 200 mm (7⅞ in) across known from Morococala, Bolivia. Smaller crystals come from Trepca, Serbia; Leadville, Colorado, Bingham Canyon, Utah, USA; also from Kerch and Anapa, Crimea, Ukraine.

Erythrine

$Co_3(AsO_4)_2 \cdot 8\,H_2O$

MONOCLINIC ● ● ●

Properties: C – dark purple, pink, colorless; S – light pink to white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 1.5-2.5; CL – perfect; F – uneven; M – long prismatic, acicular to tabular crystals, earthy aggregates, coatings, granular, massive.

Erythrite, 29 mm, Mexico



Origin and occurrence: Secondary in the oxidation zone of Co, Ni and U deposits. Tabular crystals up to 60 mm (2⅜ in) long come from Bou Azzer, Morocco. Other important localities are Schneeberg, Germany; Talmessi, Iran; Cobalt, Ontario, Canada; Mount Cobalt, Queensland, Australia.

Vivianite, 48 mm, Morococala, Bolivia




Annabergite, 55 mm, Laurion, Greece

Annabergite

$Ni_3(AsO_4)_2 \cdot 8\,H_2O$

MONOCLINIC ● ● ●

Varieties: cabrerite (Mg contents)

Properties: C – light to dark green, white; S – white; L – vitreous; D – transparent to translucent; DE – 3.2; H – 1.5-2.5; CL – perfect; F – uneven; M – long prismatic to acicular and tabular crystals, acicular and earthy aggregates, coatings, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of Ni deposits, associated with erythrite. Crystals up to 5 mm (3/16 in) across occur in Gukuroren, Turkey; Sierra Cabrera, Spain; Laurion, Greece. Nodules up to 20 mm (25/32 in) come from the Snowbird mine, Montana, USA.

Symplesite

$Fe_3(AsO_4)_2 \cdot 8\,H_2O$

TRICLINIC ● ●

Properties: C – bluish, dark blue, light green, black-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.0 H – 2.5; CL – perfect; F – uneven; M – acicular to tabular crystals, spherical aggregates with radial structure, earthy aggregates and coatings, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of ore deposits and in granitic pegmatites with


Symplesite, 12 mm xx, Baia Sprie, Romania


Picropharmacolite, 128 mm, France

As minerals, mainly arsenopyrite and lollingite. It occurs in Schneeberg, Germany; Baia Sprie, Romania and Trebsko, Czech Republic.

Picropharmacolite

$Ca_4MgH_2(AsO_4)_4 \cdot 12\ H_2O$

TRICLINIC ● ●

Properties: C – colorless, white; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 2.5; CL – perfect; F – uneven; M – acicular crystals, spherical aggregates with radial structure, coatings.
Origin and occurrence: Secondary in the oxidation zone of ore deposits with As minerals, mostly arsenopyrite and lollingite. It is also known from Ste-Marie-aux-Mines and Salsigne, France; Freiberg, Germany and Jachymov, Czech Republic.

Brushite

$CaH(PO_4) \cdot 2\ H_2O$

MONOCLINIC ● ●

Properties: C – colorless, white; S – white; L – vitreous, pearly on cleavage planes; D – transparent to translucent; DE – 2.3; H – 2.5; CL – perfect; F – uneven; M – prismatic, acicular to tabular crystals, earthy aggregates and coatings, massive.
Origin and occurrence: Secondary on bat and bird excrements and bones, it impregnates bones, along the cracks of phosphorites. Tabular crystals up to 20 mm ($^{25}/_{32}$ in) across come from Quercy, France also occurs near Oran, Algeria and Pig Hole, Virginia, USA.

Brushite, 4 mm xx, Domica, Slovakia

Legrandite, 25 mm xx, Mapimi, Mexico

Legrandite

$Zn_2(AsO_4)(OH) \cdot H_2O$

MONOCLINIC ● ●

Properties: C – colorless, yellow, purple; S – white; L – vitreous; D – transparent to translucent; DE – 4.0 H – 4.5; CL – imperfect; F – uneven; M – long prismatic crystals and their inter-growths, radial aggregates.
Origin and occurrence: Secondary in the oxidation zone of Zn deposits and in pegmatites. Prismatic crystals up to 250 mm (9$^{13}/_{16}$ in) long found in Mina Ojuela, Mapimi, Durango, Mexico. It is also known from Galileia, Minas Gerais, Brazil and Tsumeb, Namibia.

Euchroite, 10 mm xx, L'ubietova, Slovakia



Euchroite

$Cu_2(AsO_4)(OH) . 3 H_2O$

ORTHORHOMBIC ● ●

Properties: C – emerald-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.5; H – 3.5-4; CL – imperfect; F – conchoidal to uneven; M – short prismatic to thick tabular crystals, massive.
Origin and occurrence: Secondary in the oxidation zone of Cu deposits, associated with olivenite and malachite. Thick tabular crystals up to 30 mm ($1^{3}/_{16}$ in) come from L'ubietova, Slovakia. It also occurs in Zapacica, Bulgaria and Chessy, France.

Vauxite, 20 mm xx, Llallagua, Bolivia



Strunzite, 10 mm xx, Hagendorf, Germany



Vauxite

$FeAl_2(PO_4)_2(OH)_2 . 6 H_2O$

TRICLINIC ● ●

Properties: C – light to dark blue; S – white; L – vitreous; D – transparent to translucent; DE – 2.4; H – 3.5; CL – none; F – uneven; M – tabular crystals, radial aggregates, massive.
Origin and occurrence: Secondary in the oxidation zone of Sn deposits, associated with wavellite. Crystals occur in the Siglo XX Mine, Llallagua, Bolivia.

Strunzite

$MnFe^{3+}{}_2(PO_4)_2(OH)_2 . 6 H_2O$

MONOCLINIC ● ● ●

Properties: C – light yellow, yellow-brown; S – yellowish; L – vitreous; D – transparent to translucent; DE – 2.5; H – not determined; CL – not determined; F – uneven; M – acicular crystals, acicular and fibrous aggregates.
Origin and occurrence: Secondary in granitic pegmatites, as a result of weathering of primary phosphates, mostly triphyllite; rarely hydrothermal in the cracks of Fe-rich sedimentary rocks. Acicular crystals up to 20 mm ($^{25}/_{32}$ in) across known from Hagendorf, Germany; the Palermo No. 1 and No. 2 mines, North Groton and the Fletcher mine, Groton, New Hampshire, USA.

Cacoxenite, 1 mm xx, Hellertown, Pennsylvania, U.S.A.



Cacoxenite

$(Fe^{3+},Al)_{25}(PO_4)_{17}O_6(OH)_{12} . 75 H_2O$

HEXAGONAL ● ● ●

Properties: C – light yellow, yellow-brown, orange; S – yellow; L – silky; D – transparent to translucent; DE – 2.3; H – 3-4; CL – not determined; F – uneven; M – acicular and fibrous aggregates, often with radial structure, botryoidal crusts and coatings.

Origin and occurrence: Hydrothermal on the cracks of sedimentary Fe ores, associated with wavellite; rare as secondary in granitic pegmatites, as a product of weathering of primary phosphates. Crystals up to 10 mm (3/8 in) across come from the Horcajo mine, Ciudad Real, Spain; golden-yellow acicular aggregates occur in Hrbek near Svata Dobrotiva and Trenice, Czech Republic and in Amberg, Germany.

Beraunite

$Fe^{2+}Fe^{3+}_5(PO_4)_4(OH)_5 . 4 H_2O$

MONOCLINIC ● ●

Properties: C – red-brown, red, gray-green; S – yellow to green-brown; L – vitreous to dull; D – translucent; DE – 3.0; H – 3.5-4; CL – good; F – uneven; M – acicular aggregates, often with radial structure, botryoidal crusts and coatings.

Origin and occurrence: Hydrothermal on the cracks of sedimentary Fe ores, typically together with wavellite; secondary in granitic pegmatites, as a product of weathering of primary phosphates. Acicular aggregates up to 10 mm (3/8 in) across occur in Mount Indian, Alabama, USA; also known from Hrbek near Svata Dobrotiva, Czech Republic and Amberg, Germany.

Beraunite, 3 mm aggregates, Nekeszeny, Hungary



Diadochite

$Fe^{3+}_2(PO_4)(SO_4)(OH) . 5 H_2O$

TRICLINIC ● ● ●

Properties: C – yellow-brown, brown, red-brown, yellow-green, gray-green; S – yellow to light brown; L – dull, waxy; D – translucent to opaque; DE – 2.0-2.4; H – 3; CL – not determined; F – uneven, conchoidal, earthy; M – nodules, coatings and crusts, massive.

Origin and occurrence: Secondary in the oxidation zone of Fe deposits. Diadochite caves in abandoned mines are known from Saalfeld, Germany; nodules found in New Idria, California and Eureka, Nevada, USA.

Diadochite, 40 mm, Recsk, Hungary



Wavellite, 40 mm, Trenice, Czech Republic



Eosphorite, 4 mm xx, Lavra da Ilha, Brazil



Wavellite

$Al_3(PO_4)_2(OH,F)_3 . 5 H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, greenish, light blue-green, green, yellowish; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.4; H – 3.5-4; CL – perfect; F – uneven; M – isometric crystals, hemispherical aggregates with radial structure, botryoidal aggregates, nodules, coatings, massive.
Origin and occurrence: Hydrothermal in the cracks of Al and P-rich sediments, also in phosphate deposits, ore veins and pegmatites. Beautiful hemispherical aggregates up to 40 mm ($1\frac{9}{16}$ in) in diameter occur in Pencil, Garland and Magnet Cove, Arkansas, USA; also known from Trenice and Milina, Czech Republic and Ronneburg, Germany.

Eosphorite

$MnAl(PO_4)(OH)_2 . H_2O$

ORTHORHOMBIC ● ●

Properties: C – pinkish, colorless, white, brownish, red-brown; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 3.1; H – 5; CL – imperfect; F – uneven to conchoidal; M – long to short prismatic crystals, radial aggregates, granular.
Origin and occurrence: Secondary in granitic pegmatites, as a product of hydrothermal replacement of primary phosphates. Crystals up to 100 mm (4in) long found in the Joao Modesto dos Santos mine, Minas Gerais, Brazil. It occurs in Rapid Creek, Yukon, Canada, too.

Turquoise

$CuAl_6(PO_4)_4(OH)_8 . 4 H_2O$

TRICLINIC ● ● ●

Properties: C – blue, blue-green, green; S – white; L – waxy; D – transparent, translucent to opaque; DE – 2.9; H – 5-6; CL – good; F – conchoidal to uneven; M – short prismatic crystals, botryoidal aggregates, coatings, massive.
Origin and occurrence: Secondary in the surface parts of rocks with elevated contents of P and Cu, e.g. in the oxidation zone of some Cu deposits. Small crystals occurred near Lynch Station, Virginia, USA. Massive blue and blue-green concretions come from Mount Ali Mirsai near Maden, Iran. Other localities are Cortez, Nevada, Los Cerillos and Eureka, New Mexico and Bisbee, Arizona, USA.
Application: popular gemstone.

Turquoise, 3 mm aggregates, Humboldt Co., U.S.A.



Chalcosiderite

$CuFe^{3+}_6(PO_4)_4(OH)_8 \cdot 4\,H_2O$

TRICLINIC ● ●

Properties: C – dark green; S – white; L – vitreous; D – transparent to translucent; DE – 3.3; H – 4.5; CL – good; F – conchoidal to uneven; M – short prismatic crystals, coatings.

Origin and occurrence: Secondary in the oxidation zone of some Cu deposits, together with goethite, dufrenite and pharmacosiderite. It occurs in Bisbee, Arizona, USA; in the Wheal Phoenix mine, Cornwall, UK; Schneckenstein, Germany; Horni Slavkov, Czech Republic.

Turquoise, 50 mm, Kazakhstan



Chalcosiderite, 90 mm, Cornwall, UK



Chenevixite, 100 mm, Chuquicamata, Chile



Chenevixite

$Cu_2Fe^{3+}{}_2(AsO_4)_2(OH)_4 \cdot H_2O$

MONOCLINIC ●

Properties: C – dark green, olive-green to yellow-green; S – yellow-green; L – greasy; D – translucent; DE – 3.9; H – 3.5-4.5; CL – not determined; F – conchoidal to uneven; M – earthy aggregates, coatings, massive.

Origin and occurrence: Secondary in the oxidation zone of Cu deposits, associated with malachite, tyrolite, azurite and other minerals. Massive aggregates occur in the Mammoth mine, Tintic, Utah, USA; also in Klein Spitzkopje, Namibia.

Tyrolite

$CaCu_5(AsO_4)_2(CO_3)(OH)_4 \cdot 6\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – apple-green, green-blue to blue; S – light green to blue-green; L – vitreous to pearly; D – transparent to translucent; DE – 3.3; H – 2; CL – perfect; F – uneven; M B scaly and fan-shaped aggregates, coatings and crusts.

Origin and occurrence: Secondary in the oxidation zone of Cu deposits, frequently associated with chalcophyllite. Rich aggregates occur in the Majuba Hill mine, Nevada, also in Tintic, Utah, USA. It is also known from Brixlegg, Austria; Saalfeld and Schneeberg, Germany; Novoveska Huta, Slovakia.

Tyrolite, 90 mm, Novoveska Huta, Slovakia



Delvauxite

$CaFe^{3+}{}_4(PO_4,SO_4)(OH)_8 \cdot 4\text{-}6\ H_2O$

AMORPHOUS ● ● ●

Properties: C – yellow-brown, brown, red-brown, black-brown; S – yellow; L – greasy, waxy; D – translucent to opaque; DE – 1.8-2.0; H – 2.5; CL – not determined; F – conchoidal, earthy; M – nodules, stalactites, coatings and crusts, massive.

Origin and occurrence: Secondary in oxidation zone of Fe deposits. Nodules of 50 cm (20 in) across in Czech Republic. Also known in Berneau and Richelle, Belgium; Železník, Slovakia; Kerch, Crimea, Ukraine.

Delvauxite, 80 mm, Nucice, Czech Republic



Bukovskyite, 40 mm, Kaňk, Czech Republic



Bukovskyite

$Fe^{3+}{}_2(AsO_4)(SO_4)(OH) \cdot 7\ H_2O$

TRICLINIC ●

Properties: C – yellow-green, gray-green; S – yellowish white; L – dull to earthy; D – translucent to opaque; DE – 2.3; H – not determined; CL – not determined; F – earthy; M B botryoidal aggregates and nodules.
Origin and occurrence: Secondary on the old mine dumps where it forms as a product of arsenopyrite weathering. Nodules up to 60 cm (24 in), occur on medieval dumps in Kank near Kutna Hora, Czech Republic.

Chalcophyllite, 36 mm, Chile



Veszelyite

$(Cu,Zn)_3(PO_4)(OH)_3 \cdot 2\ H_2O$

MONOCLINIC ● ●

Properties: C – green, blue-green, dark blue; S – green; L – vitreous; D – translucent; DE – 3.4; H – 3.5-4; CL – good; F – uneven; M – short prismatic to tabular crystals, granular.
Origin and occurrence: Secondary in the oxidation zone of Cu-Zn deposits. Crystals up to 50 mm (2 in) across found in the Black Pine mine, Philipsburg, Montana, USA; also from Moravita, Romania; Arakawa, Japan; Wanlockhead, Scotland, UK.

Chalcophylite

$Cu_{18}Al_2(AsO_4)_3(SO_4)_3(OH)_{27} \cdot 36\ H_2O$

TRIGONAL ● ● ●

Properties: C – emerald-green, blue-green; S – light green; L – vitreous, pearly; D – transparent to translucent; DE – 2.6; H – 2; CL – perfect; F – uneven; M – tabular crystals, scaly, fan-shaped aggregates, coatings, massive.
Origin and occurrence: Secondary in the oxidation zone of Cu deposits, usually associated with tyrolite. Rich aggregates occur in the Majuba Hill, Nevada and in the Tintic district, Utah, USA. Nice specimens also come from Novoveska Huta and Piesky, Slovakia; Nizhniy Tagil, Ural mountains, Russia; Cap Garrone, France.

Veszelyite, 13 mm, Philipsburg, U.S.A.



Liroconite, 86 mm, Cornwall, UK

Lirokonit

$Cu_2Al(AsO_4)(OH)_4 . 4 H_2O$

MONOCLINIC ● ●

Properties: C – blue, green; S – light blue; L – vitreous to resinous; D – transparent to translucent; DE – 3.0; H – 2-2.5; CL – imperfect; F – conchoidal to uneven; M – lenticular, dipyramidal crystals, massive.
Origin and occurrence: Secondary in the oxidation zone of Cu deposits, together with olivenite, malachite and azurite. Perfect crystals up to 30 mm ($1\frac{3}{16}$ in) across come from Redruth and St. Day, Cornwall, UK. It is also known from Cerro Gordo, California, USA.

Evansite, 5 mm aggregates, Sirk – Zeleznik, Slovakia

Evansite

$Al_3(PO_4)(OH)_6 . 6 H_2O$

AMORPHOUS 3

Properties: C – colorless, white, greenish, light blue-green, yellowish; S – white; L – vitreous, resinous, waxy; D – transparent to translucent; DE – 1.8-2.2; H – 3-4; CL – none; F – conchoidal; M – botryoidal, stalactitic and hemispherical aggregates and coatings.
Origin and occurrence: Secondary in the oxidation zone of Fe deposits, rich in P, associated with alophane and goethite. Rich stalactitic aggregates come from Zeleznik, Slovakia and from Epernay, France.

Whiteite-(CaFeMg)

$CaFeMg_2Al_2(PO_4)_4(OH)_2 . 8 H_2O$

MONOCLINIC ● ●

Properties: C – brown; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 4; CL – good; F – uneven; M – short prismatic crystals.
Origin and occurrence: Hydrothermal in the cracks of P-rich sediments. Perfect crystals up to 20 mm ($\frac{25}{32}$ in) across come from Big Fish River, Yukon, Canada. Crystals up to 5 mm ($\frac{3}{16}$ in), are known from Lavra da Ilha de Taquaral, Minas Gerais, Brazil.

Whiteite-(CaFeMg), 65 mm, Yukon Territory, Canada

Jahnsite-(CaMnMg), 60 mm, Custer, U.S.A.



Jahnsite-(CaMnMg)

$CaMnMg_2Fe^{3+}{}_2(PO_4)_4(OH)_4 \cdot 8\ H_2O$

MONOCLINIC ● ●

Properties: C – yellow, light to dark brown; S – light yellow; L – vitreous; D – transparent to translucent; DE – 2.6; H – not determined; CL – good; F – uneven; M – short to long prismatic crystals, granular.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a result of replacement of primary phosphates. Perfect crystals up to 10 mm (⅜ in) across occur in the Tip Top mine, Custer, South Dakota, USA. It is also known from Hagendorf, Germany.

Wardite

$NaAl_3(PO_4)_2(OH)_4 \cdot 2\ H_2O$

TETRAGONAL ● ● ●

Properties: C – colorless, white, greenish, light blue-green; S -white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 5; CL – perfect; F – uneven; M – dipyramidal crystals, radial and hemispherical aggregates, coatings, crusts, granular.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a product of primary phosphate replacement; hydrothermal in the cracks in P-rich sediments. Perfect crystals up to 30 mm (1¼ in) across come from Rapid Creek, Yukon, Canada. It is also known from Piedras Lavradas, Paraiba, Brazil.

Wardite, 48 mm, Yukon Territory, Canada



Cyrilovite

$NaFe^{3+}{}_3(PO_4)_2(OH)_4 \cdot 2\ H_2O$

TETRAGONAL ● ●

Properties: C – yellow, orange, brown-yellow; S – yellow; L – vitreous; D – transparent to translucent; DE – 3.1; H – 4; CL – good; F – conchoidal; M – tabular and dipyramidal crystals, coatings and crusts.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a result of replacement of primary phosphates. Small crystals occur in Cyrilov, Czech Republic; Hagendorf, Germany and Sapucaia, Minas Gerais, Brazil.

Cyrilovite, 60 mm, Iron Monarch, Australia



Liroconite, 86 mm, Cornwall, UK



Lirokonit

$Cu_2Al(AsO_4)(OH)_4 . 4 H_2O$

MONOCLINIC ● ●

Properties: C – blue, green; S – light blue; L – vitreous to resinous; D – transparent to translucent; DE – 3.0, H – 2-2.5; CL – imperfect; F – conchoidal to uneven; M – lenticular, dipyramidal crystals, massive.

Origin and occurrence: Secondary in the oxidation zone of Cu deposits, together with olivenite, malachite and azurite. Perfect crystals up to 30 mm ($1^{3}/_{16}$ in) across come from Redruth and St. Day, Cornwall, UK. It is also known from Cerro Gordo, California, USA.

Evansite, 5 mm aggregates, Sirk – Zeleznik, Slovakia



Evansite

$Al_3(PO_4)(OH)_6 . 6 H_2O$

AMORPHOUS 3

Properties: C – colorless, white, greenish, light blue-green, yellowish; S – white; L – vitreous, resinous, waxy; D – transparent to translucent; DE – 1.8-2.2; H – 3-4; CL – none; F – conchoidal; M – botryoidal, stalactitic and hemispherical aggregates and coatings.

Origin and occurrence: Secondary in the oxidation zone of Fe deposits, rich in P, associated with alophane and goethite. Rich stalactitic aggregates come from Zeleznik, Slovakia and from Epernay, France.

Whiteite-(CaFeMg)

$CaFeMg_2Al_2(PO_4)_4(OH)_2 . 8 H_2O$

MONOCLINIC ● ●

Properties: C – brown; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 4; CL – good; F – uneven; M – short prismatic crystals.

Origin and occurrence: Hydrothermal in the cracks of P-rich sediments. Perfect crystals up to 20 mm ($^{25}/_{32}$ in) across come from Big Fish River, Yukon, Canada. Crystals up to 5 mm ($^{3}/_{16}$ in), are known from Lavra da Ilha de Taquaral, Minas Gerais, Brazil.

Whiteite-(CaFeMg), 65 mm, Yukon Territory, Canada



Jahnsite-(CaMnMg), 60 mm, Custer, U.S.A.



Jahnsite-(CaMnMg)

$CaMnMg_2Fe^{3+}{}_2(PO_4)_4(OH)_4 \cdot 8\ H_2O$

MONOCLINIC ● ●

Properties: C – yellow, light to dark brown; S – light yellow; L – vitreous; D – transparent to translucent; DE – 2.6; H – not determined; CL – good; F – uneven; M – short to long prismatic crystals, granular.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a result of replacement of primary phosphates. Perfect crystals up to 10 mm (3/8 in) across occur in the Tip Top mine, Custer, South Dakota, USA. It is also known from Hagendorf, Germany.

Wardite

$NaAl_3(PO_4)_2(OH)_4 \cdot 2\ H_2O$

TETRAGONAL ● ● ●

Properties: C – colorless, white, greenish, light blue-green; S -white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 5; CL – perfect; F – uneven; M – dipyramidal crystals, radial and hemispherical aggregates, coatings, crusts, granular.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a product of primary phosphate replacement; hydrothermal in the cracks in P-rich sediments. Perfect crystals up to 30 mm (1 3/16 in) across come from Rapid Creek, Yukon, Canada. It is also known from Piedras Lavradas, Paraiba, Brazil.

Wardite, 48 mm, Yukon Territory, Canada



Cyrilovite

$NaFe^{3+}{}_3(PO_4)_2(OH)_4 \cdot 2\ H_2O$

TETRAGONAL ● ●

Properties: C – yellow, orange, brown-yellow; S – yellow; L – vitreous; D – transparent to translucent; DE – 3.1; H – 4; CL – good; F – conchoidal; M – tabular and dipyramidal crystals, coatings and crusts.
Origin and occurrence: Secondary in granitic pegmatites, where it forms as a result of replacement of primary phosphates. Small crystals occur in Cyrilov, Czech Republic; Hagendorf, Germany and Sapucaia, Minas Gerais, Brazil.

Cyrilovite, 60 mm, Iron Monarch, Australia



Pharmacosiderite, 35 mm, Cornwall, UK



Arseniosiderite, 3 mm, Nagyborzsony, Hungary



Lavendulan, 36 mm, San Juan, Chile



Mixite, 70 mm, Cinovec, Czech Republic



Pharmacosiderite

$KFe^{3+}_4(AsO_4)_3(OH)_4 \cdot 6\ H_2O$

CUBIC ● ● ●

Properties: C – green, yellow-brown, brown; S – white; L – adamantine to greasy; D – transparent to translucent; DE – 2.8; H – 2.5; CL – imperfect; F – uneven; M – cubic crystals, coatings, crusts, granular, massive.
Origin and occurrence: Secondary in granitic pegmatites and in the oxidation zone of ore deposits, where it forms as a product of arsenopyrite and lollingite replacement. Cubic crystals up to 10 mm (3/8 in) across occur in St. Day, Liskeard and Redruth, Cornwall, UK. It also comes from the Majuba Hill mine, Nevada, USA; Horhausen, Germany and Cap Garrone, France.

Arseniosiderite

$CaFe^{3+}_3(AsO_4)_3O_2 \cdot 3\ H_2O$

MONOCLINIC ● ●

Properties: C – yellow, light to dark brown; S – yellow; L – submetallic to silky; D – opaque; DE – 3.6; H – 1.5; CL – good; F – uneven; M – fibrous and earthy aggregates, coatings, crusts, massive.
Origin and occurrence: Secondary in the oxidation zone of ore deposits and in granitic pegmatites, where it forms as a product of arsenopyrite and lollingite replacement. Rich aggregates occur in Romanche, France; also from the Eureka mine, Tintic, Utah, USA and Wittichen, Germany.

Lavendulane

$NaCaCu_5(AsO_4)_4Cl \cdot 5\ H_2O$

ORTHORHOMBIC ● ●

Properties: C – light blue-purple, blue; S – white; L – vitreous to waxy; D – translucent; DE – 3.5; H – 2.5; CL – good; F – uneven; M – acicular crystals, acicular and earthy aggregates, coatings.
Origin and occurrence: Secondary in the oxidation zone of Co, Cu and Ni deposits, as a result of arsenide weathering, associated with erythrite. Rich acicular aggregates come from Talmessi and Anarak, Iran. Small crystals found in the Blanca mine, San Juan, Chile and in Annaberg, Germany. Crystals up to 4 mm (5/32 in) across occur in the Gold Hill mine, Utah, USA.

Kovdorskite, 15 mm x, Kovdor, Kola, Russia

Mixite

$BiCu_6(AsO_4)_3(OH)_6 \cdot 3\ H_2O$

HEXAGONAL ● ●

Properties: C – emerald-green, blue-green, light blue, light green, whitish; S – light green, light blue; L – adamantine to dull; D – translucent; DE – 3.8; H – 3-4; CL – not determined; F – uneven; M – acicular crystals, acicular and earthy aggregates, coatings, massive.

Origin and occurrence: Secondary in the oxidation zone of Bi and Cu deposits, together with bismuthinite. It occurred in Jachymov, Czech Republic; in Tintic, Utah, USA; Schneeberg and Wittichen, Germany.

Kovdorskite

$Mg_5(PO_4)_2(CO_3)(OH)_2 \cdot 4{,}5\ H_2O$

MONOCLINIC ●

Properties: C – light pink-brown, white, blue; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 4; CL – none; F – conchoidal to uneven; M – tabular crystals, massive.

Origin and occurrence: Hydrothermal, associated with magnesite, magnetite and other minerals. Blue and pink-brown crystals up to 25 mm (1 in) across come from the Zheleznyi mine, Kovdor, Kola Peninsula, Russia.

Torbernite

$Cu(UO_2)_2(PO_4)_2 \cdot 8\text{-}12\ H_2O$

TETRAGONAL ● ● ●

Properties: C – emerald-green to grass-green; S – light green; L – vitreous to dull, pearly on the cleavage planes; D – transparent to translucent; DE – 3.3; H – 2-2.5; CL – perfect; F – uneven; M – tabular to pyramidal crystals, earthy aggregates, coatings, granular, massive; R – strongly radioactive.

Origin and occurrence: Secondary in the oxidation zone of U deposits, also in pegmatites and sedimentary rocks, resulting from the hydrothermal alteration of uraninite and other U minerals. Emerald-green tabular crystals, several cm across, come from Sabugal, Portugal; Jachymov, Czech Republic; Shinkolobwe, Zaire; Bois-Noirs, France; Moctezuma, Mexico and many localities in the Colorado Plateau, Utah, USA. Beautiful druses of crystals up to 20 mm ($^{25}/_{32}$ in) across, found in the Margabal mine, Aveyron, France.

Application: U ore.

Torbernite, 120 mm, Katanga, Zair

+
→

Autunite, 15 mm xx, Troncasa, Portugal



Novacekite, 70 mm, Brumado, Brazil



Autunite

$Ca(UO_2)_2(PO_4)_2 . 10\text{-}12\ H_2O$

TETRAGONAL ● ● ●

Properties: C – light to dark yellow, yellow-green to green; S – light yellow; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 2-2.5; CL – perfect; F – uneven; M – tabular crystals, foliated, scaly, earthy and pulverulent aggregates, coatings, massive; LU – yellow-green; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits, in pegmatites and in some U-rich sedimentary rocks, as a result of hydrothermal alteration of uraninite and other U minerals. It is frequently associated with torbernite and other U secondary minerals. Tabular crystals up to 30 mm (1³/₁₆ in) across come from Schneeberg and Johanngeorgenstadt, Germany and Autun, France. It is also known from Rum Jungle, Northern Territory, Australia; St. Austel, Cornwall, UK; Mount Spokane, Washington, USA and Jachymov, Czech Republic.
Application: U ore.

Uranocircite

$Ba(UO_2)_2(PO_4)_2 . 10\ H_2O$

TETRAGONAL ● ●

Properties: C – light to dark yellow, light yellow-green; S – light yellow; L – vitreous to dull, pearly on the cleavage planes; D – transparent to translu-

Uranocircite, 78 mm, Minas Gerais, Brazil



Zeunerite, 5 mm xx, Cinovec, Czech Republic



cent; DE – 3.5; H – 2-2.5; CL – perfect; F – uneven; M – tabular crystals, foliated and earthy aggregates, pulverulent coatings, massive; LU – green; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits. Yellow tabular crystals up to 10 mm (3/8 in) across occurred in Dametice, Czech Republic; Bergen and Wolsendorf, Germany and in the Sao Pedro mine, Suaçui, Minas Gerais, Brazil.

Novácekite

$Mg(UO_2)_2(AsO_4)_2 \cdot 10\ H_2O$

TETRAGONAL ● ●

Properties: C – straw-yellow, light yellow; S – light yellow; L – vitreous to dull; D – transparent to translucent; DE – 3.7; H – 2.5; CL – perfect; F – uneven; M – tabular crystals, lamellar, earthy and pulverulent aggregates, massive; LU – dark green; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits. Tabular crystals up to 50 mm (2 in) across come from the Pedra Preta Mine, Brumado, Bahia, Brazil. Lamellar aggregates are known from Zalesi, Czech Republic; Aldama, Chihuahua, Mexico; Wittichen, Germany.

Zeunerite

$Cu(UO_2)_2(AsO_4)_2 \cdot 10\text{-}16\ H_2O$

TETRAGONAL ● ●

Properties: C – emerald-green, yellow-green; S – light green; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 2.5; CL – perfect; F – uneven; M – tabular crystals, foliated aggregates, massive; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits. Tabular crystals up to 30 mm (1 3/16 in) across, come from the Pedra Preta Mine, Brumado, BahRa, Brazil. It is also known from Zalesí, Czech Republic and Schneeberg, Germany.

Carnotite

$K_2(UO_2)_2(VO_4)_2 \cdot 3\ H_2O$

MONOCLINIC ● ● ●

Properties: C – light to dark yellow, yellow-green; S – light yellow; L – dull; D – transparent to translucent, opaque; DE – 4.9; H – not determined; CL – perfect; F – uneven; M – earthy aggregates, massive; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of sedimentary U deposits, typically associated with tyuyamunite. Platy crystals, up to 2 mm (1/16 in) across found in the Mashamba West mine, Zaire. Earthy and pulverulent aggregates occur in many localities in the Colorado Plateau, e.g. Paradox Valley, Colorado and La Sal, Utah, USA. Also known from Tyuya Muyun, Uzbekistan and Radium Hill, Southern Australia, Australia.
Application: U and V ore..

Carnotite, 55 mm, Utah, U.S.A.



Tyuyamunite

$Ca(UO_2)_2(VO_4)_2 \cdot 5\text{-}8\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – yellow-green, canary yellow; S – light yellow; L – silky to adamantine; D – translucent to opaque; DE – 3.6; H – 2; CL – perfect; F – uneven; M – earthy aggregates, massive; LU – weak yellow-green; R – strongly radioactive.
Origin and occurrence: Secondary in the oxidation zone of sedimentary U deposits, together with carnotite. Common earthy and pulverulent aggregates occur in many localities in the Colorado Plateau, e.g. Paradox Valley, Colorado and Red Creek, Utah, USA. It was described from Tyuya Muyun, Uzbekistan.
Application: U and V ore.

Tyuyamunite, 80 mm, Fergana, Uzbekistan



9. Silicates

Phenakite

Be_2SiO_4

TRIGONAL ● ● ●

Properties: C – colorless, white, yellowish; S – white; L – strong vitreous; D – transparent to translucent; DE – 3.0; H – 8; CL – imperfect; F – conchoidal; M – long prismatic to tabular crystals, radial aggregates, granular.
Origin and occurrence: Magmatic in granitic pegmatites; hydrothermal in greisens; metamorphic in mica schists, associated with beryl, chrysoberyl, apatite and quartz. Prismatic crystals up to 250 mm ($9^{13}/_{16}$ in) long occurred in Kragero, Norway. It is also known from Sao Miguel de Piracicaba, Minas Gerais, Brazil in crystals, up to 100 mm (4 in) long. The other localities are Habachtal, Austria; Malyshevo, Russia; Anjanabonoina, Madagascar.
Application: sporadically cut as a gemstone.


Phenakite, 200 mmx, Kragero, Norway

Willemite

Zn_2SiO_4

TRIGONAL ● ● ●

Properties: C – white, yellowish, gray, green; S – white; L – vitreous; D – translucent; DE – 4.0; H – 5.5; CL – good; F B conchoidal to uneven; M – prismatic to tabular crystals, radial aggregates, granular; LU – distinct light green.
Origin and occurrence: Metamorphic in marbles; secondary in the oxidation zone of ore deposits, associated with zincite, franklinite, hemimorphite and smithsonite. Crystals up to 100 mm (4 in) across come from Franklin, New Jersey, USA, Mont St.-Hilaire, Quebec, Canada.
Application: as Zn ore.


Topaz, 60 mm, Thomas Range, U.S.A.
Willemite, 76 mm, Tsumeb, Namibia



Forsterite, 40 mm, Suppat, Pakistan

Forsterite

OLIVINE GROUP

Mg_2SiO_4

ORTHORHOMBIC ● ● ● ●

Properties: C – yellowish, greenish, colorless; S – white; L – vitreous; D – transparent to opaque; DE – 3.3; H – 6.5-7; CL – good; F – conchoidal to uneven; M – tabular to prismatic crystals, granular.
Origin and occurrence: Metamorphic in regionally and contact metamorphosed dolomites. Typical rock-forming mineral, associated with enstatite, spinel, phlogopite and chlorite. Green gemmy crystals up to 80 mm ($3^{1}/_{8}$ in) long come from Suppat, Pakistan. It also occurred in Crestmore, California, USA, Mount Timobly, British Columbia, Canada and Monte Somma, Italy.

Olivine

OLIVINE GROUP

$(Mg,Fe)_2SiO_4$

ORTHORHOMBIC ● ● ● ● ●

Varieties: chrysolite

Properties: C – green, yellow-green (chrysolite), brown-green to black-green; S – white; L – vitreous; D – translucent to opaque; DE – 3.3-3.6; H – 6.5-7; CL – good; F B conchoidal to uneven; M – imperfect crystals, granular.
Origin and occurrence: Magmatic in some ultrabasic rocks, e.g. dunites, lherzolites, peridotites, gabbros and in meteorites. Typical rock-forming mineral, usually associated with diopside, magnetite and pyrope. Classic locality of chrysolite is Zebirget Island in the Red Sea, Egypt, where tabular crystals

Olivine, 60 mm, Smrci, Czech Republic



up to 100 mm (4 in) across occurred. It is also known from the San Carlos Indian Reservation, Arizona, USA. Olivine was found in many basaltic rocks in Laacher See, Germany; Rockport, Massachusetts, USA and elsewhere.
Application: chrysolite is cut as a gemstone.

Fayalite
OLIVINE GROUP
Fe_2SiO_4

ORTHORHOMBIC ● ● ●

Properties: C – black-green to black; S – gray; L – dull to vitreous; D – opaque; DE – 4.2; H – 6.5-7; CL – good; F B conchoidal to uneven; M – imperfect prismatic crystals, granular.
Origin and occurrence: Magmatic in granitic pegmatites, granites and syenites, associated with orthoclase, gadolinite-(Y) and epidote; rare metamorphic. Poorly developed crystals up to 150 mm (6 in) long found in pegmatites near Baveno, the Alps, Italy. It is also known from Strzegom, Poland and the Sawtooth Batholith, Idaho, USA.

Fayalite, 80 mm, Rockport, U.S.A.



Tephroite
OLIVINE GROUP
Mn_2SiO_4

ORTHORHOMBIC ● ●

Properties: C – gray, olive-green, red-brown; S – white; L – dull to vitreous; D – translucent to transparent; DE – 4.2; H – 6; CL – good; F B conchoidal to uneven; M – prismatic crystals, granular.
Origin and occurrence: Metamorphic in skarns and Mn-rich metamorphosed sediments, together with rhodonite, franklinite and spessartine. Granular aggregates and perfect crystals up to 50 mm (2 in) across known from Franklin, New Jersey, USA; Langban, Sweden. It comes also from Tarnobrzeg, Poland, in crystals, up to 80 mm (3⅛ in) across.

Tephroite, 60 mm, Harstigen, Sweden



Pyrope, 3 mm grains, Trebivlice, Czech Republic



Pyrope

GARNET GROUP

$Mg_3Al_2Si_3O_{12}$

CUBIC ● ● ● ●

Properties: C – red to purple-red, light purple, black-brown; S – white; L – vitreous; D – transparent to translucent; DE – 3.5; H – 7-7.5; CL – none; F B conchoidal to uneven; M – isometric crystals, granular.

Origin and occurrence: Magmatic in some ultrabasic rocks, e.g. lherzolites, peridotites, kimberlites, eclogites and serpentinites; metamorphic in quartzites; also known from placers. It is associated with diopside, magnetite and diamond. It comes from many localities in ultrabasic rocks, like Trebenice and Mirunice, Czech Republic; Zoblitz, Germany; Madras, India; Kimberley, South Africa. Crystals up to 250 mm ($9^{13}/_{16}$ in) across were found in Dora Maria, the Alps, Italy.

Application: cut as a gemstone.

Almandine

GARNET GROUP

$Fe_3Al_2Si_3O_{12}$

CUBIC ● ● ● ●

Properties: C – red to purple-red, black-brown; S – white; L – vitreous; D – transparent to translucent; DE – 4.3; H – 7; CL – none; F B conchoidal to uneven; M B well-formed crystals, granular.

Origin and occurrence: Metamorphic in regionally metamorphosed rocks, as chlorite schists, gneisses,

Almandine, 38 mm x, Ötztal, Austria



Spessartine, 96 mm, Gilgit, Pakistan



Grossular, 17 mm x, Asbestos, Canada



mica schists and migmatites; magmatic in some granites and pegmatites; also in placers. Well-developed crystals up to 150 mm (6 in) across are known from Ishikawa pegmatites, Japan and Shingus, Pakistan. It comes from many mica schists and gneisses as crystals, up to about 50 mm (2 in), like Fort Wrangel, Alaska, USA; Ötztal, Austria; Bodo, Norway. It occurs in placers near Ratnapura, Sri Lanka.
Application: cut as a gemstone, abrasive material.

Spessartine

GARNET GROUP

$Mn_3Al_2Si_3O_{12}$

CUBIC ● ● ● ●

Properties: C – red, orange, light brown to yellowish; S – white; L – vitreous; D – transparent to translucent; DE – 4.3; H – 7-7.5; CL – none; F B conchoidal to uneven; M – perfect crystals, granular.
Origin and occurrence: Magmatic in granitic pegmatites and some granites; hydrothermal in cavities in rhyolites; metamorphic in some skarns and Mn-rich metamorphic rocks. Perfect crystals up to 30 mm (1$\frac{3}{16}$ in) across were found in granitic pegmatites in the Hercules mine, Ramona, California, USA; near Marienfluss river, Namibia and in rhyolite cavities in Nathrop, Colorado, USA.
Gemmy crystal fragments up to 50 mm (2 in) across were recently found in an undisclosed locality in Minas Gerais, Brazil.
Application: cut as a gemstone.

Grossular

GARNET GROUP

$Ca_3Al_2Si_3O_{12}$

CUBIC ● ● ● ●

Varieties: hessonite, tsavorite

Properties: C – red, green (tsavorite), orange, red-brown (hessonite) to colorless; S – white; L – vitreous; D – transparent to tranlucent; DE – 3.4; H – 6.5-7; CL – none; F B conchoidal to uneven; M – perfect crystals, granular.
Origin and occurrence: Metamorphic in Ca-rich, contact metamorphic rocks, skarns, rodingites; hydrothermal along the cracks in these rocks, associated with diopside, vesuvianite, wollastonite, scapolite and epidote. Perfect crystals about 30 mm (1$\frac{3}{16}$ in) across occur in the Jeffrey quarry, Asbestos, Quebec, Canada and Sierra de las Cruces, Coahuila, Mexico.
Tsavorite crystals up to 50 mm (2 in) across come from the Tsavo National Park, Kenya and Merelani Hills, Arusha, Tanzania. The other well-known localities are Ala, Italy and Ciclova, Romania. Grossular crystals up to 100 mm (4 in) in size in Vapenna, Czech Republic; Xalostoc, Mexico and Sandare, Mali.
Application: cut as a gemstone.

Andradite, 30 mm xx, Graham Co., U.S.A.



Andradite

GARNET GROUP

$Ca_3Fe^{3+}{}_2Si_3O_{12}$

CUBIC ● ● ● ●

Varieties: demantoid, melanite

Properties: C – dark red, black-brown, brown, green to yellow-green (demantoid), black-brown to black (melanite); S – white; L – vitreous; D – transparent to translucent; DE – 3.9; H – 6.5-7; CL – none; F B conchoidal to uneven; M B well-developed crystals, granular.
Origin and occurrence: Metamorphic in Ca and Fe rich contact metamorphosed rocks, skarns, rodingites; hydrothermal along the cracks of these rocks; magmatic in some alkaline igneous rocks, usually in the same localities as grossular. Crystals up to 40 mm ($1\frac{9}{16}$ in) across come from Sinerechenskoye, Russia. Fine crystals were also found in the Namgar mine, Usakos, Namibia and Ciclova, Romania. Fine melanite crystals occur in Magnet Cove, Arkansas, USA. Demantoid crystals up to 30 mm ($1\frac{3}{16}$ in) across known from Val Malenco, Italy and in the Bobrovka river basin, Ural mountains, Russia.
Application: demantoid is cut as a gemstone.

Demantoid, 3 mm xx, Bobrovka, Russia



Melanite, 5 mm xx, Rudnyi, Kazakhstan



Uvarovite, 2 mm xx, Sarany, Russia



Uvarovite

GARNET GROUP

$Ca_3Cr_2Si_3O_{12}$

CUBIC ● ●

Properties: C – dark emerald-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.9; H – 6.5-7; CL – none; F B conchoidal to uneven; M – perfect crystals, granular.
Origin and occurrence: Metamorphic and also hydrothermal are almost only limited to rocks with increased Cr content, ultrabasic rocks with chromite, serpentinites and skarns. It occurs as crystals up to 8 mm ($^{5}/_{16}$ in) across along cracks in chromite in Sarany, Ural mountains, Russia. Crystals up to 20 mm ($^{25}/_{32}$ in) across, come from Outokumpu, Finland. It is also known from Orford, Quebec, Canada.

Zircon

$ZrSiO_4$

TETRAGONAL ● ● ●

Varieties: jargon, hyacinth.

Properties: C – yellow (jargon), brown, yellow-brown, red-orange (hyacinth), red to colorless; S – white; L – vitreous, greasy to adamantine; D – transparent to translucent; DE – 4.7; H – 7.5; CL – imperfect; F B conchoidal to uneven; M – perfect long and short prismatic crystals, granular; LU – yellow; R B sometimes radioactive and usually metamict.
Origin and occurrence: Magmatic and metamorphic as an accessory mineral in different rock types; rarely hydrothermal in the Alpine-type and quartz veins; also in sediments and placers. Prismatic crystals up to 30 cm (12 in) across, occur in syenite pegmatites in Renfrew and Bancroft, Ontario, Canada. It is also known from Miass, Ural mountains and from Mount Vavnbed, Lovozero massif, Kola Peninsula, Russia. Classic occurrences in granitic pegmatites are Alto Ligonha, Mozambique; Arendal, Norway; Ytterby, Sweden and Jaguaraçu, Minas Gerais, Brazil. Gemmy zircons of different colors up to 80 mm ($3^{1}/_{8}$ in) in size come from placers near Ratnapura, Sri Lanka and elsewhere.
Application: hyacinth and jargon are cut as gemstones, Zr ore.

Zircon, 20 mm x, Vishnevogorsk, Ural Mts., Russia



Eulytite, 2 mm xx, Schneeberg, Germany

Sillimanite, 10 mm grains, Havlíčkův Brod, Czech Republic

Eulytine

$Bi_4Si_3O_{12}$

CUBIC ● ●

Properties: C – brown, yellow, gray, colorless; S – white; L – greasy; D – translucent; DE – 6.6; H – 4.5; CL – good; F B conchoidal to uneven; M – small dipyramidal crystals, radial aggregates, granular.
Origin and occurrence: Secondary in Bi deposits, typically associated with bismuth.
Its small crystals come from Horní Slavkov, Czech Republic; Schneeberg and Johanngeorgenstadt, Germany.

Euclase

$BeAlSiO_4(OH)$

MONOCLINIC ● ●

Properties: C – colorless, white, greenish, blue; S – white; L – vitreous; D – transparent to translucent; DE – 3.1; H – 7.5; CL – good; F B conchoidal to

Euclase, 42 mm, Minas Novas, Brazil



uneven; M – long prismatic crystals, radial aggregates, granular.
Origin and occurrence: Hydrothermal occurs in pegmatites, greisens and in quartz and Alpine-type veins; rare in placers. Well-formed crystals up to 80 mm ($3^{1}/_{8}$ in) in size known from Santa do Encoberto, Minas Gerais, Brazil. Blue crystals up to 50 mm (2 in) across occurred in the Last Hope Mine, Karoi, Zimbabwe. It also come from the sediments of Sanarka River, Ural mountains, Russia. Dark blue crystals up to 150 mm (6 in) across were found recently in the Chivor Mine, Colombia.
Application: locally cut as a gemstone.

Sillimanite

Al_2SiO_5

ORTHORHOMBIC ● ● ● ● ●

Properties: C – white, gray, greenish, yellowish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 6.5-7.5; CL – good; F – uneven; M – long prismatic crystals, fibrous aggregates, granular.
Origin and occurrence: Almost exclusively metamorphic in gneisses and migmatites; only rare magmatic in pegmatites and granites; also in placers. Typical rock-forming mineral, very commonly associated with andalusite. Typical localities are Bodenmais, Germany and Mar_íkov, Czech Republic. Gemmy crystals up to 20 mm ($^{25}/_{32}$ in) long are known from Rakwana-Deniyaya, Sri Lanka.

Andalusite

Al_2SiO_5

ORTHORHOMBIC ● ● ● ●

Varieties: chiastolite, viridine

Properties: C – pink, red-brown, red, gray, whitish, green (viridine); S- white; L – vitreous to dull; D – translucent to transparent; DE – 3.2; H – 6.5-7.5; CL – good; F – uneven; M – prismatic crystals, fibrous aggregates, granular, massive.
Origin and occurrence: Metamorphic in regionally and contact metamorphosed rocks; magmatic in pegmatites and granites, hydrothermal in quartzites. Typical rock-forming mineral, commonly associated with sillimanite, corundum and cordierite. Renowned localities are Lisens, the Alps, Austria; Bimbowrie, South Australia, Australia. Green gemmy crystals come from Morro do Chapeu, Bahia, Brazil. Viridine is known from Darmstadt, Germany.

Andalusite, 28 mm x, Aracuay, Minas Gerais, Brazil



Chiastolith, 20 mm, Bimbowrie, Australia



Kyanite
Al_2SiO_5

TRICLINIC ● ● ● ●

Properties: C – blue, gray, white, green, dark gray, colorless; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.6; H – 4.5-7.5; CL – good; F – uneven; M – prismatic to tabular crystals, fibrous aggregates, granular, massive.
Origin and occurrence: Almost only metamorphic in regionally metamorphosed rocks, mica schists, gneisses, granulites and eclogites; less frequently magmatic in pegmatites and granites; rarely hydrothermal in quartz veins. Typical rock-forming mineral, associated with andalusite and sillimanite. Blue columnar aggregates and crystals up to 150 mm (6 in) long occur in Barra do Salinas, Minas Gerais, Brazil. Other renowned localities are Pizzo Forno, Switzerland; Prilep, Macedonia; Keivy, Kola Peninsula, Russia.


Kyanite, 87 mm, Minas Gerais, Brazil


Topaz, 18 mm xx, Ghundao Hill, Pakistan

Topaz
$Al_2SiO_4(F,OH)$

ORTHORHOMBIC ● ● ●

Varieties: pycnite

Properties: C – colorless, blue, yellow, gray, white, greenish, pinkish, red; S – white; L – vitreous; D – transparent to translucent; DE – 3.6; H- 8; CL – good; F – uneven; M – perfect prismatic to tabular crystals, radial and columnar aggregates, granular.
Origin and occurrence: Magmatic in pegmatites and granites; hydrothermal in greisens, in rhyolite cavities, in quartz veins, also in placers. Topaz crystals in pegmatites are occasionally very large, like the crystal measuring 80 x 60 x 60 cm (31½ x 24 x 24 in) across from Fazenda do Funil; crystals

Topaz, 49 mm, Ramona, U.S.A.



up to 30 cm (12 in) from Virgem da Lapa, both Minas Gerais, Brazil. Blue, brownish and bicolored crystals up to 40 cm (15¾ in) long come from Volodarsk Volynskii, Ukraine. Other topaz localities are Iveland, Norway; Murzinka, Ural mountains, Russia; Little Three mine, Ramona, California; Pikes Peak, Colorado, USA; Gilgit, Pakistan; Spitzkopje, Namibia. Orange to red topaz (imperial topaz) comes from quartz veins near Ouro Preto, Minas Gerais, Brazil. Pink topaz crystals up to 70 mm (2¾ in) found at Mount Ghundao, Mardan, Pakistan. Important topaz specimens were also found in Schneckenstein, Germany; Thomas Range, Utah, USA; Nerchinsk, Siberia, Russia. Columnar aggregates of pycnite come from Cínovec, Czech Republic and Altenberg, Germany. *Application:* cut as a gemstone.

Pycnite, 60 mm, Cínovec, Czech Republic



Staurolite, 80 mm, Keivy, Kola, Russia



Staurolite

$Fe_2Al_9Si_4O_{22}(OH)_2$

ORTHORHOMBIC ● ● ● ●

Properties: C – dark to light brown, yellow; S – white; L – dull to vitreous; D – transparent to almost opaque; DE – 3.7; H – 7-7.5; CL – good; F – uneven; M – prismatic to tabular crystals and their combinations, granular.
Origin and occurrence: Metamorphic in regionally metamorphosed rocks, gneisses and mica schists; rare magmatic in granites; also in placers, commonly associated with almandine, andalusite and kyanite. Crystals up to 50 mm (2 in) across come from Pizzo Forno, Switzerland. It is also known from Rio Arriba, New Mexico, USA. Its cross-like twins, up to 200 mm ($7\frac{7}{8}$ in) across, occur in Keivy, Kola Peninsula, Russia and Morbihan, France.

Sapphirine, 26 mm, Vohimena, Madagascar



Sapphirine

$Mg_2Al_4SiO_{10}$

MONOCLINIC ● ●

Properties: C – dark to light blue, green; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.5; H – 7.5; CL – imperfect; F – uneven; M – tabular crystals, granular.
Origin and occurrence: Metamorphic in regionally metamorphosed rocks, rich in Al and Mg and poor in Si, associated with spinel and corundum. Crystals up to 40 mm ($1\frac{9}{16}$ in) across come from Fiskenaesset, Greenland; Betroka and Androy, Madagascar. Other localities include Val Codera, Italy and Enderby Land, Antarctica.

Chondrodite, 15 mm x, Brewster, U.S.A.



Chondrodite

$Mg_5Si_2O_8(OH,F)_2$

MONOCLINIC ● ● ●

Properties: C – yellow, greenish, brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 6-6.5; CL – imperfect; F – uneven; M – crystals of different habits, granular.
Origin and occurrence: Metamorphic in contact and regionally metamorphosed carbonate rocks; rare magmatic in carbonatites, typically associated with spinel, chlorite and phlogopite. Perfect crystals up to 50 mm (2 in) long come from the Tilly Foster mine, Brewster, New York, USA. Other localities are Pargas, Finland; Monte Somma, Italy; Riverside, California, USA.

Clinohumite

$Mg_9Si_4O_{16}(OH,F)_2$

MONOCLINIC ● ● ●

Properties: C – yellow, red, brown, white; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 6; CL – imperfect; F – uneven; M – crystals of different habits, granular.
Origin and occurrence: Metamorphic in contact and regionally metamorphosed carbonate rocks, serpentinites and talc schists, associated with spinel, chlorite, forsterite, serpentine and phlogopite. Gemmy yellow crystals up to 30 mm ($1^{3}/_{16}$ in) across come from Kukh-i-Lal, Pamir, Tajikistan. Other localities are Pargas, Finland; Monte Somma, Italy; Jensen quarry, California, USA.

Clinohumite, 19 mm, Kukh-i-lal, Tadzhikistan



Chapmanite

$SbFe^{3+}_2Si_2O_8(OH)$

MONOCLINIC ● ●

Properties: C – olive-green to dark yellow; S – yellowish to yellow; L -dull; D – translucent; DE – 3.7; H – 2.5; CL – imperfect; F – uneven; M – elongated crystals, massive.
Origin and occurrence: Hydrothermal and secondary in the cracks of rocks, sometimes with stibnite. Its massive aggregates occur in Smilkov near Votice, Czech Republic; in the Keely mine, Cobalt, Ontario, Canada.

Chapmanite, 4 mm, Pernek, Slovakia



Braunite, 60 mm, Langban, Sweden



Braunite

$Mn^{2+}Mn^{3+}_6SiO_{12}$

TETRAGONAL ● ● ●

Properties: C – black, black-gray, black-brown; S – gray; L – submetallic to metallic; D – opaque; DE – 4.7; H – 6-6.5; CL – perfect; F – uneven to conchoidal; M – dipyramidal crystals, granular.
Origin and occurrence: Metamorphic in regionally and contact metamorphosed rocks; hydrothermal in sedimentary rocks rich in Mn and in hydrothermal veins, associated with hausmanite, pyrolusite and other Mn minerals. Its perfect crystals up to 70 mm (2¾ in) long, come from Kacharhavee and Tirodi, India. It is also known from Langban, Sweden; Ilfeld and Ilmenau, Germany; St. Marcel, Italy; Tizi Bashkun, Morocco.
Application: Mn ore.

Thaumasite, 3 mm aggregate, Maglovec, Slovakia



Thaumasite

$Ca_6Si_2(CO_3)_2(SO_4)_2(OH)_{12} \cdot 24\,H_2O$

HEXAGONAL ● ●

Properties: C – white to colorless; S – white; L – vitreous to dull; D – transparent to translucent; DE – 1.9; H – 3.5; CL – imperfect; F – uneven; M B acicular aggregates, granular, massive; LU – white.
Origin and occurrence: Hydrothermal or metamorphic in contact metamorphosed carbonate rocks, usually associated with other Ca silicates and carbonates, like ettringite and prehnite. Typical localities are Crestmore, California; West Paterson, New Jersey, USA; Langban, Sweden; N'Chwaning mine No. 2, Kuruman, South Africa.

Titanite

$CaTiOSiO_4$

MONOCLINIC ● ● ● ●

Properties: C – colorless, yellow, brown, green, gray to black; S – white; L – vitreous to dull; D – transparent, translucent to opaque; DE – 3.5; H – 5-5.5; CL – good; F – uneven to conchoidal; M – tabular crystals and their combinations, granular, massive.
Origin and occurrence: Metamorphic and magmatic as a common accessory mineral in many igneous and

Fersmanite, 10 mm x, Khibiny Massif, Kola, Russia



Titanite, 20 mm xx, Stubachtal, Austria

metamorphic rocks and pegmatites; hydrothermal in the Alpine-type veins; also in placers.

The most beautiful crystals up to 180 mm ($7^{1}/_{16}$ in) long occur in Alpine-type veins in Tavetsch and Binntal, Switzerland; Zillertal and Felbertal, Austria; Dodo, Polar Ural, Russia. Large, poorly developed crystals weighing up to 40 kg (88 lb), come from Eganville, Ontario, Canada and Rossie, New York, USA.

Chloritoid, 30 mm, Ille de Croix, France

Fersmanite

$(Na,Ca)_4(Ti,Nb)_2Si_2O_{11}(OH,F)_2$

TRICLINIC ● ●

Properties: C – light to dark brown; S -white; L – vitreous to dull; D – translucent; DE – 3.5; H – 5-5.5; CL – none; F – uneven to conchoidal; M – tabular crystals.

Origin and occurrence: Magmatic to hydrothermal in alkaline pegmatites together with pectolite, apatite and sulfides. Crystals up to 30 mm ($1^{3}/_{16}$ in) across known from Mount Eveslogchorr, Khibiny massif, Kola Peninsula, Russia.

Chloritoid

$Fe_2Al_4Si_2O_{10}(OH)_2$

MONOCLINIC, TRICLINIC ● ● ●

Properties: C – dark gray, gray-green to black-green; S – gray; L – vitreous to dull; D – translucent; DE – 3.6; H – 6.5; CL – perfect; F – uneven to conchoidal; M – tabular crystals, foliated and scaly aggregates, granular.

Origin and occurrence: Metamorphic in some mica schists and phyllites; hydrothermal alteration product in lavas. Typical localities are Zermatt, Switzerland; Ottrez, Belgium; Pregraten, Austria.

Datolite, 30 mm xx, Dalnegorsk, Russia



Datolite

$CaBSiO_4(OH)$

MONOCLINIC ● ● ●

Properties: C – white to colorless, yellowish, greenish, gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 5-5.5; CL – none; F – uneven to conchoidal; M – prismatic to tabular crystals, nodules, granular.

Origin and occurrence: Metamorphic and hydrothermal in contact metamorphosed rocks, in cavities in volcanic rocks, in ore veins and pegmatites. It is commonly associated with zeolites, prehnite, calcite and also with tourmaline. Prismatic and tabular crystals up to 100 mm (4 in) long occur in Dalnegorsk, Russia. Other typical localities are West Paterson, New Jersey; Keweenaw Peninsula, Michigan, USA; Haslach, Germany; Charcas, San Luis Potosi, Mexico.

Gadolinite-(Y)

$Y_2FeBe_2Si_2O_{10}$

MONOCLINIC ● ●

Properties: C – black, dark red, brown, greenish; S – gray-green; L – vitreous to greasy, D – transparent to translucent; DE – 4.4; H – 6.5-7; CL – none; F –

Gadolinite-(Y), 60 mm, Hitterö, Norway



Howlite, 30 mm, California, U.S.A.



Dumortierite, 60 mm, Dehesa, U.S.A.



conchoidal; M – prismatic crystals, granular; R – locally metamict.
Origin and occurrence: Magmatic in granites and pegmatites, locally associated with fluorite and allanite; rare hydrothermal in the Alpine-type veins. Aggregates, up to 40 cm (15¾ in) across come from Hittero, Norway. Barringer Hill and Clear Creek, Texas, USA yielded aggregates, weighing up to 90 kg (198 lb). Other famous localities are Blatchford Lake, Northwest Territories, Canada; Baveno, the Alps, Italy; Iveland, Evje, Norway.

Kornerupine

$Mg_4Al_6(Si,Al,B)_5O_{21}(OH)$

ORTHORHOMBIC ● ●

Properties: C – colorless, white, greenish, gray, brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 6.5-7; CL – none; F – conchoidal; M – prismatic crystals, radial aggregates, granular.
Origin and occurrence: Metamorphic in strongly metamorphosed rocks, as granulites. Crystals up to 230 mm ($9\frac{1}{16}$ in) across known from Fiskenaesset, Greensland. It also occurs in Lac Ste-Marie, Quebec, Canada; Waldheim, Germany; Itrongay, Madagascar.

Dumortierite

$(Al,Ti,Mg)Al_6BSi_3O_{16}(O,OH)_2$

ORTHORHOMBIC ● ● ●

Properties: C – purple, pink, blue, brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 8.5; CL – good; F – uneven; M – prismatic crystals, radial and acicular aggregates, massive.
Origin and occurrence: Metamorphic in some Al-rich metamorphic rocks, e.g. in migmatites and gneisses; magmatic in granites and pegmatites; hydrothermal in altered rocks. It comes from Dehesa, California; Rochester, Nevada, USA; Beaunan, France; crystals are known from the vicinity of Kutna Hora, Czech Republic; Soavina, Madagascar.

Howlite

$Ca_2B_5SiO_9(OH)_5$

MONOCLINIC ● ●

Properties: C – white; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.5; H – 3.5; CL – good; F – uneven; M – tabular crystals, nodules, massive.
Origin and occurrence: Hydrothermal in borate deposits, associated with ulexite and colemanite. Crystals, several cm across, come from the vicinity of Bras d'Or Lake, Nova Scotia, Canada. It occurs also in Lang and Daggett, California, USA.

Kornerupine, 90 mm, Lac Ste.-Marie, Canada



Cuprosklodowskite, 82 mm, Musonoi, Zair



Cuprosklodowskite

$Cu(UO_2)_2Si_2O_7 . 6 H_2O$

MONOCLINIC ● ●

Properties: C – various hues of green; S – greenish; L – vitreous to dull; D – transparent to translucent; DE – 3.8; H – 4; CL – good; F – uneven; M – radial, acicular aggregates, thin coatings, granular, massive; R – strong radioactive.

Origin and occurrence: Secondary in the oxidation zone of U deposits, associated with autunite, torbernite, uranophane and other U secondary minerals. Crystals, up to several cm long, come from

Uranophane, 125 mm, Brewster, Texas, U.S.A.

Kasolite, 30 mm, Musonoi, Zair

the Mashamba West mine, Musonoi, Zaire. It also occurred in Jachymov, Czech Republic.

Uranophane

$Ca(UO_2)_2Si_2O_7 . 6 H_2O$

MONOCLINIC ● ● ●

Properties: C – various hues of yellow to brown; S – yellowish; L – vitreous to dull; D – transparent to translucent; DE – 3.9; H – 2.5; CL – good; F – uneven; M – radial, acicular aggregates, thin coatings, granular, massive; LU – yellow-green; R – strong radioactive.
Origin and occurrence: Secondary in the oxidation zone of U deposits as a product of uraninite alteration, associated with autunite, torbernite and other secondary U minerals. Needles up to 10 mm ($^3/_8$ in) long, come from Musonoi, Shinkolobwe, Zaire.
It is also known from the Faraday mine, Bancroft, Ontario, Canada. It occurs in Wolsendorf, Germany, as well as in Jachymov, Czech Republic.

Kasolite

$Pb(UO_2)SiO_4 . H_2O$

MONOCLINIC ● ●

Properties: C – various hues of yellow, green to brown; S – yellowish; L – vitreous to dull; D – translucent to opaque; DE – 6.2; H – 4.5; CL – good; F – uneven; M – prismatic crystals, radial and acicular aggregates, thin coatings, granular, massive; R – strong radioactive.
Origin and occurrence: Secondary mineral in the oxidation zone of U deposits. It is a product of uraninite alteration and is associated with uranophane, torbernite and U hydroxides. Crystals up to 10 mm ($^3/_8$ in) long occur in Shinkolobwe, Kasolo, Zaire and Mounana, Gabon.

Akermanite

$Ca_2MgSi_2O_7$

TETRAGONAL ● ● ●

Properties: C – white, gray, green, brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.9; H – 5.5; CL – good; F – uneven to conchoidal; M – short prismatic crystals, granular.
Origin and occurrence: Magmatic in volcanic basic rocks; metamorphic in contact metamorphosed marbles. A typical representative of localities in marbles is Crestmore, California, USA. It occurs also in Ca-rich volcanic rocks in Velardena, Mexico.

Akermanite, 5 mm xx, Mt. Vesuvius, Italy



Gehlenite

$Ca_2Al_2SiO_7$

TETRAGONAL ● ● ●

Properties: C – white, gray, yellowish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 5-6; CL – good; F – uneven to conchoidal; M – short prismatic crystals, granular.
Origin and occurrence: Magmatic in volcanic basic rocks; metamorphic in contact metamorphic marbles.
It occurs in Crestmore, California, USA; Monzoni, Italy; Oraviza, Romania and elsewhere.

Gehlenite, 80 mm, Vata de Sus, Romania



Ilvaite, 20 mm xx, Dalnegorsk, Russia



Bertrandite, 36 mm, Mt.Antero, U.S.A.



Ilvaite

$CaFe^{2+}{}_2Fe^{3+}Si_2O_8(OH)$

ORTHORHOMBIC ● ● ●

Properties: C – black to black-gray; S – black; L – submetallic to dull; D – opaque; DE – 4.1; H – 5.5-6; CL – good; F – uneven; M – prismatic crystals, granular.
Origin and occurrence: Metamorphic and hydrothermal in contact metamorphosed Fe, Zn and Cu deposits. Prismatic crystals up to 100 mm (4 in) long come from Rio Marina, Elba, Italy. Crystals up to 30 cm (12 in) long are known from Serifos Island, Greece. Crystals, several cm long occur also in Dalnegorsk, Russia and in the Laxey mine, Idaho, USA.

Bertrandite

$Be_4Si_2O_7(OH)_2$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.6; H – 6-7; CL – perfect; F – uneven; M – tabular crystals and their combinations, radial aggregates, granular, massive.
Origin and occurrence: Hydrothermal in granitic pegmatites, greisens and in hydrothermal veins, together with beryl, also as pseudo-morphs after beryl. Tabular crystals up to 50 mm (2 in) across occur in Conselheira Pena, Minas Gerais, Brazil. It is known from Kounrad and Kara-Oba, Kazakhstan in crystals up to 30 mm (1³/₁₆ in) across. It also comes from Stoneham, Maine, USA; Písek, Czech Republic and Iveland, Norway.
Application: the most important Be ore.

Hemimorphite

$Zn_4Si_2O_7(OH)_2 . H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish, greenish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 4.5-5; CL – perfect; F – uneven; M – tabular crystals and their combinations, botryoidal and radial aggregates, granular, massive.
Origin and occurrence: Secondary in the oxidation zone of Zn deposits, associated with sphalerite, smithsonite and cerussite. Crystals up to 100 mm (4 in) long come from Bisbee, Arizona, USA.. It is also from the El Potosi Mine, Santa Eulalia, Chihuahua, Mexico; Bleiberg, Austria; Cho-Dien, Vietnam.
Application: Zn ore.

Hemimorphite, 30 mm xx, Mapimi, Mexico



Lamprophylite

$Na_2Sr_2Ti_3Si_4O_{16}(OH,F)_2$

MONOCLINIC ● ●

Properties: C – brown to dark brown; S - white; L – vitreous to submetallic; D – translucent; DE – 3.5; H – 2-3; CL – perfect; F – uneven; M – tabular crystals, radial aggregates.

Origin and occurrence: Magmatic in alkaline syenites and their pegmatites, associated with nepheline, aegirine and eudialyte. The best crystals up to 150 mm (6 in) long come from Mount Flora, Lovozero massif, Kola Peninsula, Russia. It is also known from Langesundsfjord, Norway and Mont St.-Hilaire, Quebec, Canada.

Hemimorphite, 26 mm, Arizona, U.S.A.



Lamprophyllite, 50 mm xx, Lovozero Massif, Kola, Russia



Clinozoisite, 36 mm, Eden Mills, U.S.A.

Clinozoisite

$Ca_2Al_3Si_3O_{12}(OH)$

MONOCLINIC ● ● ● ●

Properties: C – colorless, yellowish, green, pink; S – white; L – vitreous to dull; PS – transparent to translucent; DE – 3.4; H – 6.5; CL – good; F – uneven; M – prismatic crystals, columnar, radial aggregates, granular, massive.
Origin and occurrence: Metamorphic and hydrothermal in contacts of marbles and in the Alpine-type veins. Prismatic crystals up to 60 mm ($2^{3}/_{8}$ in) long come from Radoy Island, Norway. It comes also from Eden Mills, Vermont; Allens Park, Colorado, USA; Pinos Altos, Baja California, Mexico.

Epidote

$Ca_2(Al,Fe^{3+})_3Si_3O_{12}(OH)$

MONOCLINIC ● ● ● ● ●

Properties: C – green, brown, greenish, yellow-green; S – white; L – vitreous to dull; D – transparent to translucent, locally opaque; DE – 3.4; H – 6-7; CL – good; F – uneven; M – prismatic crystals, columnar and radial aggregates, granular, massive.
Origin and occurrence: Metamorphic in marble/granite contacts; hydrothermal in the Alpine-type veins and in hydrothermally altered rocks, typically associated with albite, prehnite and amphibole. Its green crystals up to 140 mm (5½ in) long, were found in Sobotín, Czech Republic. Perfect crystals up to 100 mm (4 in) across come from Knappenwand, Austria. Thick tabular crystals occur in Prince of Wales Island, Alaska, USA. Fine crystals, resembling Austrian crystals, were found recently in Alchuri, Shigar, Pakistan. Fine columnar aggregates of crystals are known from Pampa Blanca, Peru and also reported from Arendal, Norway.

Piemontite

$Ca_2(Al,Mn^{3+})_3Si_3O_{12}(OH)$

MONOCLINIC ● ●

Properties: C – red-brown to black, crimson, red-yellow; S – white; L – vitreous to dull; D – translucent, locally opaque; DE – 3.5; H – 6; CL – good; F – uneven; M – prismatic crystals, radial aggregates, granular.
Origin and occurrence: Metamorphic in shales and Mn-rich metamorphic rocks; rare magmatic in rhyolites and pegmatites. Needles up to 30 mm ($1^{3}/_{16}$

Epidote, Dashkesan, Azerbaidzhan

Epidote, 50 mm, Knappenwand, Austria



in) long come from St. Marcel, Piedmont, Italy and Otakiyama, Japan.

Allanit-(Ce)

$(Ca,Ce,Y)_2(Al,Fe^{3+})_3Si_3O_{12}(OH)$

MONOCLINIC ● ● ●

Properties: C – black to dark brown; S – light gray; L – greasy to submetallic; D – translucent to opaque; DE – 3.9; H – 5.5-6; CL – none; F – conchoidal to uneven; M – tabular crystals, granular; R – usually metamict.

Origin and occurrence: Magmatic in pegmatites and granites; metamorphic in various types of metamorphic rocks, e.g. migmatites, amphibolites and gneisses. Grains, up to 70 cm ($27^{9}/_{16}$ in) across found in pegmatites near Bancroft, Ontario, Canada. Also occurs in Barringer Hill, Colorado; Amelia district, Virginia, USA; Arendal and Hittero, Norway; Ytterby and Riddarhyttan, Sweden; Yates mine, Quebec, Canada.

Piemontite, 45 mm, Todyryact, Morocco



Allanite-(Ce), 40 mm, Vizcaya, Spain



Tanzanite, 37 mm, Arusha, Tanzania



Zoisite, 60 mm, Weisenstein, Germany



Zoisite

$Ca_2Al_3Si_3O_{12}(OH)$

ORTHORHOMBIC ● ● ●

Varieties: thulite, tanzanite

Properties: C – colorless, yellowish, green, pink, red (thulite), blue (tanzanite); S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 6.5; CL – good; F – uneven; M – prismatic crystals, radial aggregates, granular.
Origin and occurrence: Metamorphic in regionally metamorphosed Ca-rich rocks, mainly in pyroxenic gneisses, amphibolites and in marble contacts. It is known from many localities like Saualpe, Austria; Zermatt, Switzerland; Lexviken, Norway (thulite); Traversella, Italy; Alchuri, Pakistan; Merelani Hills, Arusha, Tanzania (tanzanite), where crystals up to 70 mm (2¾ in) long were found.
Application: tanzanite and thulite are cut as gemstones.

Thulite, 40 mm, Lexviken, Norway



Vesuvianite

$Ca_{19}(Al,Mg,Fe)_{13}Si_{18}O_{68}(OH,F,O)_{10}$

TETRAGONAL ● ● ●

Properties: C – brown, yellowish, green, blue, purple, colorless; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 6-7; CL – imperfect; F – uneven to conchoidal; M – prismatic to tabular crystals, columnar aggregates with radial structure, granular, massive.

Origin and occurrence: Metamorphic and hydrothermal in contact metamorphosed Ca-rich rocks, mainly in skarns, in marble contacts, also in rodingites; rarely magmatic in alkaline rocks. It is usually associated with grossular, wollastonite and diopside. Perfect green crystals up to 180 mm ($7\frac{1}{16}$ in) long and purple crystals up to 70 mm ($2\frac{3}{4}$ in) long come from the Jeffrey quarry, Asbestos, Quebec, Canada. It is also known from Hazlov, Czech Republic; Crestmore, California, Franklin, New Jersey, USA; Monzoni, Italy.

Vesuvianite, 110 mm, Asbestos, Canada



Viluite

$Ca_{19}(Al,Mg)_{13}B_5Si_{18}O_{68}(O,OH)_{10}$

TETRAGONAL ●

Properties: C – dark green, gray-brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 6; CL – imperfect; F – uneven to conchoidal; M – prismatic crystals.

Origin and occurrence: Metamorphic in serpentinized skarn, associated with grossular. Its perfect prismatic crystals up to 50 mm (2 in) long are only known from the Vilui River basin, Yakutia, Russia.

Viluite, 30 mm xx, Vilui River, Russia

Benitoite

$BaTiSi_3O_9$

TRIGONAL ● ●

Properties: C – blue, pink, white, colorless; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.6; H – 6-6.5; CL – imperfect; F – uneven to conchoidal; M – prismatic to tabular crystals, mainly with trigonal cross-section; LU – bluish.
Origin and occurrence: Hydrothermal in veins, cross-cutting serpentinites, always associated with neptunite and natrolite. Its classic locality is the Benitoite Gem mine, San Benito Co., California, USA, where it forms tabular crystals up to 40 mm ($1^{9}/_{16}$ in) across.

Catapleiite

$Na_2ZrSi_3O_9 . 2 H_2O$

HEXAGONAL ● ●

Properties: C – light yellow, yellow-brown, pink, brown, blue; S – white; L – vitreous to dull; D – transparent to opaque; DE – 2.8; H – 5-6; CL – good; F – uneven; M – thin tabular crystals, lamellar aggregates.
Origin and occurrence: Magmatic in nepheline syenites and their pegmatites, together with aegirine, titanite, nepheline and microcline. It occurs in Mont St.-Hilaire, Quebec, Canada, as tabular crystals up to 150 mm (6 in) across. Crystals up to 30 mm ($1^{3}/_{16}$ in) across come from Mount Yukspor, Khibiny massif, Kola Peninsula, Russia. It is also known from Langesundsfjord, Norway; Magnet Cove, Arkansas, USA.

Eudialyte

$Na_4(Ca,Fe,Ce,Mn)_2ZrSi_6O_{18}(OH,Cl)$

TRIGONAL ● ●

Properties: C – red, pink to brown; S – white; L – vitrous to dull; D – transparent to translucent; DE – 2.8; H – 5-5.5; CL – imperfect; F – uneven; M – prismatic and tabular crystals, granular.
Origin and occurrence: Magmatic in nepheline syenites and their pegmatites, associated with aegirine, nepheline and microcline. Crystals up to 80 mm ($3^{1}/_{8}$ in) across come from Mount Kukisvumchorr, Khibiny massif, Kola Peninsula, Russia. Crystals up to 50 mm (2 in) across are also known from Mont St.-Hilaire, Quebec, Canada. It also occurs in Langesundsfjord, Norway and in Los Island, Guinea.

Ferroaxinite

$Ca_2FeAl_2BSi_4O_{15}(OH)$

TRICLINIC ● ● ●

Properties: C – brown to purple- brown, light purple; S – white; L – vitreous to dull; D – trans-

Benitoite, 28 mm x, San Benito Co., U.S.A.



Catapleiite, 37 mm, Mont St.-Hilaire, Canada



Eudialyte, 20 mm grain, Khibiny Massif, Kola, Russia



Ferroaxinite, 62 mm, Khapalu, Pakistan



parent to translucent; DE – 3.3; H – 6. 5-7; CL – good; F – uneven to conchoidal; M – tabular crystals, platy aggregates, granular, massive.

Origin and occurrence: Metamorphic and hydrothermal in contacts of marbles and granites, associated with clinozoisite, prehnite, calcite and actinolite, also in the Alpine-type veins and pegmatites. Perfect tabular crystals up to 150 mm (6 in) across come from Puiva, Polar Ural, Russia. Other renowned localities are Obira, Japan; Bourg d'Oisans, France; Monte Scopi, Switzerland.

Tinzenite

$Ca(Mn,Fe)_2Al_2BSi_4O_{15}(OH)$

TRICLINIC ● ●

Properties: C – yellow, orange to red; S – white; L – vitrous to dull; D – transparent to translucent; DE – 3.3; H - 6.5-7; CL – good; F - uneven to conchoidal; M – tabular crystals, platy and fibrous aggregates, granular, massive.

Origin and occurrence: Hydrothermal in the Alpine-type veins, cross-cutting a rock, rich in braunite. It comes from Tinzen, Val d'Err, Switzerland and in the Cassagna mine, Genova, Italy.

Tinzenite, 10 mm xx, Val Graveglia, Italy



Beryl

$Be_3Al_2Si_6O_{18}$

HEXAGONAL ● ● ● ●

Varieties: emerald, aquamarine, heliodor, morganite, goshenite, red beryl (bixbite).

Properties: C – variable in different varieties; common beryl – mostly yellow, yellow-green, light green to white, rare blue; varieties: emerald – dark emerald-green; aquamarine – light to dark blue-green: morganite – pink; heliodor – light yellow to yellow-green; goshenite – white to colorless; red beryl B red; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.6; H – 7.5-8; CL – imperfect; F – uneven to conchoidal; M – long prismatic to tabular crystals, columnar and radial aggregates, granular, massive.

Origin and occurrence: Magmatic in pegmatites and granites; hydrothermal in greisens, in cavities in rhyolite, in quartz veins; metamorphic in mica schists. Perfect prismatic crystals of common beryl up to 9 m (29 ft 6 in) long found in the Etta mine, Keystone, South Dakota, USA. Crystals weighing up to 177 tons, come from Namivo, Alto Ligonha, Mozambique. Other localities are Pici, Brazil; Iveland, Norway; Antsirabe, Madagascar. Emerald crystals occur in mica-schists, marbles and ultrabasic rocks, associated with other Be minerals, phenakite and

Emerald, 30 mm x, Boyaca, Colombia



Emerald, 30 mm, Ural Mts., Russia



chrysoberyl. Beautiful dark green transparent crystals are known from Malyshevo, Ural Mts., Russia; Muzo and Coscuez, Colombia; Habachtal, Austria, where the largest crystals reach up to 120 mm ($4^{11}/_{16}$ in) in size. Aquamarine is mainly known from pegmatites and hydrothermal veins, commonly

Emerald, 90 mm, Muzo, Colombia



Aquamarine, 97 mm, Koronel Hurta, Brazil



Aquamarine, 158 mm, Shingus, Pakistan



Heliodor, 87 mm, Volodarsk Volynskii, Ukraine

associated with tourmaline, quartz and albite. Intense blue crystals are known from many pegmatites in Minas Gerais, Brazil, where in the Marambaia mine, crystals, up to 70 cm ($27\frac{9}{16}$ in) long and weighing up to 110 kg (242 lb) found. Very beautiful gemmy crystals over 30 cm (12 in) long recently occurred in the Medina Mine. It also come from Murzinka, Ural mountains and Adun Chilon, Siberia, Russia. It also comes from Spitzkopje, Namibia; Gilgit, Pakistan and elsewhere. Morganite is a typical mineral of granitic pegmatites, where it occurs in mainly in cavities, usually associated with color varieties of tourmaline, quartz and albite. Its tabular crystals up to 100 mm (4 in) across found in the White Queen mine, Pala, California, USA. Smaller crystals come from San Piero in Campo, Elba, Italy. Crystals up to 50 cm (20 in) across reported from several localities in Minas Gerais, Brazil. Heliodor also occurs in pegmatite cavities, hydrothermal veins and in gneisses, commonly associated with quartz and albite. Prismatic crystals up to 200 mm ($7\frac{7}{8}$ in) long, come from Volodarsk Volynskii, Ukraine. It is also known from Nerchinsk, Siberia, Russia and several mines in Minas Gerais, Brazil. Goshenite occurs only in pegmatites. Its prismatic crystals come from Goshen, Massachusetts,

Heliodor, 26 mm x, Pamir, Tadzhikistan

Goshenite, 39 mm, Apalygun, Pakistan



Red beryl, 17 mm x, Wah Wah Mts., U.S.A.



USA; San Piero in Campo, Elba, Italy. Red beryl occurs in Violet Claims, Wah Wah mountains, Utah, USA, where crystals up to 50 mm (2 in) were found. *Application:* Be ore, color varieties are cut as gemstones.

Morganite, 43 mm x, San Diego Co., U.S.A.



Bazzite, 70 mm, Tordal, Norway



Bazzite

$Be_3(Sc,Al)_2Si_6O_{18}$

HEXAGONAL ●

Properties: C – light to intense blue; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.8; H – 6.5; CL – imperfect; F – uneven to conchoidal; M – long prismatic crystals, columnar and radial aggregates.

Origin and occurrence: Hydrothermal in the Alpine-type veins and pegmatites. Crystals up to 20 mm (25/32 in) long come from Tørdal, Norway. It is also known from Lago Maggiore, Italy and St. Gotthard, Switzerland.

Cordierite

$Mg_2Al_4Si_5O_{18}$

ORTHORHOMBIC ● ● ● ●

Varieties: iolite (gemmy blue)

Sekaninaite, 40 mm x, Dolni Bory, Czech Republic



Properties: C – blue, purple, gray, gray-green, gray-brown, trichroic; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.5; H – 7-7.5; CL – imperfect; F – uneven to conchoidal; M – short prismatic crystals, granular.

Origin and occurrence: Metamorphic in migmatites and gneisses and in contact cherts; magmatic in granites and granitic pegmatites, usually associated with andalusite and sillimanite, also known from placers. It is a typical rock-forming mineral. Its prismatic crystals are very rare. Poorly developed transparent crystals up to 200 mm (7 7/8 in) long come from Naverberg, Sweden. It also occurs in Orijarvi, Finland; Kragero, Norway; Bodenmais, Germany. Gemmy pebbles are known from the vicinity of Ratnapura, Sri Lanka.

Sekaninaite

$Fe_2Al_4Si_5O_{18}$

ORTHORHOMBIC ● ● ●

Properties: C – blue, purple, strongly pleochroic; S

Cordierite, 50 mm, Fishtail Lake, Canada



Dravite, 27 mm, Gujarkkot, Nepal



– white; L – vitreous to dull; D – transparent to translucent; DE – 2.8; H – 7-7.5; CL – imperfect; F – uneven to conchoidal; M – short prismatic crystals, granular.

Origin and occurrence: Magmatic in granitic pegmatites and some granites, associated with andalusite and tourmaline; metamorphic in gneisses and migmatites. Conical, imperfect crystals, up to 70 cm (27$\frac{9}{16}$ in) long typically come from Dolni Bory, Czech Republic; also known from San Piero in Campo, Elba, Italy.

Dravite

TOURMALINE GROUP

$NaMg_3Al_6(BO_3)_3Si_6O_{18}(OH)_4$

TRIGONAL ● ● ● ●

Properties: C – light to dark black-brown, blue, colorless, commonly pleochroic; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 7-7.5; CL – none; F – uneven to conchoidal; M – long to short prismatic crystals, columnar to acicular aggregates, granular.

Origin and occurrence: Metamorphic in migmatites, gneisses, mica schists, marbles and in contact metasomatic rocks; magmatic in some granitic pegmatites; hydrothermal in quartz veins and ore veins, also known from placers. Brown to dark brown perfect crystals up to 200 mm (7$\frac{7}{8}$ in) long come from mica schists near Dravograd, Slovenia. It is also known from marbles in Gouverneur, New York, USA. Crystals up to 150 mm (6 in) across found in Yinnietharra, Western Australia, Australia. Crystals up to 50 mm (2 in) long were recently found in Gujarkot, Nepal.

Application: transparent crystals are cut as gemstones.

Buergerite, 12 mm x, San Luis Potosí, Mexico



Buergerite

TOURMALINE GROUP

$NaFe^{3+}{}_3Al_6(BO_3)_3Si_6O_{21}F$

TRIGONAL ●

Properties: C – black, strongly pleochroic; S – yellow-brown; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 7; CL – none; F – uneven to conchoidal; M B prismatic crystals, granular.

Origin and occurrence: Hydrothermal in rhyolites. Its black crystals, up to 40 mm (19/16 in) long, are known from Mexquitic, San Luis Potosi, Mexico.

Schorl, 40 mm, Gilgit, Pakistan



Schorl

TOURMALINE GROUP

$NaFe_3Al_6(BO_3)_3Si_6O_{18}(OH)_4$

TRIGONAL ●●●●

Properties: C – black, black-brown, blue-black, strongly pleochroic; S – white; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 7-7.5; CL – none; F – uneven to conchoidal; M – long to short prismatic crystals, columnar to acicular aggregates, granular, massive.

Origin and occurrence: Magmatic in granites and granitic pegmatites; hydrothermal in greisens, in quartz and ore veins; metamorphic in migmatites, gneisses, mica schists and tourmalinites; also known from placers. It is usually associated with muscovite, quartz and albite. Perfect black crystals come from many pegmatite localities.

Its long prismatic crystals, up to 5 m long, come from Arendal, Norway. Very good crystals are also known from Kaatiala, Finland; Dolni Bory, Czech Republic; Conselheira Pena and Galileia, Minas Gerais, Brazil.

Povondraite

TOURMALINE GROUP

$NaFe^{3+}_3Mg_2Fe^{3+}_4(BO_3)_3Si_6O_{18}(OH)_4$

TRIGONAL ●

Properties: C – black; S – gray; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 7; CL –

Povondraite, 60 mm, Alto Chapare, Bolivia



Elbaite, 115 mm, Tourmaline Queen Mine, U.S.A.



none; F – uneven to conchoidal; M – short prismatic crystals, granular.
Origin and occurrence: Hydrothermal along the cracks in metamorphosed evaporites. Its black crystals up to 10 mm ($^{3}/_{8}$ in) long typically come from Alto Chapare, Cochabamba, Bolivia.

Elbaite

TOURMALINE GROUP

$Na(Li_{1.5}Al_{1.5})Al_6(BO_3)_3Si_6O_{18}(OH)_3F$

TRIGONAL ● ● ●

Varieties: rubellite, verdelite, indiccolite, achroite

Properties: C – varies in different varieties, rubellite – pink to red; verdelite – various hues of green; indiccolite – blue; achroite – colorless, other colors include yellow, brown and black; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 7; CL – none; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates, granular, massive.
Origin and occurrence: Almost only magmatic and hydrothermal in granitic pegmatites, typically associated with lepidolite and albite; also in placers. Its crystals are mostly known from pegmatite cavi-

Elbaite, 153 mm, Afghanistan



Rubellite, 23 mm, Pala, U.S.A.



ties in many localities. Rubellite crystal called 'The Rocket' (109 cm/$43\frac{5}{16}$ in long) was found in the Jonas mine, Minas Gerais, Brazil. Rubellite crystals up to 40 cm (15¾ in) long come from Alto Ligonha district, Mozambique. Rubellite crystals up to 250 mm ($9\frac{13}{16}$ in) long occurred in the Stewart Lithia, Tourmaline King and Tourmaline Queen mines, Pala, California, USA. Verdelite crystal 270 mm ($10\frac{5}{8}$ in) long, is known from the Dunton mine, Newry, Maine, USA. Other important localities include San Piero in Campo, Elba, Italy; Malkhan, Transbaikalia, Russia; Rozna , Czech Republic; Uto, Sweden; Gilgit, Pakistan; Paprok, Afghanistan.
Application: commonly used as a gemstone.

Uvite

TOURMALINE GROUP

$CaMg_4Al_5(BO_3)_3Si_6O_{18}(OH,F)_4$

TRIGONAL ● ● ●

Properties: C – gray, black, brown, green, red, pleochroic; S – white; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 7-7.5; CL – none; F – uneven to conchoidal; M – long to short prismatic crystals, columnar aggregates, granular.
Origin and occurrence: Metamorphic in Ca-rich rocks, marbles, skarns; magmatic in some pegmatites; hydrothermal in ore veins.
Perfect green and red crystals, up to 30 mm ($1\frac{3}{16}$ in) across, occur in Brumado, Bahía, Brazil. It is also known from Gouverneur and Pierrepont, New York, USA.

Uvite, 41 mm, Brumado, Brazil



Liddicoatite

TOURMALINE GROUP

$Ca(Li_2Al)Al_6(BO_3)_3Si_6O_{18}(OH)_3F$

TRIGONAL ● ● ●

Varieties: rubellite, verdelite

Properties: C – varies in different varieties, mainly pink, green, green-brown to yellow-brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 7; CL – none; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates, granular.
Origin and occurrence: Magmatic in granitic peg-

Liddicoatite, 60 mm, Anjanobonoina, Madagascar




Verdelite, 24 mm, Gillette Quarry, U.S.A.


Indigolite, 32 mm, Esmeralda Mine, Mesa Grande, U.S.A.

matites in association with lepidolite, spodumene and albite. Its perfect red and green crystals up to 250 mm ($9^{13}/_{16}$ in) long come from pegmatite cavities in many localities in Madagascar, e.g. Sahatany and Anjanabonoina. It is also known from Blizná, Czech Republic.

Application: cut as a gemstone.


Liddicoatite, 41 mm, Madagascar

Foitite

TOURMALINE GROUP

☐ $Fe_2AlAl_6(BO_3)_3Si_6O_{18}(OH)_4$

TRIGONAL ● ● ●

Properties: C – black to black-purple; S – white; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 7; CL – none; F – uneven to conchoidal; M – prismatic crystals, acicular aggregates.
Origin and occurrence: Magmatic in granitic pegmatites and granites; hydrothermal in pegmatite cavities. Foitite typically forms black tips of elbaite crystals (moors heads) in Dobra Voda, Czech Republic; San Piero in Campo, Elba, Italy; White Queen mine, Pala, California, USA. It occurs together with schorl in some granitic pegmatites, like Rozna, Czech Republic.

Rossmanite

TOURMALINE GROUP

☐ $LiAl_2Al_6(BO_3)_3Si_6O_{18}(OH)_4$

TRIGONAL ●

Properties: C – pink; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 7; CL – none; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates.
Origin and occurrence: Magmatic in granitic pegmatites. Prismatic crystals, up to 20 mm (25/32 in) long, were found in massive lepidolite in Rozna, also in Lastovicky, Czech Republic.

Dioptase

$Cu_6Si_6O_{18} . 6 H_2O$

TRIGONAL ● ●

Properties: C – emerald-green to blue-green; S – light blue-green; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 5; CL – good; F – uneven to conchoidal; M – long to short prismatic crystals, granular.
Origin and occurrence: Secondary in the oxidation zone of Cu deposits, associated with other secondary Cu minerals. Beautiful crystals up to 50 mm (2 in) across occur in Tsumeb, Namibia; Altyn Tyube, Kazakhstan; Renneville, Congo. It also comes from the Mammoth mine, Tiger, Arizona, USA.

Milarite

$KCa_2AlBe_2Si_{12}O_{30} . H_2O$

HEXAGONAL ● ●

Properties: C – colorless, white, gray, light green; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.5; H – 5-6; CL – none; F – uneven to conchoidal; M – long prismatic to acicular crystals, granular.
Origin and occurrence: Hydrothermal in the Alpine-type veins, in pegmatites and hydrothermal veins, associated with adularia. Crystals up to 40 mm (1 9/16 in) long come from Jaguaraçu, Minas Gerais, Brazil. It was also found in St. Gotthard, Switzerland; Klein Spitzkopje, Namibia; Valencia mine, Guanajuato, Mexico.

Foitite, 20 mm x, Dobra Voda, Czech Republic



Rossmanite, 10 mm xx, Lastovicky, Czech Republic



Dioptase, 40 mm, Mindouli, Zair



Sugilite

$KNa_2(Fe,Mn,Al)_2Li_3Si_{12}O_{30}$

HEXAGONAL ●

Properties: C – purple; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.7; H – 6-6.5; CL – none; F – uneven to conchoidal; M – long prismatic to acicular crystals, granular.
Origin and occurrence: Hydrothermal in alkaline syenites, associated with pectolite, albite and aegirine. It occurs in Iwagi Island, Japan and Hotazel, South Africa. *Application:* cut and polished as a gemstone and decorative stone.

Milarite, 22 mm, Jaguaracu, Brazil



Sugilite, 40 mm, Hotazel, South Africa



Bronzite, 15 mm, Minas Gerais, Brazil

Enstatite

PYROXENE GROUP

$Mg_2Si_2O_6$

ORTHORHOMBIC ● ● ● ●

Varieties: bronzite

Properties: C – colorless, gray, yellowish, greenish, brown (bronzite); S – white; L – vitreous to dull; D – transparent to opaque; DE – 3.2; H – 5-6; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular.

Origin and occurrence: Magmatic in ultrabasic rocks, gabbros, peridotites and in meteorites; metamorphic in marbles, associated mainly with olivine and pyrope. Known from Bamle, Norway in crystals up to 50 cm (20 in) long. It was originally described from Ruda nad Moravou, Czech Republic. Gemmy crystals up to 20 mm ($^{25}/_{32}$ in) long occur in Brumado, Bahia, Brazil.

Diopside

PYROXENE GROUP

$CaMgSi_2O_6$

MONOCLINIC ● ● ● ● ●

Varieties: chrome diopside, fassaite, jeffersonite

Properties: C – light green, dark green (chrome diopside), colorless, white, gray, brown, rare blue; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 5.5-6.5; CL – good; F – uneven to conchoidal; M – long to short prismatic crystals, granular.

Chrome diopside, 5 mm grains, Inagli, Russia

Origin and occurrence: Metamorphic in Ca-rich rocks, skarns, pyroxene gneisses, marbles; magmatic in basic igneous rocks, pegmatites and meteorites; hydrothermal in the Alpine-type veins. Fassaite occurs in skarns, chrome diopside in metamorphic deposits of Cu and Cr; jeffersonite in metamorphic deposits of Mn and Zn. Diopside is a typical rock-forming mineral.

Diopside, 22 mm x, Ala, Italy



associated with plagioclase, grossular and epidote. Well formed crystals are relatively rare. Jeffersonite forms prismatic crystals up to 250 mm ($9\,^{13}/_{16}$ in) long in Franklin, New Jersey, USA. Crystals in Corrego Setuba, Minas Gerais, Brazil reach up to 30 cm (12 in). Other typical localities are Zillertal, Austria; Nordmarken, Sweden; Orford mine, Quebec, Canada. Fassaite is known from Val di Fassa, Italy. Chrome diopside crystals reach up to 100 mm (4 in) in Outokumpu, Finland and gem rough recently found in Inagli, Yakutia, Russia.

Hedenbergite

PYROXENE GROUP

$CaFeSi_2O_6$

MONOCLINIC ● ● ● ●

Properties: C – dark green, brown-green, brown to black; S – white to gray; L – vitreous to dull; D – transparent to translucent; DE – 3.6; H – 6; CL – good; F – uneven to conchoidal; M – long to short prismatic crystals, granular.

Origin and occurrence: Metamorphic in Ca-rich rocks, like Fe-skarns and pyroxene gneisses; magmatic in some granites and syenites, associated with magnetite, grossular and epidote. Crystals are relatively rare, reaching up to 50 mm (2 in) from Dalnegorsk, Russia and Franklin, New Jersey, USA. Also occurs in Nordmarken, Sweden. Large lamellar aggregates come from skarns in Rio Marina, Elba, Italy.

Hedenbergite, 40 mm, Dalnegorsk, Russia



Augite, 17 mm, Firmerich, Germany



Augite

PYROXENE GROUP

$(Ca,Mg,Fe,Al)(Si,Al)_2O_6$

MONOCLINIC ● ● ● ● ●

Properties: C – dark brown to black; S – gray-green; L – vitreous to dull; D – translucent to opaque; DE – 3.6; H – 6; CL – good; F – uneven to conchoidal; M – short prismatic crystals, granular.

Origin and occurrence: Magmatic in basic rocks (basalts, gabbros, diabases and their tuffs); rare metamorphic in skarns. It is a typical rock-forming mineral, known from many localities. Well formed crystals up to 150 mm (6 in) across occur mainly in volcanic rocks, such as near Lake Clear, Ontario, Canada. Also known from Laacher See, Germany; Lukov and Pa_kapole, Czech Republic, in crystals, up to 50 mm (2 in) in size.

Omphacite, 90 mm, St.Leonhard, Austria



Omphacite

PYROXENE GROUP

$(Ca,Na)(Mg,Fe^{2+},Fe^{3+},Al)(Si,Al)_2O_6$

MONOCLINIC ● ● ● ●

Properties: C – green to dark green; S – gray-white; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 5-6; CL – good; F – uneven to conchoidal; M – short prismatic crystals, acicular aggregates, granular. *Origin and occurrence:* Metamorphic in ultrabasic and basic rocks, originated under high-temperature, usually associated with pyrope, diopside and kyanite. It occurs in eclogites and granulites in Rubinberg, Germany; Headsburg, California, USA and elsewhere.

Jadeite, 85 mm, Guerro Negro, Baja California, Mexico



Nephrite, 60 mm, Jordanow, Poland



Jadeite

PYROXENE GROUP

$NaAlSi_2O_6$

MONOCLINIC ● ●

Varieties: nephrite

Properties: C – white, lavender to gray, in aggregates also light green (nephrite); S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 6; CL – good; F – uneven to conchoidal; M – prismatic crystals, acicular aggregates, granular.
Origin and occurrence: Exclusively metamorphic in strongly metamorphosed rocks; also in placers. Blocks, weighing several tons, are known from Ben Sur, California, USA. It also come from Tawmaw, Burma; New Zealand; Tibet and elsewhere.
Application: as a material for carvings and decorative purposes.

Aegirine

PYROXENE GROUP

$NaFe^{3+}Si_2O_6$

MONOCLINIC ● ● ●

Properties: C – dark green to black-green; S – light yellow-gray; L – vitreous to dull; D – translucent to opaque; DE – 3.6; H – 6; CL – good; F – uneven to conchoidal; M – long prismatic to acicular crystals, acicular aggregates.
Origin and occurrence: Magmatic, mainly in alkaline magmatic rocks (syenites, carbonatites, alkaline granites and their pegmatites); rare hydrothermal in sediments. Well formed prismatic crystals up to 150 mm (6 in) long come from Mount Malosa, Malawi. Crystals up to 30 cm (12 in) occur in Langensundsfjord, Norway. Other localities are Mount Karnasurt, Lovozero massif, Kola Peninsula, Russia and Mont St.-Hilaire, Quebec, Canada.

Aegirine, 77 mm, Mt.Malosa, Malawi



Spodumene, 52 mm x, Kunar, Afghanistan



Hiddenite, 35 mm, Adams Property, U.S.A.



Kunzite, 118 mm, Nuristan, Afghanistan



Spodumene

PYROXENE GROUP

$LiAlSi_2O_6$

MONOCLINIC ● ● ●

Varieties: kunzite, hiddenite, triphane

Properties: C – white, gray, yellowish (triphane), green (hiddenite), pink to purple (kunzite); S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 6.5-7.5; CL – good; F – uneven to conchoidal; M – long to short prismatic crystals, cleavable aggregates, granular; LU – orange.
Origin and occurrence: Magmatic in granitic pegmatites; hydrothermal in pegmatite cavities. It is known from many localities. Its poorly developed crystals up to 6 m (20 ft) long occur in the Etta mine, Keystone, South Dakota and in Kings Mountain, North Carolina, USA. Transparent kunzite crystals up to 40 cm (15¾ in) long come from Mawi, Laghman, Afghanistan. Kunzite crystals up to 280 mm (11 in) long found in the Pala Chief mine, Pala, California, USA. Cracked kunzite crystals, up to 1 m (39⅜ in) long known from Araçuai, Minas Gerais, Brazil. Hiddenite occurs in crystals up to 250 mm ($9^{13}/_{16}$ in) long in Resplendor, Minas Gerais, Brazil. It also comes from the Adams property, North Carolina, USA.
Application: raw material for ceramics, kunzite and hiddenite are cut as gemstones.


Carpholite, 70 mm, Horni Slavkov, Czech Republic

Carpholite

$MnAl_2Si_2O_6(OH)_4$

ORTHORHOMBIC ● ●

Properties: C – various hues of yellow; S – white; L – vitreous to dull; D – translucent; DE – 3.0; H – 5-5.5; CL – good; F – uneven to conchoidal; M – acicular crystals and their aggregates.
Origin and occurrence: Hydrothermal in veins, cross-cutting greisens, associated with fluorite, quartz and cassiterite; also in metamorphic rocks. It was described from Horni Slavkov, Czech Republic, where it forms acicular crystals up to 10 mm (3/8 in) long and radial aggregates. It is also known from Meuville, Belgium and Wippra, Germany.


Lorenzenite, 20 mm xx, Flora Mt., Kola, Russia

Lorenzenite

$Na_2Ti_2Si_2O_9$

ORTHORHOMBIC ● ●

Properties: C – brown to black; S – yellowish; L – vitreous to dull; D – translucent to opaque; DE – 3.4; H – 6; CL – good; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates, granular.
Origin and occurrence: Magmatic in alkaline syenites and their pegmatites, associated with astrophyllite, nepheline and aegirine. Crystals up to 80 mm (3 1/8 in) long come from Mount Flora, Lovozero massif, Kola Peninsula, Russia. Other localities are Narssarssuk, Greenland and Mont St.-Hilaire, Quebec, Canada.

Ajoite

$(K,Na)Cu_7AlSi_9O_{24}(OH)_6 . 3\ H_2O$

TRICLINIC ●

Properties: C – blue-green; S – light green; L – vitreous to dull; D – translucent to opaque; DE – 3.0; H – not determined; CL – not determined; F – uneven to conchoidal; M – prismatic crystals, massive.
Origin and occurrence: Secondary in Cu deposits, associated with shattuckite. It occurs rarely as small crystals in the New Cornelia mine, Ajo, Arizona, USA. It is also known as inclusions in quartz crystals in the Messina mine, Transvaal, South Africa.


Ajoite, 60 mm, Ajo, U.S.A.

Holmquistite, 60 mm, Lac Malartic, Canada

Antophyllite

AMPHIBOLE GROUP

$Mg_7Si_8O_{22}(OH,F)_2$

ORTHORHOMBIC ● ● ● ●

Properties: C – white, light brown, yellow, light green; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 5.5-6; CL – good; F – uneven to conchoidal; M – long prismatic crystals, columnar and radial aggregates, granular.
Origin and occurrence: Metamorphic in gneisses, serpentinites and at the contact of serpentinites and pegmatites, usually with actinolite or tremolite and cordierite. Crystals up to 150 mm (6 in) long come from the Marbridge No.1 mine, Quebec, Canada. It is also known from Bodenmais, Germany; Snarum, Sweden and Hermanov, Czech Republic.

Anthophyllite, 60 mm, North Carolina, U.S.A.



Holmquistite

AMPHIBOLE GROUP

$Li_2Mg_3Al_2Si_8O_{22}(OH,F)_2$

ORTHORHOMBIC ● ● ●

Properties: C – blue, purple, gray, black; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.0; H – 5.5-6; CL – good; F – uneven to conchoidal; M – acicular and prismatic crystals, fibrous aggregates, granular.
Origin and occurrence: Hydrothermal at the contacts between complex Li-bearing pegmatites and amphibolites, sometimes associated with biotite. It occurs in Greenbushes, Western Australia, Australia where its fibers reach up to 180 mm ($7^{1}/_{16}$ in) in length. It is also known from Uto, Sweden; Manono, Zaire and Brandbrucken, Austria.

Manganogedrite

AMPHIBOLE GROUP

$Mn_2Fe_5Si_8O_{20}(OH)_2$

MONOCLINIC ● ●

Properties: C – gray, dark green, brown, greenish; S – white; L – vitreous to dull; D – translucent to opaque; DE – 3.5; H – 5-6; CL- good; F – uneven to conchoidal; M – columnar, acicular and radial aggregates, granular.
Origin and occurrence: Metamorphic in contact and regionally metamorphosed Mn rich rocks, associated with chlorite and magnetite. It comes from Dannemora, Sweden and elsewhere.

Manganogedrite, 70 mm, Franz Joseph Iceberg, New Zealand



Tremolite, 37 mm, Maricopa Co., Arizona, U.S.A.



Tremolite

AMPHIBOLE GROUP

$Ca_2Mg_5Si_8O_{20}(OH)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – white, gray, greenish, green, brown, pink; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.9; H – 5-6; CL – good; F – uneven to conchoidal; M – columnar, acicular and radial aggregates, granular.
Origin and occurrence: Metamorphic in contact and regionally metamorphosed rocks, dolomites and ultrabasic rocks; hydrothermal in the Alpine-type veins, typically associated with diopside, talc, dolomite and calcite. It is a typical rock-forming mineral, known from many localities. Prismatic crystals up to 40 cm (15¾ in) long come from Brumado, Bahia, Brazil. It occurs also in Campolungo, Switzerland; Zillertal, Austria; Gouverneur, New York, USA and elsewhere.

Actinolite

AMPHIBOLE GROUP

$Ca_2(Mg,Fe)_5Si_8O_{20}(OH)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – light green to almost black; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 5-6; CL – good; F – uneven to conchoidal; M – columnar, acicular and radial aggregates, granular.
Origin and occurrence: Metamorphic in contact and regionally metamorphosed rocks, also in dolomites and some basic rocks (amphibolites, shales). It is a typical rock-forming mineral, associated with anthophylite, chlorite, talc, dolomite and calcite. It is known from many localities where it forms columnar aggregates up to 250 mm (9$^{13}/_{16}$ in) long, as in Knappenwand and Zillertal, Austria; Val Malenco, Italy; Brumado, BahRa, Brazil and Sobotín, Czech Republic.

Actinolite, 30 mm xx, Austris



Edenite

AMPHIBOLE GROUP

$NaCa_2(Mg,Fe)_5Si_7AlO_{22}(OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – white, gray to dark green; S – white; L – vitreous to dull; D – transparent, translucent to opaque; DE – 3.1; H – 5-6; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular.
Origin and occurrence: Metamorphic in regionally metamorphosed basic rocks and marbles; magmatic in diorites and gabbros. Typical rock-forming mineral, its crystals up to 40 mm (1$^{9}/_{16}$ in) long come from Edenville, New York, USA and Bancroft, Ontario, Canada.

Edenite, 48 mm, Wilberforce, Canada



Pargasite

AMPHIBOLE GROUP

$NaCa_2(Mg,Fe)_4AlSi_6Al_2O_{22}(OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – light brown, green-blue, brown to black-brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 5-6; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.

Origin and occurrence: Metamorphic in regionally metamorphosed basic rocks, marbles and skarns; magmatic in diorites and gabbros; typical rock-forming mineral. Crystals up to 80 mm ($3^{1}/_{8}$ in) across come from the Jensen quarry, Riverside, California, USA; Pargas, Finland; Hunza, Pakistan.

Common Amphibole

AMPHIBOLE GROUP

$(Ca,Na)_2(Mg,Fe,Al)_5(Si,Al)_8O_{22}(OH,F)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – dark green, brown to black; S – gray; L – vitreous to dull; D – translucent to opaque; DE – 3.4; H – 5-6; CL – good; F – uneven to conchoidal; M – short prismatic crystals, columnar aggregates, granular.

Origin and occurrence: Metamorphic in basic rocks, as amphibolites and shales; magmatic in some igneous rocks, as syenites, diorites, andesites and basalts. Typical rock-forming mineral, known from many localities. Large crystals up to 1 m ($39^{3}/_{8}$ in) long come from Silver Crater, Ontario, Canada. It is also known from Zillertal, Austria; Lukov, Czech Republic and elsewhere.

Common Amphibole, 50 mm x, Lukov, Czech Republic

Richterite

AMPHIBOLE GROUP

$Na_2Ca(Mg,Fe,Al)_5(Si,Al)_8O_{22}(OH,F)_2$

MONOCLINIC ● ● ●

Properties: C – brown, yellow, dark red, dark green; S – gray; L – vitreous to dull; D – transparent to translucent; DE – 3.1; H – 5-6; CL – good; F – uneven to conchoidal; M – long prismatic crystals, columnar aggregates, granular.

Origin and occurrence: Magmatic in alkaline rocks, as trachytes and alkaline granites; rare metamorphic in some metamorphosed rocks, as skarns and marbles. Crystals up to 100 mm (4 in) long come from Wilberforce, Ontario, Canada and Langban, Sweden.

Pargasite, 70 mm, Limberg, Parainen, Finnland

Richterite, 40 mm, Wilberforce, Canada



Riebeckite, 45 mm, Griqualand, South Africa



Riebeckite

AMPHIBOLE GROUP

$Na(Fe^{2+},Mg)_3Fe^{3+}{}_2Si_8O_{22}(OH)_2$

MONOCLINIC ● ● ● ●

Varieties: crocidolite (tiger's eye)

Properties: C – dark blue to black, crocydolite – gray-blue; S – white; L – vitreous to dull; D – translucent to opaque; DE – 3.4; H – 5; CL – perfect; F – uneven to conchoidal; M – long prismatic crystals, acicular to fibrous aggregates.
Origin and occurrence: Magmatic in alkaline rocks, as granites, syenites and rhyolites; metamorphic in regionally metamorphosed Fe rich shales. Large crystals up to 150 mm (6 in) long come from Khangay, Mongolia. Crocidolite is famous from Griqualand, South Africa.

Wollastonite, 44 mm, Crestmore, U.S.A.



Aenigmatite, 40 mm xx, Eveslogchorr, Kola, Russia



Aenigmatite

$Na_2Fe_5TiSi_6O_{20}$

TRICLINIC ● ●

Properties: C – black; S – red-brown; L – submetallic to dull; D -almost opaque; DE – 3.8; H – 5.5; CL – perfect; F – uneven to conchoidal; M – long prismatic crystals, columnar aggregates, granular.
Origin and occurrence: Magmatic in alkaline syenites and volcanic rocks, associated with aegirine and arfvedsonite. It occurs in Julianehab, Greenland; Lipari Island, Italy and elsewhere.

Wollastonite

$Ca_3Si_3O_9$

TRICLINIC ● ● ● ●

Properties: C - white, gray, light greenish, pink; S – white; L – vitrous to dull; D – transparent to translucent; DE – 3.0; H – 4.5-5; CL – good; F – uneven to conchoidal; M – tabular to short prismatic crystals, columnar and radial aggregates, granular; LU - orange.
Origin and occurrence: Metamorphic mainly in contact metamorphosed rocks, as marbles, skarns, less common in pyroxene gneisses and quartzites, associated with grossular, diopside and vesuvianite. Columnar and acicular aggregates up to 180 mm ($7^1/_{16}$ in) long occur in the Strickland quarry, Connecticut, USA. It also come from Crestmore, California, USA; Ciclova, Romania and Zulova , Czech Republic. Short prismatic crystals up to 30 cm (12 in) across are known from the Santa Fe mine, Chiapas, Mexico.



Bustamite, 20 mm xx, Broken Hill, Australia

Bustamite

$(Mn,Ca)_3Si_3O_9$

TRICLINIC ● ● ●

Properties: C – pink to red-brown; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.4; H – 5.5-6.5; CL – good; F – uneven to conchoidal; M – tabular crystals, acicular aggregates, massive.
Origin and occurrence: Metamorphic or hydrothermal in Mn rich metamorphic rocks or skarns. It is associated with rhodonite and other Mn silicates in Franklin, New Jersey, USA; Langban, Sweden; Broken Hill, New South Wales, Australia.



Pectolite, 70 mm, Zelechovske udoli, Czech Republic

Pectolite

$Ca_2NaSi_3O_8(OH)$

TRICLINIC ● ● ●

Properties: C – white, pinkish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.9; H – 4.5-5; CL – good; F – uneven to conchoidal; M B acicular and radial aggregates; LU – locally yellow to orange.
Origin and occurrence: Hydrothermal in basalt cavities, less frequently along the cracks in marbles, associated with zeolites. Classic localities are West Paterson, New Jersey, USA, where it forms acicular spherical aggregates up to 180 mm (7$^{1}/_{16}$ in) across; also Monte Baldo, Italy; Zelechovske udolí, Czech Republic. Prismatic crystals up to 50 mm (2 in) long come from Mont St.-Hilaire, Quebec, Canada.

Serandite

$Mn_2NaSi_3O_8(OH)$

TRICLINIC ●

Properties: C – pink, red; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.9; H – 4.5-5; CL – good; F – uneven to conchoidal; M – tabular and prismatic crystals, granular.
Origin and occurrence: Hydrothermal in cavities of igneous rocks (alkaline syenite, carbonatite) together with aegirine and analcime. Perfect pink crystals up to 200 mm (7$^{7}/_{8}$ in) long come from Mont St.-



Serandite, 25 mm, Mont St.-Hilaire, Canada

Hilaire, Quebec, Canada; crystals up to 60 mm (2⅛ in) long found in the Yubileinaya dike, Mount Karnasurt, Lovozero massif, Kola Peninsula, Russia.

Charoite

$(K,Sr,Ba)(Ca,Na)_2(Si,Al)_4O_{10}(OH,F)$

TRICLINIC ● ●

Properties: C – purple; S – white; L – vitreous to dull; D – translucent to opaque; DE – 2.6; H – 5-6; CL – good; F – uneven; M – fibrous aggregates, massive.
Origin and occurrence: Hydrothermal in alkaline igneous rocks, associated with aegirine and nepheline. Rich aggregates occur in Sirenevyi Kamen, Chara river basin, Murun massif, Yakutia, Russia.
Application: cut and polished as decorative stone.

Agrellite

$NaCa_2Si_4O_{10}F$

TRICLINIC ●

Properties: C – gray-white to greenish; S – white; L – vitreous, dull to pearly; D – transparent to translucent; DE – 2.9; H – 5.5; CL – good; F – uneven; M – long prismatic crystals, granular.
Origin and occurrence: Metamorphic in alkaline gneisses. It occurs as prismatic crystals up to 100 mm (4 in) long in the Kipawa river basin, Quebec, Canada.

Okenite

$CaSi_2O_4(OH)_2 \cdot H_2O$

TRICLINIC ● ●

Properties: C – white, yellowish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.3; H – 4.5-5; CL – good; F – uneven to conchoidal; M B blade-shaped crystals, acicular crystals and their spherical aggregates.
Origin and occurrence: Hydrothermal in basalt cavities together with zeolites. Rich acicular spherical aggregates up to 80 mm (3⅛ in) in diameter come from basalt cavities in the vicinity of Poona, India; also known from Faeroe Islands.

Charoite, 50 mm, Sirenevyi Kamen, Russia



Agrellite, 120 mm, Kipawa, Canada



Okenite, 125 mm, Mumbai, India



Xonotlite, 20 mm vein, Stare Ransko, Czech Republic



Xonotlite

$Ca_6Si_6O_{17}(OH)_2$

MONOCLINIC ● ●

Properties: C – white, pinkish, gray; S – white; L – vitreous, dull to pearly; D – transparent to translucent; DE – 2.7; H – 6.5; CL – good; F – uneven to conchoidal; M – acicular to fibrous aggregates, massive.
Origin and occurrence: Hydrothermal in cavities of basic and ultrabasic rocks and in the Alpine-type veins, associated with calcite and zeolites; rare metamorphic in skarns and in contact metamorphosed marbles. It comes from Tetela de Xonotla, Puebla, Mexico; Crestmore, California, USA; Mihara mine, Japan. It is was also found in Stare Ransko, Czech Republic.

Elpidite

$Na_2ZrSi_6O_{15} \cdot 3 H_2O$

ORTHORHOMBIC ● ●

Properties: B – colorless, yellowish, red; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.6; H – 5.5-6.5; CL – good; F – uneven to conchoidal; M – long prismatic crystals, fibrous aggregates.
Origin and occurrence: Hydrothermal in albitized parts of alkaline pegmatites, associated with albite and aegirine. Perfect crystals up to 30 cm (12 in) long come from Tarbagatay, Kazakhstan. Crystals up to 200 mm ($7\frac{7}{8}$ in) long found at Mont St.-Hilaire, Quebec, Canada. Also known from Khan Bogdo, Gobi desert, Mongolia; Umbozero mine on Mount Alluaiv, Lovozero massif, Kola Peninsula, Russia.

Elpidite, 128 mm, Mont St.-Hilaire, Canada



Rhodonite, 35 mm x, Broken Hill, Australia



Rhodonite, 70 mm, Maloye Sedelnikovo, Ural Mts., Russia

Rodonite

$CaMn_4Si_3O_9$

TRICLINIC ● ● ●

Properties: C – pink, red, red-brown, gray; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.7; H – 5.5-6.5; CL – good; F – uneven to conchoidal; M – tabular crystals, granular, massive.
Origin and occurrence: Metamorphic in Mn-rich rocks, hydrothermal in ore veins, associated with spessartine and Mn oxides. Perfect crystals up to 200 mm ($7\frac{7}{8}$ in) long come from Franklin, New Jersey, USA; also from Broken Hill, New South Wales, Australia.
Granular and massive aggregates occur in Langban, Sweden and in Maloye Sidelnikovo, Ural mountains, Russia.
Application: cut and polished as a decorative stone.

Babingtonite

$Ca_2Fe^{2+}Fe^{3+}Si_5O_{14}(OH)$

TRICLINIC ● ●

Properties: C – green-black to black-brown; S – green-gray; L – vitreous to dull; D – translucent to opaque; DE – 3.3; H – 5. 5-6; CL – good; F – uneven to conchoidal; M – short prismatic crystals, granular.
Origin and occurrence: Hydrothermal along the cracks in rocks, associated with prehnite, adularia and epidote.
Well-formed crystals about 20 mm ($\frac{25}{32}$ in) across are known from Arendal, Norway. Other localities are Westfield, Massachusetts, USA; Baveno, Italy.

Babingtonite, 5 mm x, Mumbai, India

Kinoite

$Ca_2Cu_2Si_3O_8(OH)_4$

MONOCLINIC ●

Properties: C – blue; S – light blue; L – vitreous to dull; D – transparent to translucent; DE – 3.2; H – 5; CL B perfect; F – uneven to conchoidal; M – prismatic crystals, granular.
Origin and occurrence: Hydrothermal along cracks in rocks, associated with apophyllite and copper. Small crystals were found in the Christmas mine, Santa Rita mountains, Arizona, also in the Kearsarge vein, Keweenaw Peninsula, Michigan, USA.

Inesite

$Ca_2Mn_7Si_{10}O_{28}(OH)_2 . 5\ H_2O$

TRICLINIC ● ●

Properties: C – pink, brown; S – white; L – vitreous to dull; D – translucent; DE – 3.0; H – 5.5; CL – good; F – uneven to conchoidal; M – short prismatic and tabular crystals, columnar and radial aggregates, granular.
Origin and occurrence: Hydrothermal in ore veins, associated with rhodochrosite, rhodonite and calcite. Rich aggregates and well-formed crystals about 10 mm ($^{3}/_{8}$ in) across found in Langban, Sweden; also in Hale Creek, California, USA; Broken Hill, New South Wales, Australia. Its spherical aggregates up to 30 mm ($1^{3}/_{16}$ in) in diameter are known from the Wessels mine, Kuruman, South Africa.

Neptunite

$KNa_2LiFe_2Ti_2Si_9O_{22}$

MONOCLINIC ● ●

Properties: C – dark brown to black; S – red-brown; L – vitreous to submetallic; D – translucent to opaque; DE – 3. 2; H – 5-6; CL – good; F – uneven to conchoidal; M – long prismatic crystals, granular.
Origin and occurrence: Hydrothermal in veins, associated with natrolite, benitoite and eudialyte. Well-formed prismatic crystals up to 80 mm ($3^{1}/_{8}$ in) long come from the Benitoite Gem mine, San Benito Co., California, USA. It is also known from Mont St.-Hilaire, Quebec, Canada and Narssarssuk, Greenland.

Epididymite

$NaBe_2Si_3O_7(OH)$

ORTHORHOMBIC ● ●

Properties: C – white, gray, yellowish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.6; H – 6-7; CL – good; F – uneven to conchoidal;

Kinoite, 36 mm, Christmas Mine, U.S.A.



Inesite, 50 mm, Kuruman, South Africa



Neptunite, 28 mm, San Benito Co., U.S.A.

M – tabular crystals, lamellar aggregates, granular. *Origin and occurrence:* Hydrothermal in cavities of alkaline pegmatites, associated with zeolites. Tabular crystals up to 60 mm ($2\frac{3}{8}$ in) across come from Mount Malosa, Malawi. It is also known from Langesundsfjord, Norway; Mont St.-Hilaire, Quebec, Canada; Narssarssuk, Greenland.

Bavenite, 40 mm, Yermolayevskoye, Russia

Bavenite

$Ca_4Al_2Be_2Si_9O_{26}(OH)_2$

ORTHORHOMBIC ● ● ●

Properties: C – white, yellowish, pinkish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.8; H – 5.5; CL – good; F – uneven to conchoidal; M – prismatic to tabular crystals, radial and lamellar aggregates. *Origin and occurrence:* Hydrothermal in pegmatic cavities with albite: typically produced by beryl replacement in pegmatites or helvite replacement in skarns. Found in Baveno, Italy with crystals up to 20 mm ($^{25}/_{32}$ in) across. Also known from Strzegom, Poland. Crystals up to 4 mm ($^{5}/_{32}$ in) across found in the Hewitt quarry, USA.

Epididymite, 70 mm, Apatity, Kola, Russia

Prehnite, 28 mm, Brandberg, Namibia



Prehnite

$Ca_2Al_2Si_3O_{10}(OH)_2$

ORTHORHOMBIC ● ● ● ●

Properties: C – white, greenish to green, yellow, gray; S – white; L – vitreous; PS – transparent to translucent; DE – 2.9; H – 6-6.5; CL – good; F – uneven to conchoidal; M – tabular to prismatic crystals, usually forming botryoidal or spherical aggregates, granular.
Origin and occurrence: Hydrothermal in basalt cavities and in the Alpine-type veins, commonly associated with calcite, albite, epidote and zeolites. Rich aggregates are known from West Paterson, New Jersey, USA; Val di Fassa, Italy; Poona, India.

Astrophyllite, 30 mm xx, Khibiny Massif, Kola, Russia



Fluorapophyllite, 47 mm, Poona, India



Crystals up to 45 mm (1¾ in) across found in Copper Valley, Brandberg, Namibia, Asbestos, Quebec, Canada and Talnakh, Siberia, Russia.

Astrophyllite

$(K,Na)_3(Fe,Mn)_7Ti_2Si_8O_{24}(O,OH)_7$

TRICLINIC ● ●

Properties: C – various hues of yellow; S – white; L – vitreous to dull; D – transparent to translucent; DE – 3.3; H – 3; CL – good; F – uneven to conchoidal; M – long prismatic crystals, bladed aggregates.
Origin and occurrence: Magmatic in alkaline pegmatites. Crystals and their radial aggregates reaching up to 100 mm (4 in) come from Mount Eveslogchorr, Khibiny massif, Kola Peninsula., Russia. It is also known from Mont St.-Hilaire, Quebec, Canada.

Fluorapophyllite

$KCa_4Si_8O_{20}(F,OH) . 8\ H_2O$

TETRAGONAL ● ● ●

Properties: C – white, greenish yellowish, pinkish; S – white; L – greasy to pearly; D – transparent to translucent; DE – 2.4; H – 4.5-5; CL – perfect; F – uneven; M – prismatic and tabular crystals, lamellar aggregates, massive.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, along the cracks in the Alpine-type veins, in ore veins and pegmatites. Well-formed crystals up to 100 mm (4 in) long are known from Jalgaon and Poona, India; Centreville and Fairfax,

Pyrophyllite, 37 mm, California, U.S.A.



Virginia, USA. Other localities are St. Andreasberg, Germany; Bento Gonçalves, Rio Grande do Sul, Brazil.

Pyrophyllite

$Al_2Si_4O_{10}(OH)_2$

MONOCLINIC ● ● ● ●

Varieties: agalmatolite

Properties: C – white, greenish, yellow, gray; S – white; L – greasy to pearly: D – translucent to transparent; DE – 2.8; H – 1-2; CL – perfect; F – uneven; M B foliated and lamellar aggregates, massive (agalmatolite), radial to acicular aggregates.
Origin and occurrence: Metamorphic in Al-rich rocks, together with andalusite and kyanite; hydrothermal in veins with quartz and micas. Rich foliated and radial aggregates and poorly-formed crystals up to 10 mm ($^3/_8$ in) across are known from Zermatt, Switzerland; Berezovsk, Ural mountains, Russia and the Champion mine, California, USA.
Application: heat-resistant material, agalmatolite as decorative stone.

Talc

$Mg_3Si_4O_{10}(OH)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – white, greenish, yellow, pinkish, gray; S – white; L – greasy to pearly; D – transparent to translucent; DE – 2.8; H – 1; CL – perfect; F – uneven; M – tabular crystals, foliated aggregates, massive.
Origin and occurrence: Metamorphic in metamorphosed basic rocks and dolomites, together with actinolite, dolomite and chlorite; hydrothermal in veins. Tabular crystals up to 20 mm ($^{25}/_{32}$ in) across come from Brumado, Bahia, Brazil and Chester, Massachusetts, USA. Rich foliated aggregates are known from Zillertal, Austria. Pseudo-morphs after quartz crystals come from St. Gotthard, Switzerland. Large deposits of massive talc are mined in China.
Application: as a filling material in textile, paper and chemical industries, heat-resistant material.

Agalmatolite, 70 mm, India

Talc, 61 mm, Rochester, U.S.A.



Muscovite

MICA GROUP

$KAl_3Si_3O_{10}(OH,F)_2$

MONOCLINIC ● ● ● ● ●

Varieties: fuchsite
Properties: C – white, greenish, yellowish, pinkish, green (fuchsite), gray; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, lamellar and scaly aggregates, massive.
Origin and occurrence: Metamorphic in various rock types, as mica schists, gneisses; magmatic in granites and pegmatites; hydrothermal in veins or next to ore veins (fuchsite). Important rock-forming mineral, usually associated with quartz, K-feldspar, albite and biotite. Its sheets, reached up to 5 x 3 m in size and weighed up to 85 tons in the Inikurti mine, Nellore, India. Large sheets are also known from Custer, South Dakota, USA. Well-formed crystals up to 100 mm (4 in) across come from Alabashka near Murzinka, Ural mountains, Russia. Other famous localities include Mamsk, Ural mountains, Russia and Cruzeiro mine, Minas Gerais, Brazil, where gemmy crystals were found.
Application: insulation material in electrical applications and construction.

Muscovite, 35 mm, Plumos, California, U.S.A.



Celadonite

MICA GROUP

$KFe^{3+}(Mg,Fe^{2+},Al)Si_4O_{10}(OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – light green to blue-green; S – white; L – dull; D – translucent to almost opaque; DE – 3.0; H – 2; CL – perfect; F – uneven; M – earthy, sometime small scaly aggregates, massive.
Origin and occurrence: Hydrothermal as a product of mafic mineral replacement in volcanic rocks, associated with zeolites, prehnite and calcite. Famous localities are Val di Fassa and Monte Balda, Italy; also known from Bisbee, Arizona, USA.

Boromuscovite

MICA GROUP

$KAl_2BSi_3O_{10}(OH)_2$

MONOCLINIC ●

Properties: C – yellowish; S – white; L – dull; D – transparent to translucent; DE – 2.8; H – 2.5; CL – perfect; F – uneven; M – small scaly aggregates, massive.
Origin and occurrence: Hydrothermal in cavities in

Fuchsite, 4 mm xx, Pamir, Tadzhikistan



Celadonite, 60 mm, Unhošť'any, Czech Republic



complex pegmatites, associated with albite, elbaite and lepidolite. Fine-grained scaly aggregates were described from the Little Three mine, Ramona, California, USA; also in Řecice, Czech Republic.

Paragonite

MICA GROUP

$NaAl_3Si_3O_{10}(OH,F)_2$

MONOCLINIC ● ● ●

Properties: C – white, greenish, yellowish, pinkish; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.8; H – 2.5; CL B perfect; F – uneven; M – tabular crystals, scaly aggregates, massive.
Origin and occurrence: Metamorphic in various rock types, as mica schists and gneisses. Fine-grained scaly aggregates are known from Pizzo Forno, Switzerland and elsewhere.

Boromuscovite, 40 mm, Ramona, U.S.A.



Paragonite, 80 mm, St.Gotthard, Switzerland



Glauconite

MICA GROUP

$K_{0.8}(Al,Fe^{2+},Fe^{3+},Mg)(Si,Al)_4O_{10}(OH)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – light green, yellow-green to blue-green; S – light green; L – dull; PS – translucent to opaque; DE – 2.9; H – 2; CL B perfect; F – uneven; M B earthy and platy aggregates, massive.
Origin and occurrence: Hydrothermal in sedimentary and volcanic sedimentary rocks, also as a product of replacement of mafic minerals in volcanic rocks. Common in sandstones and limestones, locally associated also with phosphorites. It occurs in many localities in the Karpathians, Poland; in Polabi region, Czech Republic. Massive aggregates are known from the N'Chwaning No. 2 mine, Kuruman, South Africa.

Glauconite, 80 mm, Malomerice, Czech Republic



Annite, 120 mm, Budec, Czech Republic

Annite

MICA GROUP

$KFe_3AlSi_3O_{10}(OH,F)_2$

MONOCLINIC ● ● ●

Properties: C – black, locally with reddish or greenish tint; S – colorless; L – vitreous to pearly; D – transparent to translucent, locally opaque; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, lamellar aggregates, massive.

Origin and occurrence: Metamorphic in skarns; magmatic in some pegmatites and granites. Its lamellar aggregates are known from Langban, Sweden and Cape Ann, Massachusetts, USA. Crystals up to 150 mm (6 in) across come from Mont St.-Hilaire, Quebec, Canada.

Phlogopite

MICA GROUP

$KMg_3AlSi_3O_{10}(OH,F)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – light brown, greenish, yellowish, colorless, gray; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, platy and scaly aggregates, massive.

Origin and occurrence: Metamorphic in various rock types, as marbles and some ultrabasic rocks, at the contacts of pegmatites and serpentinites, magmatic in some ultrabasic rocks and pegmatites, associated with dolomite, diopside, anthophyllite. Rich scaly aggregates come from many localities, as Pargas, Finland and elsewhere. Crystals up to 5 m (16 ft) across found in Sludyanka, Siberia, Russia. Crystals up to 50 cm (20 in) across occurred in the Gardiner complex, Greenland. The largest crystals, 10 x 5 m (33 x 16 ft) across, weighing up to 90 tons, come from the Lacy mine, Ontario, Canada.

Application: as insulation material in electrical applications.

[redacted]

[redacted]

Biotite

MICA GROUP

$K(Fe,Mg)_3AlSi_3O_{10}(OH,F)_2$

MONOCLINIC ● ● ● ● ●

Properties: C – brown to black, commonly with red or green tint; S – colorless; L – vitreous to pearly; D – transparent to translucent, locally opaque; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, scaly aggregates, massive.

Origin and occurrence: Metamorphic in various rock types, as mica schists, gneisses, migmatites and different types of metamorphosed shales; magmatic in pegmatites, granites, syenites and diorites, rare in basalts and ultrabasic rocks. Typical rock-forming mineral, usually associated with quartz, feldspars and muscovite. Rich scaly aggregates are known from a pegmatite in Evje, Norway, where its crystals reach up to several meters across. Other famous localities are Bessnes, France; Uluguru mountains, Tanzania; Silver Crater mine, Ontario, Canada and Laacher See, Germany.

Polylithionite

MICA GROUP

$KLi_2AlSi_4O_{10}(F,OH)_2$

MONOCLINIC ● ● ●

Properties: C – gray, colorless, yellowish, purple; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M B tabular crystals, scaly aggregates, massive.

Origin and occurrence: Magmatic and locally also hydrothermal in alkaline pegmatites, granites and carbonatites, rare in Li-bearing granitic pegmatites. Well-formed crystals up to 40 mm ($1\frac{9}{16}$ in) across are known from cavities in alkaline pegmatites from Mont St.-Hilaire, Quebec, Canada. It comes also from Illimaussaq, Greenland and from cavities in granitic pegmatites in Rœice, Czech Republic and

Biotite, 30 mm x, Ontario, Canada

elsewhere. Large industrial deposits known in Blatchford Lake, Northwest Territories, Canada.
Application: Li and Cs ore.

Trilithionite

MICA GROUP

$KLi_{1,5}Al_{2,5}Si_3O_{10}(F,OH)_2$

MONOCLINIC ● ● ● ●

Properties: C – purple, pink, blue, colorless, green; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, scaly aggregates, massive.
Origin and occurrence: Magmatic in Li-bearing pegmatites and granites, commonly associated with elbaite, spodumene, petalite, quartz and albite; sometimes hydrothermal in quartz veins and pegmatites. Well-formed crystals from pegmatite cavities are known from Virgem da Lapa, Minas Gerais, Brazil. Massive aggregates come from the Stewart Lithia mine, Pala, California and the Brown Derby No. 1 mine, Colorado, USA; Varutrask, Sweden; Rožna , Czech Republic; Meldon Quarry, Devon, UK.
Application: Li and Cs ore.

Polylithionite, 30 mm, Lovozero Massif, Kola, Russia

Zinnwaldite

MICA GROUP

$KLiFeAl_2Si_3O_{10}(F,OH)_2$

MONOCLINIC ● ● ●

Properties: C – gray, colorless, brown; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 3.7; H – 2.5-3; CL – perfect; F – uneven; M – tabular crystals, scaly aggregates, massive.
Origin and occurrence: Hydrothermal in quartz veins and greisens; magmatic in pegmatites and granites, associated with fluorite, cassiterite and wolframite. Rich aggregates with scales up to 100 mm (4 in) across are known from quartz veins in Cínovec, Czech Republic. Crystals up to 150 mm (6 in) across come from pegmatite cavities in Virgem da Lapa, Minas Gerais, Brazil. It also occurs in the Pikes Peak batholith, Colorado, USA; Baveno, Italy.
Application: Li ore.

Trilithionite, 70 mm, Tanco, Canada

Zinnwaldite, 10 mm xx, Cinovec, Czech Republic

Margarite, 73 mm, Chester, U.S.A.



Margarite

$CaAl_4Si_2O_{10}(OH)_2$

MONOCLINIC ● ● ●

Properties: C – pinkish, colorless, yellowish; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 3.1; H – 3.5-4.5; CL B perfect; F – uneven; M – tabular crystals, platy and scaly aggregates, massive.
Origin and occurrence: Metamorphic, associated with corundum, diaspore, tourmaline and staurolite in various types of metamorphosed shales. Coarse platy aggregates come from Chester, Massachusetts and Sterling Hill, New Jersey, USA.

Clintonite

$Ca(Mg,Al)_3(Al_3Si)O_{10}(OH)_2$

MONOCLINIC ● ●

Properties: C – colorless, yellowish, pinkish, greenish; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 3.1; H – 3.5; CL – perfect; F – uneven; M – tabular crystals, lamellar aggregates, massive.
Origin and occurrence: Metamorphic in contact metamorphosed marbles, associated with vesuvianite, grossular, diopside and spinel. Rich aggregates with lamellae up to 20 mm ($^{25}/_{32}$ in) across occur in Green Monster mountain, Alaska and Crestmore, California, USA and Monzoni, Italy.

Clintonite, 3 mm xx, Pomaz, Hungary



Stilpnomelane, 100 mm, Horni Udoli, Czech Republic



Stilpnomelane

$K(Fe^{2+},Mg,Fe^{3+})_8(Si,Al)_{12}(O,OH)_{27}$

MONOCLINIC ● ● ● ●

Properties: C – black, black-brown, black-green, yellow-brown; S – colorless; L – vitreous to dull; D – translucent to opaque; DE – 2.8; H – 3; CL – perfect; F – uneven; M – tabular crystals, foliated, lath-like and acicular aggregates..
Origin and occurrence: Metamorphic in Fe-rich shales, usually associated with chlorite, magnetite and albite. Crystals up to 20 mm ($^{25}/_{32}$ in) across come from Jim Pond township, Maine, USA. Foliated aggregates are known from Horní Udoli near Zlate Hory, Czech Republic; Mesabi Range, Minnesota, USA.

Montmorillonite

$(Ca,Na)_{0.33}(Al,Mg)_2Si_4O_{10}(OH)_2 \cdot n\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – white, yellowish, greenish, bluish; S – white; L – greasy; D – translucent to opaque; DE – 2.3; H – 1-2; CL – perfect, wet massive aggregates are plastic; F – uneven; M – earthy aggregates, massive.
Origin and occurrence: Hydrothermal as a product of replacement of other minerals in volcanic rocks, granitic pegmatites and sediments. It is abundant in many localities. Montmorillonite deposits are known from Antrim, Northern Ireland, UK; in Hungary; Slovakia and many places in the USA.
Application: ceramics and chemical industry.

Saponite

$(Ca,Na)_{0.3}(Fe,Mg)_3(Si,Al)_4O_{10}(OH)_2 \cdot 4\ H_2O$

MONOCLINIC ● ● ●

Properties: C – white, yellowish, gray-green, bluish; S – white; L – greasy; D – translucent to opaque; DE – 2.1; H – 1-2; CL – perfect, massive aggregates are plastic under wet conditions; F – uneven; M – earthy, nodular, massive.
Origin and occurrence: Hydrothermal as a product of replacement of other minerals in volcanic rocks and serpentinites. It occurs together with copper in many places in Keweenaw Peninsula, Michigan, USA. Scales up to 10 mm ($^3/_8$ in) across described from Mont St.-Hilaire, Quebec, Canada.

Montmorillonite, Kisthaas, Syria



Saponite, 2 mm crust, Erdobenye, Hungary



Vermiculite

$(Fe,Mg,Al)_3(Si,Al)_4O_{10}(OH)_2 \cdot 4\ H_2O$

MONOCLINIC ● ● ●

Properties: C – yellow-brown, gray-green, green-brown; S – white; L – greasy; D – translucent to opaque; DE – 2.5; H – 1.5; CL B perfect; F – uneven; M – scaly aggregates, massive; R – it expands when heated.
Origin and occurrence: Hydrothermal as a product of replacement of phlogopite and other mafic micas in various rock types. It occurs in Palbora, South Africa; Milbury, Massachusetts, USA; Kovdor massif, Kola Peninsula, Russia.
Application: electrical applications and paper industry.

Vermiculite, 50 mm, Drahonin, Czech Republic



Cookeite, 60 mm, Dobrá Voda, Czech Republic

Cookeite

CHLORITE GROUP

$LiAl_4Si_3O_{10}(OH)_8$

MONOCLINIC ● ●

Properties: C – white, yellowish, pinkish, brown; S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 2.6; H – 2.5-3.5; CL – perfect; F – uneven; M B scaly, locally radial aggregates, massive.

Origin and occurrence: Hydrothermal in cavities in Li-bearing pegmatites, associated with elbaite, lepidolite, fluorapatite and albite, it also replaces spodumene; metamorphic in Al-rich shales, together with diaspore and pyrophyllite. Massive aggregates, replacing spodumene, occur in the Tanco mine, Bernic Lake, Manitoba, Canada. It also comes from cavities in pegmatites in the Little Three mine, Ramona and the Himalaya mine, Mesa Grande, California. It is also known from the Pulsifer quarry, Maine, USA and Muiane, Mozambique.

Clinochlore, 5 mm xx, Sarany, Russia

Clinochlore

CHLORITE GROUP

$(Mg,Fe)_5Al_2Si_3O_{10}(OH)_8$

MONOCLINIC ● ● ● ● ●

Varieties: kammererite

Properties: C – greenish, gray, white, yellowish, brown, red-purple (kammererite); S – colorless; L – vitreous to pearly; D – transparent to translucent; DE – 2.7; H – 2-2.5; CL – perfect; F – uneven; M B poorly-developed tabular crystals, foliated and radial aggregates, massive.

Kammererite, 11 mm xx, Kop Daglari, Turkey



Chamosite, 70 mm, Hajan, Hungary

Origin and occurrence: Metamorphic in various types of shales and marbles; hydrothermal in quartz veins and Alpine-type veins, occasionally replaces certain minerals as biotite. Crystals up to 50 mm (2 in) across, associated with chondrodite and magnetite, are known from the Tilly Foster mine, Brewster, New York and Chester, Pennsylvania, USA. It also occurs in Val d'Ala, Italy and Zillertal, Austria. Scales up to 40 cm (15¾ in) across come from Beramy, Madagascar. Kammererite crystals up to 20 mm ($^{25}/_{32}$ in) across found in Kop Daolari, Erzerum, Turkey.

Chamosite

CHLORITE GROUP

$(Fe,Mg)_5Al_2Si_3O_{10}(OH)_8$

MONOCLINIC ● ● ● ●

Properties: C – gray, gray-green, brown; S – gray-green; L – vitreous to dull; D – translucent to opaque; DE – 3.2; H – 2-2.5; CL – perfect; F – uneven; M B scaly and oolitic aggregates, massive.
Origin and occurrence: Metamorphic to hydrothermal in various types Fe-rich sediments, typically associated with siderite and magnetite.
It is common in Chamoson, Switzerland; Nucice, Czech Republic. Spherical aggregates up to 15 mm ($^{19}/_{32}$ in) in diameter found in Mont St.-Hilaire, Quebec, Canada.

Kaolinite

$Al_2Si_2O_5(OH)_4$

TRICLINIC ● ● ● ● ●

Properties: C – white, yellowish, greenish, gray; C – colorless; L – earthy; D – translucent to opaque; DE – 2.6; H – 1; CL – perfect; F – uneven; M – earthy and exceptionally scaly aggregates, massive.
Origin and occurrence: Hydrothermal, as a result of feldspar replacement in various rock types, as granites and arcoses. It forms large deposits in China, France, UK and Czech Republic.
Application: raw material for ceramics.

Dickite, 100 mm, Nowa Ruda, Poland

Dickite

$Al_2Si_2O_5(OH)_4$

MONOCLINIC ● ● ●

Properties: C – white, yellowish; S – colorless; L – earthy to pearly; D – translucent to opaque; DE – 2.6; H – 1; CL – perfect; F – uneven; M – earthy and platy aggregates, massive.
Origin and occurrence: Hydrothermal in cavities in hydrothermal veins, together with quartz, carbonates and sulfides. It occurs in Essen, Germany; Anglesey, Wales , UK; Kladno, Czech Republic. Microscopic crystals come from Mas d'Alary, France.

Kaolinite, 50 mm, St.Austell, UK

Nakrite, 70 mm, Rochlitz, Germany



Nacrite

$Al_2Si_2O_5(OH)_4$

MONOCLINIC ● ● ●

Properties: C – white, yellowish, gray-white; S – colorless; L – earthy to pearly; D – translucent to opaque; DE – 2.6; H – 1; CL – perfect; F – uneven; M – earthy and scaly aggregates, massive.
Origin and occurrence: Hydrothermal in cavities of hydrothermal veins, associated with quartz, fluorite and topaz. It occurs in Horni Slavkov, Czech Republic; Freiberg, Germany. Pseudo-morphs after topaz come from Ouro Preto, Minas Gerais, Brazil.

Antigorite

$Mg_3Si_2O_5(OH)_4$

MONOCLINIC ● ● ● ● ●

Properties: C – white, yellowish, greenish, gray; S – colorless to gray; L – vitreous, pearly, silky, earthy; D – translucent to opaque; DE – 2.6; H – 2.5-3.5; CL – perfect; F – uneven; M B foliated, lamellar and fibrous aggregates, massive.
Origin and occurrence: Metamorphic in serpentinites, marbles and other Mg-rich rocks; hydrothermal in veins cross-secting these rocks. It is important rock-forming mineral. It occurs in Kraubat, Austria; Hrubsice, Czech Republic; Antigorio, Italy and elsewhere.

Antigorite, 110 mm, Felsocsatar, Hungary



Amesite

$Mg_2Al(SiAl)O_5(OH)_4$

TRICLINIC ● ●

Properties: C – greenish, gray; S – colorless; L – vitreous to pearly; D – translucent; DE – 2.8; H – 2.5-3; CL – perfect; F – uneven; M B foliated to radial aggregates, massive.
Origin and occurrence: Hydrothermal in Mg-rich rocks, associated with diaspore, magnetite and chromite. It comes from Chester, Massachusetts, USA. Crystals up to 40 mm (1 9/16 in) across found in Sarany, Ural mountains, Russia.

Cronstedtite

$Fe^{2+}{}_2Fe^{3+}{}_2SiO_5(OH)_4$

MONOCLINIC ● ●

Properties: C – black, black-brown, black-green; S – dark olive-green; L – vitreous to submetallic; D – translucent to opaque; DE – 3.6; H – 3.5; CL – perfect; F – uneven; M – prismatic crystals, columnar aggregates.
Origin and occurrence: Hydrothermal in ore veins. Fan-shaped aggregates of crystals come from Pribram and Kutna Hora, Czech Republic; Ouro Preto, Minas Gerais, Brazil; Salsigue mine, Auge, France.

Amesite, 40 mm, Sarany, Ural Mts., Russia




Cronstedtite, 42 mm, Hunan, Bolivia


Chrysocolla, 50 mm, Arizona, U.S.A.

Chrysocolla

$(Cu,Al)_2H_2Si_2O_5(OH)_4 \cdot n\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – different hues of blue-green; S – white; L – vitreous, greasy to earthy; D – translucent to almost opaque; DE – 2.0-2.4; H – 2-4; CL – none; F – conchoidal to uneven; M – microscopic acicular crystals, botryoidal, stalactitic and earthy aggregates.
Origin and occurrence: Secondary in Cu deposits, associated with malachite and other secondary Cu minerals.
Rich aggregates come from many places in Arizona, USA, like Bisbee and Morenci. It is also known from Mednorudnyansk, Ural mountains, Russia and Broken Hill, New South Wales, Australia.

Allophane

approximately $Al_2SiO_5 \cdot n\ H_2O$

AMORPHOUS ● ● ●

Properties: C – white, gray, bluish, greenish, brown; S -white; L – vitreous, greasy and earthy; D – transparent, translucent to opaque; DE – 1.9; H – 2-3; CL – none; F – conchoidal to uneven; M – botryoidal, stalactitic and earthy aggregates.
Origin and occurrence: Hydrothermal product of alteration along the cracks of sedimentary rocks in coal deposits and in the oxidation zone of ore deposits, associated with other secondary minerals. Rich botryoidal aggregates occur in Dehr, Germany; Moldova Nuova, Romania; New Cornelia mine, Arizona, USA; El Dragon mine, Potosi, Bolivia.


Allophane, 90 mm, Zlate Hory, Czech Republic

Palygorskite, 120 mm, Burda, Hungary

Palygorskite

$(Mg,Al)_2Si_4O_{10}(OH) . 4 H_2O$

MONOCLINIC ● ● ● ●

Properties: C – white, gray; S – white; L – dull; D – translucent to almost opaque; DE – 2.2; H – 1; CL – good; F – uneven, aggregates plastic under wet conditions; M – acicular crystals, fibrous aggregates, massive.
Origin and occurrence: Hydrothermal as a product of alteration of different rock types, such as serpentinites, granites, marbles and graywackes, also in ore veins and the Alpine-type veins. Rich aggregates resembling leather occur along the cracks in marbles in Hejná near Horažd'ovice, Czech Republic; in the Mammoth mine, Tiger, Arizona, USA and in Palygorskaya, Russia.

Sepiolite, 70 mm, Eskisehir, Turkey

Sepiolite

$Mg_4Si_6O_{15}(OH)_2 . 6 H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – white, yellowish, gray; S – white; L – dull; D – opaque; DE – 2.0; H – 2-2.5; CL – not determined; F – uneven; M – earthy aggregates, massive.
Origin and occurrence: Hydrothermal as a product of serpentinite alteration, typically associated with magnesite. Classic locality is Eskişehir, Turkey; also known from Biskoupky, Czech Republic.

Zeophylite

$Ca_4Si_3O_8(OH,F)_4 . 2 H_2O$

TRICLINIC ● ●

Properties: C – white; S – white; L – pearly; D – transparent to translucent; DE – 2.6; H – 3; CL – perfect; F – uneven; M – platy crystals, commonly with radial structure.
Origin and occurrence: Hydrothermal in cavities of volcanic rocks, associated with zeolites. Its most important locality is Radejčín, Czech Republic, where it forms spherical aggregates up to 10 mm (3/8 in) in diameter. Also known from Schellkopf, Germany and Monte Somma, Italy.

Cavansite

$CaVOSi_4O_{10} . 4 H_2O$

ORTHORHOMBIC ● ●

Properties: C – green-blue, blue; S – light blue; L – vitreous; D – transparent; DE – 2.2; H – 3-4; CL – good; F – uneven; M – long prismatic to acicular crystals, radial aggregates.
Origin and occurrence: Hydrothermal in cavities of volcanic rocks, associated with calcite, apophyllite and zeolites. Rich radial aggregates up to 30 mm

Zeophyllite, 60 mm, Radejčín, Czech Republic

Cavansite, 120 mm, Poona, India



($1^{3}/_{16}$ in) in diameter come from the Wagholi Quarry, Poona, India.

Nepheline

$(K,Na)AlSiO_4$

HEXAGONAL ● ● ● ●

Properties: C – colorless, white, greenish, yellowish, gray, green, brown; S – white; L – vitreous to greasy; D – transparent to translucent; DE – 2.7; H – 5.5-6; CL – none; F – uneven to conchoidal; M – prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in many alkaline rocks, as alkaline syenites and their pegmatites, also in some basalts; rare metamorphic in gneisses. It is a typical rock-forming mineral, associated with leucite, augite and apatite. Well-formed crystals found in Mount Vesuvius, Italy. Rich aggregates are known from many localities in Khibiny massif, Kola Peninsula, Russia. Crystals up to 70 cm ($27^{9}/_{16}$ in) long occur in Davis Hill, Bancroft, Ontario. Perfect crystals up to 35 mm ($1^{3}/_{8}$ in) long, come from Mont St.-Hilaire, Quebec, Canada.
Application: locally as Al ore and in ceramic industry.

Nepheline, 43 mm, Aouli, Morocco





Petalite, 23 mm, Paprok, Afghanistan

Petalite

$LiAlSi_4O_{10}$

MONOCLINIC ● ● ●

Properties: C – colorless, white, greenish, yellowish; S – white; L – vitreous; D – transparent to translucent; DE – 2.5; H – 6-6.5; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular.
Origin and occurrence: Magmatic in Li-bearing pegmatites, associated with lepidolite, elbaite, amblygonite and locally replaced by a mixture of quartz and spodumene. Gigantic crystals several meters long, come from Bikita, Zimbabwe; and Varutrask, Sweden. Clear gemmy crystals up to 230 mm (9$^{1}/_{16}$ in) across found in pegmatite cavities in Paprok, Afghanistanand also in San Piero in Campo, Elba, Italy. Crystals up to 100 mm (4 in) across occur in Araçuai, Minas Gerais, Brazil.
Application: ceramic industry.



Chkalovite, 70 mm, Umbozero, Kola, Russia

Chkalovite

$Na_2BeSi_2O_6$

ORTHORHOMBIC ● ●

Properties: C – colorless, white; S – white; L – vitreous; D – transparent to translucent; DE – 2.7; H – 6; CL – imperfect; F – conchoidal; M – prismatic crystals, granular, massive.
Origin and occurrence: Hydrothermal in alkaline pegmatites, usually associated with natrolite, sodalite and eudialyte. Crystals up to 200 mm (7$^{7}/_{8}$ in) across come from the Umbozero mine, Mount Alluaiv, Lovozero massif, Kola Peninsula, Russia; also at Julianhab, Greenland and Mont St.-Hilaire, Quebec, Canada.



Sanidine, 30 mm x, Drachenfels, Germany

Sanidine

FELDSPAR GROUP
$KAlSi_3O_8$

MONOCLINIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish, gray; S – white; L – vitreous: D – transparent to translucent; DE – 2.6; H – 6-6.5; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.
Origin and occurrence: Magmatic in acid volcanic rocks, as rhyolites and trachytes, a typical rock-forming mineral. Well-formed crystals and their combinations up to 100 mm (4 in) in size occur in rhyolites and trachytes in Drachenfels and Laacher See, Germany. It also comes from Roc de Courlande, France; Beaverdell, British Columbia, Canada; Kyustendil, Bulgaria.

Orthoclase

FELDSPAR GROUP
$KAlSi_3O_8$

MONOCLINIC ● ● ● ● ●

Varieties: adularia, moonstone (gemmy variety with chatoyancy)

Properties: C – colorless, white, yellowish, pinkish, gray, brown, yellow; S – white; L – vitreous to pearly (adularia); D – transparent to translucent; DE – 2.5; H – 6-6.5; CL – good; F – uneven to conchoidal; M – prismatic and tabular crystals and their combinations, granular, massive.
Origin and occurrence: Magmatic in rhyolites, trachytes, granites, syenites and pegmatites; metamorphic in various rock types, as orthogneisses and migmatites; hydrothermal in the Alpine-type veins, ore veins and some sediments, also in placers, a typical rock-forming mineral. Well-formed crystals and twins up to 200 mm (7⅞ in) across come from granites in Twentynine Palms, California, USA; Marina di Campo, Elba, Italy; Loket and Karlovy Vary, Czech Republic; in pegmatite cavities in Strzegom, Poland; San Piero in Campo, Elba, Italy. Yellow gemmy crystals up to 70 mm (2¾ in) across found in Itrongay, Madagascar. Gigantic feldspar crystals up to tens of meters long known from several pegmatite localities in Black Hills, South Dakota, USA; also Hagendorf, Germany. Adularia is known from Alpine–type veins in St. Gotthard, Switzerland; pebbles of moonstone occur in gem-bearing gravels in Ratnapura, Sri Lanka.
Application: ceramic and glass industry, moonstone as a gemstone.

Orthoclase, 32 mm x, Oro Grande, U.S.A.



Adularia, 60 mm, Alps, Switzerland



Microcline, 110 mm, Lake George, Teller Co., U.S.A.



Microcline

FELDSPAR GROUP

$KAlSi_3O_8$

TRICLINIC ● ● ● ● ●

Varieties: amazonite

Properties: C – colorless, white, yellowish, pinkish, gray, light to dark green (amazonite); S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 6-6.5; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.

Origin and occurrence: Magmatic in granites, syenites and pegmatites; metamorphic in various rock types, as orthogneisses and migmatites; hydrothermal in the Alpine-type veins and ore veins; a typical rock-forming mineral. Well-formed amazonite crystals up to 40 cm (15¾ in) across occur in pegmatite cavities in Crystal Peak, Colorado, USA; Keivy, Kola Peninsula, Russia; Morefield mine, Virginia, USA. Gigantic microcline crystals up to 12 m (39 ft) across come from pegmatites in Black Hills, South Dakota, USA; Kaatiala, Finland.

Application: ceramic industry, amazonite as a decorative stone.

Hyalophane

FELDSPAR GROUP

$(K,Ba)Al(Si,Al)_3O_8$

MONOCLINIC ● ● ●

Properties: C – colorless, white, yellowish; S – white; L – vitreous; D – transparent to translucent; DE – 2.9; H – 6-6.5; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.

Amazonite, 60 mm, Keivy, Kola, Russia

Hyalophane, 50 mm, Busovaca, Bosnia



Oligoclase, 40 mm, Ural Mts., Russia

Origin and occurrence: Magmatic in phonolites; metamorphic in various rock types, as marbles, gneisses and Mn-rich rocks; hydrothermal in the Alpine-type and ore veins. Crystals up to 100 mm (4 in) across found in Alpine-type veins near Busovaca, Bosnia-Hercegovina.

Albite

FELDSPAR GROUP
$NaAlSi_3O_8$

TRICLINIC ● ● ● ● ●

Varieties: pericline, cleavelandite

Properties: C – colorless, white, yellowish, pinkish, gray, greenish, bluish; S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 6-6.5; CL – good; F – uneven to conchoidal; M – tabular crystals and their twins, platy aggregates, granular, massive.
Origin and occurrence: Magmatic in granites, syenites and their pegmatites; metamorphic in various rock types, as orthogneisses, migmatites, phyllites and metamorphosed shales; hydrothermal in the Alpine-type veins and ore veins, a typical rock-forming mineral. Well-formed tabular to platy cleavelandite crystals up to 150 mm (6 in) across occur in pegmatite cavities in the Amelia district, Virginia and the Pala district, California, USA. Albite crystals also come from Strzegom, Poland; San Piero in Campo, Elba, Italy; Murzinka, Ural mountains, Russia; many localities in Minas Gerais, Brazil. Pericline crystals are known from the cracks along Alpine-type veins in Grossgreiner, Austria; St. Gotthard, Switzerland; also from ore veins in Roznava, Slovakia.

Albite, 85 mm, Governador Valadares, Brazil



Oligoclase

FELDSPAR GROUP
$(Na_{0,9-0,7}Ca_{0,1-0,3}Al_{1,1-1,3}Si_{2,9-2,7}O_8$

TRICLINIC ● ● ● ● ●

Varieties: peristerite, sunstone

Properties: C – white, yellowish, pinkish, greenish, iridescent (peristerite); S – white; L – vitreous; D – transparent to translucent; DE – 2.6; H – 6-6.5; CL – good; F – uneven to conchoidal; M – tabular crystals, platy aggregates, granular, massive.
Origin and occurrence: Magmatic in granites, syenites, andesites and pegmatites; metamorphic in gneisses and migmatites; hydrothermal in the Alpine-type veins; typical rock-forming mineral. Large crystals, several dm long, are known mainly from pegmatites. Peristerite comes from Arendal, Norway; Miass, Ural mountains, Russia; Quadeville, Ontario, Canada; Tvedestrand, Norway. It also occurs in Vezna , Czech Republic. Sunstone is mined in the Ponderosa mine near Lakeview, Oregon, USA.
Application: peristerite and sunstone are used as gemstones.

Andesine, 50 mm, Bodenmais, Germany



Andesine

FELDSPAR GROUP

$(Na_{0,7-0,5}Ca_{0,3-0,5}Al_{1,3-1,5}Si_{2,7-2,5}O_8$

TRICLINIC ● ● ● ●

Properties: C – yellowish, pinkish, gray, light green; S – white; L – vitreous; D – transparent to translucent; DE – 2.7; H – 6-6.5; CL – good; F – uneven to conchoidal; M – platy aggregates, granular, massive.

Labradorite, 50 mm, Labrador, Canada



Anorthite, 10 mm xx, Pasmaada, Finnland



Origin and occurrence: C – white to dark gray, greenish; S – white; L – vitreous, pearly; D – transparent to translucent; DE – 2.7; H – 6-6.5; CL – good; F – uneven to conchoidal; M B cleavable aggregates, granular, massive.

Labradorite

FELDSPAR GROUP

$Ca_{0,7-0,5}Na_{0,3-0,5}Al_{1,5-1,7}Si_{2,5-2,3}O_8$

TRICLINIC ● ● ● ●

Properties: Magmatic in andesites, diorites; metamorphic in gneisses and migmatites; typical rock-forming mineral. Large grains are known from migmatites in Bodenmais, Germany and Adamello, Italy.
Origin and occurrence: Magmatic in gabbros, basalts, anorthosites; metamorphic in amphibolites. Large iridescent aggregates up to 1 m ($39\frac{3}{8}$ in) across, come from Nain, Labrador, Quebec, Canada and also occur in Korostenskiy massif, Ukraine and Ylamaa, Finland.
Application: as a decorative stone.

Anortite

FELDSPAR GROUP

$CaAl_2Si_2O_8$

TRICLINIC ● ● ●

Properties: C – gray, greenish, pinkish; S – white; L – vitreous, dull; D – transparent to translucent; DE – 2.8; H – 6-6.5; CL – good; F – uneven to conchoidal; M B granular, massive.
Origin and occurrence: Magmatic in gabbros, basalts, anorthosites; metamorphic in contact metamorphosed rocks. Pinkish grains and poorly-developed crystals come from Val di Fassa, Italy. Crystals up to 50 mm (2 in) across are known from Miyake-Jima Island, Japan. It was also found in Mount Erebus, Antarctica and Monte Somma, Italy.

Danburite

$CaB_2Si_2O_8$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, gray, greenish, pinkish, yellow, brown, red-brown; S – white; L – vitreous, dull; D – transparent to translucent; DE – 3.0; H – 7; CL – imperfect; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates, granular, massive.

Origin and occurrence: Hydrothermal in pegmatite cavities, ore veins and the Alpine-type veins; metamorphic in skarns and contact metamorphosed rocks.

Well-formed prismatic crystals up to 250 mm ($9^{13}/_{16}$ in) long come from Russell, New York, USA; Toroku, Japan; Dalnegorsk, Russia; and Charcas, San Luis Potosi, Mexico.

Cancrinite

$Na_6CaAl_6Si_6O_{24}(CO_3) \cdot 2\,H_2O$

HEXAGONAL ● ● ●

Properties: C – colorless, white, yellow, orange, bluish; S – white; L – vitreous; D – transparent to translucent; DE – 2.4; H – 5-6; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.

Origin and occurrence: Magmatic in alkaline syenites; hydrothermal as a product of replacement of volcanic rocks, associated with nepheline and sodalite.

Crystals up to 20 mm ($^{25}/_{32}$ in) across come from Mont St.-Hilaire, Quebec, Canada. It was also found in Litchfield, Maine, USA; Cancrinite Hill, Bancroft, Ontario, Canada and elsewhere.

Cancrinite, 70 mm, Ditrau, Romania



Danburite, 109 mm, Charcas, Mexico



Leifite

$Na_2(Si,Al,Be)_7\,(O,OH,F)_{14}$

TRIGONAL ●

Properties: C – colorless; S – white; L – vitreous; D – translucent; DE – 2.5; H – 6; CL – good; F – uneven; M – acicular crystals.

Origin and occurrence: Hydrothermal in cavities of alkaline pegmatites, associated with microcline and zinnwaldite. Crystals up to 20 mm ($^{25}/_{32}$ in) across occur in Narssarssuk, Greenland. Fine crystals are also known from Mont St.-Hilaire, Quebec, Canada, associated with serandite.

Leifite, 100 mm, Mont St.-Hilaire, Canada



Sodalite, 50 mm, Bancroft, Canada

Sodalite

$Na_8Al_6Si_6O_{24}Cl_2$

CUBIC ● ● ●

Varieties: hackmanite

Properties: C – colorless, white, blue, yellow, pink (hackmanite); S – white; L – vitreous; D – transparent to translucent; DE – 2.3; H – 5.5-6; CL – imperfect; F – uneven to conchoidal; M – isometric crystals, granular, massive; LU – orange-red.
Origin and occurrence: Magmatic in alkaline syenites and phonolites, associated with nepheline, zircon and titanite; hydrothermal in marbles. Granular aggregates are known from the Princess Sodalite mine, Bancroft, Ontario, Canada and Ditrau, Romania. Crystals up to 100 mm (4 in) across come from Kangerdluarssuk, Greenland.
Application: cut as a gemstone.

Noseane

$Na_8Al_6Si_6O_{24}(SO_4)$

CUBIC ● ●

Properties: C – colorless, white, blue, gray, black; S – white; L – vitreous; D – transparent to translucent; DE – 2.3; H – 5-6; CL – good; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Magmatic in alkaline basalts and similar effusive rocks, associated with nepheline and haüyne. Granular aggregates are known from Laacher See, Germany and Monte Somma, Italy.

Lazurite

$(Na,Ca)_8Al_6Si_6O_{24}(S,SO_4)$

CUBIC ● ● ●

Properties: C – dark blue; S -light blue; L – vitreous; D – transparent to translucent; DE – 2.4; H – 5-5.5; CL – imperfect; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Metamorphic in contact metamorphosed marbles, associated with pyrite. Crystals up to 50 mm (2 in) across come from Sar-e-Sang, Badakhshan province, Afghanistan. Granular aggregates are known from many localities, such as Malobystrinskoye deposit near Lake Baikal, Russia or Monte Somma, Italy.
Application: decorative stone and gemstone.

Nosean, 6 mm grains, Laacher See, Germany

Lazurite, 60 mm, Afghanistan

Lazurite, 21 mm x, Nuristan, Afghanistan



Lazurite, 60 mm, Chile



Tugtupite

$Na_8Be_2Al_2Si_8O_{24}Cl_2$

TETRAGONAL ● ●

Properties: C – white, pink, red, bluish; S – white; L – vitreous; D – transparent to translucent; DE – 2.3; H – 5; CL – good; F – uneven to conchoidal; M – small crystals, granular, massive.
Origin and occurrence: Hydrothermal in alkaline syenites and their pegmatites, also as a product of chkalovite alteration. Aggregates up to 60 mm ($2^3/_8$ in) across come from the Umbozero mine, Mount Alluaiv, Lovozero massif, Kola Peninsula, Russia and IlRmaussaq, Greenland. Small crystals occur in the Poudrette quarry, Quebec, Canada.

Tugtupite, 90 mm, Illimaussaq, Greenland



Danalite

$Fe_4Be_3Si_3O_{12}S$

CUBIC ● ●

Properties: C – gray,yellow,pink, red, brown; S – white; L – vitreous; D – transparent to translucent; DE – 3.4; H – 5.5-6; CL – imperfect; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites; hydrothermal in greisens, skarns and ore veins. It occurs in Cape Ann, Massachusetts, USA; Hortekollen, Norway and Coolgardie, Western Australia, Australia.

Danalite, 70 mm, Yxjoberg, Sweden



Helvite, 2 mm xx, Cavnic, Romania

Helvite

$Mn_4Be_3Si_3O_{12}S$

CUBIC ●●●

Properties: C – brown, gray, yellow, yellow-green; S – white; L – vitreous; D – transparent to translucent; DE – 3.4; H – 6; CL – good; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Magmatic in granitic pegmatites and alkaline syenites; hydrothermal in greisens, skarns and ore deposits. Cubic crystals up to 25 mm (1 in) across known from the Sawtooth Batholith, Idaho, USA. Crystals also come from Schwarzenberg, Germany; Cavnic, Romania; and Oslofjord, Norway.
Application: Be ore.

Scapolite, 44 mm x, Leslie Lake, Quebec, Canada



Marialite

SCAPOLITE GROUP

$Na_8(AlSi_3O_8)_6\ (Cl_2,SO_4)$

TETRAGONAL ●●●

Properties: : C – colorless, white, gray, purplish, yellow; S – white; L – vitreous, locally pearly; D – transparent to translucent; DE – 2.5; H – 5-6; CL – good; F – uneven to conchoidal; M – prismatic crystals, columnar aggregates, granular, massive; LU – yellow to orange.
Origin and occurrence: Hydrothermal in veins, cross-cutting alkaline metamorphic rocks and in pegmatites, cross-cutting ultrabasic rocks; metamorphic in marbles and metaevaporites. It comes from Ankazobe, Madagascar; Umba, Tanzania and Crestmore, California, USA.

Meionite

SCAPOLITE GROUP

$Ca_8(Al_2Si_2O_8)_6\ (CO_3,SO_4)$

TETRAGONAL ●●●●

Properties: C – colorless, white, gray, purplish, green, blue; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 5-6; CL – good; F – uneven to conchoidal; M – long prismatic crystals, columnar aggregates, granular, massive; LU – yellow to orange.

Leucite, 30 mm, Mt.Vesuvius, Italy

Analcime, 45 mm, Tunguzka, Russia



Origin and occurrence: Metamorphic in skarns, marbles, granulites and in contacts of volcanic rocks; hydrothermal in veins, cross-cutting Ca-rich rocks. Well formed crystals up to 40 cm (15¾ in) across come from Lake Clear and Eganville, Ontario, Canada. Crystals are also known from Monte Somma, Italy; Sludyanka, Siberia, Russia and Pargas, Finland.

Leucite

ZEOLITE GROUP

$KAlSi_2O_6$

TETRAGONAL ● ● ● ●

Properties: C – colorless, white, gray; S – white; L – vitreous; D – transparent to translucent; DE – 2.5; H – 5.5-6; CL- imperfect; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Magmatic in effusive K-rich basalts, associated with nepheline and sanidine. Well-formed crystals, several cm in size, come from Mount Vesuvius, Italy and Laacher See, Germany.
Application: ceramic industry.

Analcime

ZEOLITE GROUP

$NaAlSi_2O_6 . H_2O$

CUBIC ● ● ● ●

Properties: C – colorless, white, pinkish, yellowish; S – white; L – vitreous; D – transparent to translucent; DE – 2.3; H – 5-5.5; CL – imperfect; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Mainly hydrothermal as a product of nepheline or sodalite replacement; rare magmatic in effusive rocks; also in sediments, associated with calcite and zeolites. Well-formed crystals up to 30 cm (12 in) across come from Nidym, Siberia, Russia; Lago Maggiore, Italy; Mont St.-Hilaire, Quebec, Canada; West Paterson, New Jersey, USA and elsewhere.

Pollucite

ZEOLITE GROUP

$(Cs,Na)AlSi_2O_6 . H_2O$

CUBIC ● ● ●

Properties: C – colorless, white, gray; S – white; L – vitreous; D – transparent to translucent; DE – 2.9; H – 6.5-7; CL – none; F – uneven to conchoidal; M – isometric crystals, granular, massive.
Origin and occurrence: Magmatic and rarely also hydrothermal in Li-bearing pegmatites, associated with lepidolite, albite, quartz and petalite. Almost monomineral layer of pollucite several meters thick occurs in the Tanco mine, Bernic Lake, Manitoba, Canada. White and colorless crystals from pegmatite cavities up to 60 cm (24 in) across come from Paprok, Afghanistan. Also known from San Piero in Campo, Elba, Italy and Gilgit, Pakistan.
Application: ceramic industry, Cs ore.

Pollucite, 22 mm x, Gilgit, Pakistan



Natrolite, 47 mm, Maricopa Co., Arizona, U.S.A.



Scolecite, 165 mm, Nasik, India



Natrolite

ZEOLITE GROUP

$Na_2Al_2Si_3O_{10} \cdot 2\ H_2O$

ORTHORHOMBIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish; S – white; L – vitreous to silky; D – transparent to translucent; DE – 2.2; H – 5-5.5; CL – perfect; F – uneven to conchoidal; M – long prismatic to acicular crystals, fibrous and radial aggregates, granular, massive.

Origin and occurrence: Hydrothermal in cavities in volcanic rocks, alkaline pegmatites, along the Alpine-type fissures, also as a product of plagioclase replacement, commonly associated with calcite and zeolites. Colorless and white acicular crystals up to 30 cm (12 in) long come from cavities of alkaline pegmatites in Mount Putelichorr, Khibiny massif, Kola Peninsula, Russia. Crystals were also found in Narssarssuk, Greensland and Mont St.-Hilaire, Quebec, Canada. Crystals also occur in cavities of basaltic rocks in Teigarhorn, Iceland; Zalezly and Soutisky, Czech Republic and in Faeroe Islands.

Skolecite

ZEOLITE GROUP

$CaAl_2Si_3O_{10} \cdot 3\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white; S – white; L – vitreous to silky; D – transparent to translucent; DE – 2.3; H – 5; CL – good; F – uneven; M – long prismatic to acicular crystals, fibrous and radial aggregates.

Origin and occurrence: Hydrothermal in cavities in volcanic rocks and along the Alpine-type fissures, associated with calcite and zeolites. Clear prismatic crystals up to 200 mm ($7\frac{7}{8}$ in) long come from basalt cavities near Nasik, India. Crystals come also from Teigarhorn, Iceland and Suderoy, Faeroe Islands.

Mesolite, 150 mm, Mahrashitra, India



Mesolite

ZEOLITE GROUP

$Na_{16}Ca_{16}Al_{48}Si_{72}O_{240} \cdot 64\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white; S – white; L – vitreous to silky; D – transparent to translucent; DE – 2.3; H – 5; CL – good; F – uneven; M – acicular crystals, fibrous and radial aggregates, granular, massive.

Origin and occurrence: Hydrothermal in cavities in volcanic rocks, associated with other zeolites. Colorless needles up to 150 mm (6 in) long come from the basalt cavities in Berufjord and Teigarhorn, Iceland. Radial aggregates up to 200 mm ($7\frac{7}{8}$ in) in diameter known from the vicinity of Poona, India. Prismatic crystals up to 100 mm (4 in) long found in Skookumchuck Dam, Washington, USA.

Thomsonite

ZEOLITE GROUP

$Ca_2NaAl_4(Al,Si)_2Si_4O_{20} \cdot 6\ H_2O$

ORTHORHOMBIC ● ● ●

Properties: C – colorless, white, yellowish, brown-red; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.3; H – 5-5.5; CL – good; F – uneven to conchoidal; M – prismatic crystals in clusters with radial structure, botryoidal aggregates, massive.

Origin and occurrence: Hydrothermal in cavities in volcanic rocks, also as a product of hydrothermal feldspar replacement. Colorless and white acicular crystals, forming radial aggregates up to 50 mm (2 in) in diameter come from Old Kilpatrick, Scotland, UK and West Paterson, New Jersey, USA. Hemispherical aggregates up to 30 mm ($1\frac{3}{16}$ in) across known from Vinaicka hora near Kladno, Czech Republic.

Thomsonite, 50 mm, Bazsi, Hungary



Gonnardite, 10 mm xx, Zalahalap, Hungary



Gonnardite

ZEOLITE GROUP

$(Na,Ca)_{6-8}(Al,Si)_{20}O_{40} \cdot 12\ H_2O$

TETRAGONAL ● ● ●

Properties: C – colorless, white, yellowish; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.3; H – 4.5-5; CL – good; F – uneven to conchoidal; M – prismatic crystals, fibrous and radial aggregates.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, associated with zeolites, also in the contact zone of marbles, associated with wollastonite. Acicular crystals and fibrous aggregates occur in Aci Castello, Sicily, Italy; Weilberg, Germany; Bundoora, Victoria, Australia.

Edingtonite

ZEOLITE GROUP

$BaAl_2Si_3O_{10} \cdot 3\ H_2O$

TETRAGONAL ● ● ●

Properties: C – white, gray, pinkish; S – white; L – vitreous; D – transparent to translucent; DE – 2.8; H – 4; CL – good; F – uneven to conchoidal; M – prismatic crystals, granular, massive.
Origin and occurrence: Hydrothermal in cavities and along the cracks in volcanic rocks, associated with calcite and harmotome. Colorless and white prismatic crystals up to 40 mm ($1\frac{9}{16}$ in) across come from Old Kilpatrick, Scotland, UK; Stare Ransko,

Edingtonite, 100 mm, Stare Ransko, Czech Republic

Czech Republic and Mont St.-Hilaire, Quebec, Canada.

Dachiardite-Ca

ZEOLITE GROUP

$(Ca_{0.5},Na,K)_5Al_5Si_{19}O_{48} \cdot 13\ H_2O$

MONOCLINIC ● ●

Properties: C – colorless, white, yellowish; S – white; L – vitreous to pearly; D – transparent to translucent; DE – 2.1; H – 4-4.5; CL – good; F – uneven to conchoidal; M – prismatic crystals and complex interpenetration twins.
Origin and occurrence: Hydrothermal in cavities in granitic pegmatites, associated with albite, petalite and elbaite, also as pseudo-morphs after petalite. It occurs in San Piero in Campo, Elba, Italy and in the Opal Hill quarry, Riverside, California, USA.

Ferrierite-Ca

ZEOLITE GROUP

$(Ca,Na,K,Mg)_6Al_6Si_{30}O_{72} \cdot 18\ H_2O$

ORTHORHOMBIC ● ●

Properties: C – colorless, white, greenish, pink, brownish; S – white; L – vitreous; D – transparent to translucent; DE – 2.1; H – 3-3.5; CL – good; F – uneven to conchoidal; M – tabular crystals, platy and columnar aggregates, massive.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, along the cracks of the Alpine-type veins and in volcanic tuffs, associated with calcite and zeolites. Platy aggregates occur in Svojanov, Czech Republic; Albero Bosso and Monastir, Sardinia, Italy; Kamploops Lake, British Columbia, Canada.

Ferrierite-Ca, 2 mm aggregates, Regec, Hungary



Dachiardite-Ca, 2 mm xx, Regec, Hungary



Laumontite

ZEOLITE GROUP

$Ca_4Al_8Si_{16}O_{48} \cdot 18\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish; S – white; L – vitreous; D – transparent to translucent, weathered almost opaque; DE – 2.4; H – 3-4; CL – good; F – uneven to conchoidal; M – prismatic crystals, fibrous and radial aggregates.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, along the cracks in the Alpine-type veins, in ore veins and sediments, associated with calcite and other zeolites. Colorless and white acicular crystals up to 38 cm ($14^{15}/_{16}$ in) long come from the Pandulena Hill Quarries, India. Crystals up to 150 mm (6 in) long known from Pine Creek, Bishop, California, USA. It was also found in Dillenburg, Germany.

Laumontite, 120 mm, Markovice, Czech Republic



Heulandite-Ca, 8 mm xx, Parana, Brazil



Heulandite-Ca

ZEOLITE GROUP

$(Ca_{0.5},Sr_{0.5},Na,K)_{4.5}Al_9Si_{27}O_{72} \cdot 24\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish, red, brown; S – white; L B vitreous to pearly; D – transparent to translucent; DE – 2.1; H – 3.5-4; CL – perfect; F – uneven to conchoidal; M – prismatic to tabular crystals, granular, massive.

Origin and occurrence: Hydrothermal in cavities in volcanic rocks, in the Alpine-type fissures, ore veins and sedimentary rocks, usually associated with calcite and other zeolites. Colorless and white tabular crystals up to 100 mm (4 in) across come from Nasik, India; West Paterson, New Jersey, USA; Teigarhorn, Iceland. Red heulandite found in Val di Fassa, Italy.

Clinoptilolite-Ca, 2 mm xx, Hon?ova Hurka, Czech Republic



Clinoptilolite-Ca

ZEOLITE GROUP

$(Ca_{0.5},Na,K)_{4.5}Al_9Si_{27}O_{72} \cdot 24\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish, red, greenish; S – white; L – vitreous; D – transparent to translucent; DE – 2.2; H – 3.5-4; CL – perfect; F – uneven to conchoidal; M – platy crystals, massive.
Origin and occurrence: Hydrothermal in volcanic-sedimentary rocks. Large industrial deposits occur in New Zealand, Japan and Australia. Crystals come from Agate Beach, Oregon, USA.
Application: construction, chemical industry and agriculture.

Stilbite-Ca

ZEOLITE GROUP

$(Ca_{0.5},Na,K)_9Al_9Si_{27}O_{72} \cdot 28\ H_2O$

MONOCLINIC ● ● ● ●

Properties: C – colorless, white, yellowish, pinkish, brown; S – white; L – vitreous, locally pearly; D – transparent to translucent; DE – 2.2; H – 3.5-4; CL – good; F – uneven to conchoidal; M – prismatic and tabular crystals, commonly complicated interpenetration twins and sheaf-like aggregates, granular, massive.
Origin and occurrence: Hydrothermal in cavities of volcanic rocks, along Alpine-type fissures, in ore veins, also in sedimentary rocks and hot springs, typically associated with calcite and other zeolites. Colorless and white tabular crystals and their combinations up to 200 mm ($7\frac{7}{8}$ in) across come from the Pandulena Hill Quarries, India. Crystals are also known from Teigarhorn, Iceland; Faeroe Islands; West Paterson, New Jersey, USA and elsewhere.

Epistilbite, 15 mm x, Nasik, India



Epistilbite

ZEOLITE GROUP

$(Ca,Na_2)Al_2Si_4O_{12} \cdot 4\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, yellowish, pinkish, light brown; S – white; L – vitreous; D – transparent to translucent; DE – 2.2; H – 4; CL – good; F – uneven to conchoidal; M – prismatic crystals, radial aggregates.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks; associated with other zeolites. Clear and white tabular crystals and their twins up to 30 mm ($1\frac{3}{16}$ in) across come from Jalgaon, India; also in Teigarhorn, Iceland and Faeroe Islands.

Stilbite-Ca, 83 mm, Nasik, India



Gismondine, 2 mm xx, Tapolca-Diszel, Hungary



Gismondine

ZEOLITE GROUP

$CaAl_2Si_2O_8 \cdot 4{,}5\ H_2O$

MONOCLINIC ● ●

Properties: C – colorless, white, bluish, pinkish; S – white; L – vitreous; D – transparent to translucent; DE – 2.3; H – 4.5; CL – good; F – uneven; M – complex twins of crystals, platy aggregates.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, in hydrothermally altered rocks. It comes from Capo di Bove, Italy; Schiffenberg, Germany and Dobrna, Czech Republic.

Harmotome, 79 mm, Strontian, UK



Phillipsite-K, 3 mm xx, Limberg, Germany



Phillipsite-K

ZEOLITE GROUP

$(K,Na,Ca_{0.5})Al_5Si_{11}O_{32} \cdot 12\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, reddish; S – white; L – vitreous; D – transparent to translucent; DE – 2.2; H – 4-4.5; CL – good; F – uneven; M – prismatic crystals and complex interpenetration twins, granular, massive.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, sedimentary rocks and hot springs; associated with calcite and other zeolites. Colorless and white interpenetration twins up to 20 mm ($^{25}/_{32}$ in) across come from Capo di Bove, Italy; Doughboys, Tasmania, Australia; Sovince near Litomiøce, Czech Republic and elsewhere.

Harmotome

ZEOLITE GROUP

$(Ba_{0.5},Ca_{0.5},K,Na)_5Al_5Si_{11}O_{32} \cdot 12\ H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, gray, reddish, yellow, brown; S – white; L – vitreous; D – transparent to translucent; DE – 2.4; H – 4.5; CL – good; F – uneven; M – prismatic crystals, commonly complex interpenetration twins, granular massive.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks, in the Alpine-type veins, ore veins and in pegmatites. Prismatic crystals and their twins up to 20 mm ($^{25}/_{32}$ in) across are known from Strontian, Scotland, UK. Crystals also come from St. Andreasberg and Oberstein, Germany; Kozakov, Czech Republic and Kongsberg, Norway.

Goosecreekite

ZEOLITE GROUP

$CaAl_2Si_3O_{10} . 5 H_2O$

MONOCLINIC ●

Properties: C – white, colorless; S – white; L – vitreous; D – transparent to translucent; DE – 2.2; H – 4.5; CL B perfect; F – uneven to conchoidal; M – prismatic crystals, granular.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks. It is known from Goose Creek, Virginia, USA. Crystals up to 30 mm (1 3/16 in) across found in the Pandulena Hill quarries, India.

Goosecreekite, 25 mm xx, Maharashtra, India



Chabasite-Ca

ZEOLITE GROUP

$(Ca_{0.5},Na,K)Al_4Si_8O_{24} . 12 H_2O$

TRIGONAL ● ● ●

Properties: C – colorless, white, yellowish, pinkish, greenish; S – white; L – vitreous to dull; D – transparent to translucent; DE – 2.2; H – 4-4.5; CL – imperfect; F – uneven to conchoidal; M – rhombohedral crystals and their twins, granular, massive.
Origin and occurrence: Hydrothermal in cavities in volcanic rocks and pegmatites, along Alpine-type fissures and in hot springs, usually associated with calcite and other zeolites. Colorless and white interpenetration twins up to 60 mm (24 in) across, come from Faeroe Islands. Crystals are also known from Repcice, Czech Republic; Berufjord, Iceland; Panvil, India; Maglovec, Slovakia and elsewhere.

Chabazite-Ca, Passboro, Nova Scotia, Canada





10. Organic compounds

Whewellite

$CaC_2O_4 . H_2O$

MONOCLINIC ● ● ●

Properties: C – colorless, white, grayish; S – colorless; L – vitreous; D – transparent to translucent; DE – 2,2; H – 2,5; CL – good; F – conchoidal; M – prismatic crystals, commonly twinned.
Origin and occurrence: Rare hydrothermal, mainly sedimentary in coal basins, associated with barite, ankerite and other minerals. Hydrothermal crystals up to 70 mm (2¾ in) long, come from U-bearing veins in PrRbram, Czech Republic. Similar crystals, up to 70 mm (2¾ in) long, occurred in Cavnic, Romania. Heart-shaped and butterfly twins, up to 100 mm (4 in) found in concretions near Kladno, Czech Republic. Similar specimens are known from Burgk near Dresden, Germany. Interesting flat radial aggregates found along cracks in clays in the vicinity of Most, Czech Republic.



Amber, 40 mm, Baltic Sea, Latvia
Whewellite, 27 mm x, Burgk, Germany

Mellite, 170 mm, Bicske-Csordakút, Hungary



Mellite

$Al_2[C_6(COO)_6] . 18 H_2O$

TETRAGONAL ● ●

Properties: C – honey-yellow; S – white; L – resinous to vitreous; D – transparent to translucent; DE – 1,7; H – 2; CL – imperfect; F – conchoidal; M – dipyramidal crystals, granular; LU – blue.
Origin and occurrence: Secondary in the cracks in brown coal and lignite. The best specimens with crystals up to 40 mm ($1\frac{9}{16}$ in) in size, come from Csordakut near Tatabanya, Hungary. Crystals, up to 10 mm ($\frac{3}{8}$ in) across, were found in Artern, Germany. Granular aggregates are known from Valchov, Czech Republic.

Evenkite

$C_{24}H_{50}$

MONOCLINIC ●

Properties: C – colorless to light yellow; S – colorless; L – waxy; D – translucent; DE – 0,9; H – 1; CL – good; M – pseudo-hexagonal tabular crystals; R – melts at 50EC (122°F).
Origin and occurrence: Probably secondary. It occurs within geodes near Evenki, Siberia, Russia. Also known from the cracks in altered andesite in Dubnik, Slovakia.

Fichtelite

$C_{19}H_{34}$

MONOCLINIC ● ● ●

Properties: C – colorless to yellowish; S – colorless; L – vitreous; PS – transparent to translucent; DE – 1; H – 1; M – thin tabular crystals, scales, crystalline crusts.

Evenkite, 50 mm, Dubnik, Slovakia



Origin and occurrence: Secondary, typical mineral of peat-bogs. Its crystals are known from Borkovice near Sobeslav, Czech Republic; also known from Marktredwitz, Germany.

Amber

a mixture of hydrocarbons

AMORPHOUS ● ● ●

Properties: C – honey-yellow, yellow-brown, brown, red-brown, blue, green, black; S – white; L – resinous, dull; D – transparent to translucent, rare opaque; DE – 1,0-1,1; H – 2-2,5; CL – none; F – conchoidal; M – massive irregular or drop-shaped aggregates, nodules and fragments; LU – light blue, yellow.
Origin and occurrence: Amber is a petrified resin from Tertiary and Mesozoic conifers, occurring rarely in sediments. Plant or insect remnants are sometimes found trapped in amber. The most famous localities are located along the southern coast of the Baltic Sea in Poland, Germany, Lithuania, Estonia, Latvia and Russia. The largest masses found weighed up to 10 kg (22 lb). Blue amber is known from the Dominican Republic. Other amber localities are found in Syria, Lebanon, Thailand, Vietnam, Canada and the USA.
Application: as a gemstone.

Fichtelite, 80 mm, Mazice, Czech Republic

Amber, 95 mm, Madagascar



11. Rocks, meteorites and tektites

Rocks consist of minerals and often of fragments of other rocks and organic matter. Since rocks are mixtures, we cannot determine certain physical / chemical data (chemical formula, crystal system, hardness, etc.). Unlike minerals, some rocks form huge bodies which may cover several thousand km^2 so no single localities are shown in this book. Rocks are mainly used for building, in agriculture, and as raw materials for chemicals, ceramics and metals.
Rocks are generally divided into three principal groups according to their origin:

1. **igneous rocks**
2. **sedimentary rocks**
3. **metamorphic rocks**.

1. Igneous rocks

Properties: C – light gray, gray, white, brown, black, gray-green, pinkish, red-brown; D – opaque, rare transparent to translucent; L – dull, rare vitreous; DE – varies from 2.6 up to about 3.8; F – uneven, rare conchoidal; M – coarse to fine grained, commonly massive aggregates, consisting of microscopic or larger grains or crystals of various minerals, up to several decameters across, glass is also present rarely. Minerals in rocks usually have characteristic texture features, like graphic granite and others.

Origin and classification: Igneous rocks form at high temperature and commonly at high pressure in solidification of mainly silicate magma of variable composition. The mineral composition reflects a chemical composition of magma. Typical rock-forming minerals are quartz, orthoclase, microcline, plagioclase, biotite, muscovite, amphiboles, pyroxenes, olivine and nepheline. Rocks may solidify at various depths, according to which they are either intrusive, dyke or effusive. They can be grouped according to chemical composition (SiO2 content):
felsic – granite, syenite, pegmatite, rhyolite, obsidian
intermediate – diorite, andesit **basic** – gabbro, basalt
utrabasic – peridotite, varies from 1.0 up to about 2.8; F – uneven, sometimes conchoidal; M – coarse to fine grained and massive aggregates, consisting of grains or crystals, from microscopic to several dm in size, also of rock fragments and organic matter, banded textures are typical and some rocks are fossiliferous.

Granite, 65 mm, Norway



Orbicular granite, 150 mm, Sweden
Pegmatite, 65 mm, Dolni Bory, Czech Republic



Diabase, 65 mm, Rožany, Czech Republic



Sandstone, 65 mm, Buffalo Gap, South Dakota, U.S.A.

Conglomerate, 65 mm, St.Alban, UK



2. Sedimentary rocks

Properties: C – grey, brown, red-brown, black, green-grey, pinkish, white, yellow, often variable even within one rock, banding is typical; D – opaque, rare translucent; L – dull, sometimes vitreous, greasy or earthy; DE -varies from 1.0 up to about 2.8; F - uneven, sometimes conchoidal; M – coarse to fine grained and massive aggregates, consisting of grains or crystals, ranging from microscopic to several dm in size, also of rock fragments and organic matter, banded textures are typical and some rocks are fossiliferous.

Origin and classification: Sedimentary rocks originate under surface temperatures and pressures, as a result of sedimentation of mineral and rock fragments and organic matter of different size through the water and wind activity, or by precipitation from water solutions. Typical rock-forming minerals are quartz, calcite, dolomite, halite, clay minerals and others. According to their origins we can distinguish several groups of sedimentary rocks:

clastic (consisting of rock fragments) – sandstone, conglomerate, quartzite, siltstone.

organic (consisting mainly of organic matter) – limestone, coal.

chemical (originating by precipitation from water solutions) – evaporites, travertine.

Limestone, 65 mm, Italy



Evaporite, 40 mm, Walkenried, Germany



Serpentinite, 65 mm, Hrubšice, Czech Republic



Gneiss, 65 mm, Doubravcany, Czech Republic



3. Metamorphic rocks

Properties: C – light gray, gray, brown, green, red-brown, black, green-gray, pinkish, white, sometimes variable within one rock, banding is relatively common; D – opaque; L – dull, rare vitreous; DE – varies from 2.5 to 4.8; F – uneven, rare conchoidal; M – coarse to fine-grained, platy, acicular and sometimes massive aggregates, consisting of grains and crystals, ranging from microscopic to several decimeters across. Typical are planar textures and foliation of some minerals.

Origin and classification: Metamorphic rocks originate under higher temperature and pressure during metamorphism of originally igneous or sedimentary rocks. The source of a thermal energy could be magma, then this type is called contact metamorphism, or the thermal source lies in the depth of the earth's crust and effects large areas, then this type is called regional metamorphism. During a process of metamorphism new minerals originate. Typical rock-forming metamorphic minerals are quartz, orthoclase, plagioclases, biotite, muscovite, amphiboles, pyroxenes, calcite, dolomite, sillimanite, kyanite, almandine, staurolite and serpentine.

Regionally metamorphosed rocks: serpentinite, mica schist, gneiss, marble.

Contact metamorphosed rocks: contact chert (porcelanite), skarn.

Marble, 100 mm, Greece



Skarn, 65 mm, Lisna, Czech Republic



Iron meteorite, 50 mm, Sikhote-Alin, Russia



Iron meteorite, 40 mm detail, Gibeon, Namibia



Meteorites

Properties: C - light gray, gray, gray-green, black; D – opaque; L – dull, metallic, rare vitreous; DE – varies from 3.0 to 7.3; F – uneven; M – coarse to fine-grained, sometimes massive aggregates, consisting of irregular grains of different minerals, ranging from microscopic to several cm across.

Origin and classification: Meteorites are igneousrocks formed in space. Most originate in the asteroidbelt between Mars and Jupiter. They consist of various minerals and their chemical composition differs greatly. Typical rock-forming minerals in meteorites are olivine, pyroxenes, plagioclases, Fe and Ni alloys and sulfides, rarely also organic matter. Meteorites fall into four main groups, accordingto metallic iron and silicate component:

iron meteorite;

siderolite;

chondrite;

achondrite;

Occurrence: Meteorite falls are known throughout the world. The largest known iron meteorite, weighing approximately 60 tons , is located near the Hoba farm, Namibia. The largest known chondrite, weighing about 1 ton , fell in 1948 in Norton County, Nebraska, USA. Most meteorites that have been found recently come from large glaciers such as those of Antarctica and from desert in Namibia.

Moldavite, 35 mm, Southern Bohemia, Czech Republic



Tectite, 55 mm, Dalat, Vietnam



Tektites

Properties: C – light to dark green, yellow-green, brown-green, brown, green-gray, black; D – transparent, translucent to opaque; L – vitreous; DE – varies from 2.3 to 2.6; H – 6-7; F – conchoidal to uneven; M – massive irregular, drop-shaped or disc-shaped aggregates, irregular fragments, sometimes with typical sculptured surface.

Origin, classification and occurrence: Natural glasses, rich in SiO2, which formed as a result of rapid melting of surface rocks during impacts of large meteorites or comets.

They are classified according to their age and occurrence (following sequence from the oldest to the youngest):

Bediasites and georgianites – the USA, Mexico, Barbados, Cuba;

Urengoites – Novyi Urengoi, Russia;

Moldavites – southern Bohemia and western Moravia, Czech Republic;

Ivorites – Ivory Coast;

Irghisites – Zhamanshin, Russia;

Indochinites, phillipinites, javanites, bilitonites – southeastern Asia;

Australites – Australia.

Application: some tektites, mainly moldavites, as gemstones.

Moldavites, 40 mm, Southern Bohemia, Czech Republic



Recommended literature

Anthony J.W. et al. (1990, 1995, 1997):
Handbook of Mineralogy I, II, III,
Mineral Data Publishing, Tucson.

Bernard J.H., Rost R. a kol. (1992):
Encyklopedický prehled mineralů ,
Academia, Prague, in Czech.

Clark A.M. (1993):
Hey's Mineral Index, 3rd print,
Chapman & Hall, London.

Duda R., Rejl L. (1986):
Minerals of the World,
Hamlyn, Twickenham.

Fleischer M., Mandarino J.A. (1995):
Glossary of Mineral Species,
Mineralogical Record, Tucson.

Roberts W.L. et al. (1990):
Encyclopedia of Minerals,
Van Nostrand Reinhold, New York.

Strunz H. (1977):
*Mineralogische Tabellen,*6th print,
Geest & Portig, Leipzig.

Porcelanite, 85 mm, Komňa, Czech Republic
Agate, 50 mm, Zeleznice, Czech Republic

THE COMPLETE ENCYCLOPEDIA OF
MINERALS

The Complete Encyclopedia of Minerals is a book for all the people, who are interested in the beautiful world of minerals. They can find here hundreds of photographs of beautiful crystals and crystal aggregates, together with a list of classic and new occurrences for each mineral species. Minerals are arranged into chapters according to the mineral system:

- Elements • Sulfides • Halides • Oxides
- Carbonates • Borates • Sulphates • Phosphates
- Silicates • Organic compounds
- Rocks, meteorites and tektites

ISBN 1-84013-404-6

9 781840 134049

DK


As
Au
Zirconium gemstone
Eu
Helium-filled balloon
Lithium ore
Nickel-plated spoon
Silicon computer chip
Mg
Ca
Mercury thermometer

THE PERIODIC TABLE BOOK

A VISUAL ENCYCLOPEDIA OF THE ELEMENTS

Zn
Vanadium ore
C
Hydrogen-rich atmosphere of Jupiter
Indium LED
Sulfur ore
Aluminium foil
Copper wire
Br
Ba
Cl

DK | Penguin Random House

DK India

Senior Editor Bharti Bedi
Project Art Editor Amit Verma
Editorial Team Neha Ruth Samuel, Charvi Arora, Deeksha Saikia
Art Editors Mansi Agrawal, Amisha Gupta, Ravi Indiver
Assistant Art Editors Neetika Malik Jhingan, Nidhi Rastogi
Jacket Designer Suhita Dharamjit
Jackets Editorial Coordinator Priyanka Sharma
Senior DTP Designer Harish Aggarwal
DTP Designers Sachin Gupta, Syed Md Farhan, Nityanand Kumar, Mohammad Rizwan
Picture Researcher Nishwan Rasool
Managing Jackets Editors Saloni Singh, Sreshtha Bhattacharya
Picture Research Manager Taiyaba Khatoon
Pre-production Manager Balwant Singh
Production Manager Pankaj Sharma
Managing Editor Kingshuk Ghoshal
Managing Art Editor Govind Mittal

DK UK

Project Editor Ashwin Khurana
Senior Art Editor Smiljka Surla
Jacket Editor Claire Gell
Senior Jacket Designer Mark Cavanagh
Jacket Design Development Manager Sophia MTT
Managing Editor Dr Lisa Gillespie
Managing Art Editor Owen Peyton Jones
Producers, Pre-production Dragana Puvacic, Catherine Williams
Producer Anna Vallarino
Publisher Andrew Macintyre
Art Director Karen Self
Associate Publishing Director Liz Wheeler
Design Director Phil Ormerod
Publishing Director Jonathan Metcalf

Photographer Ruth Jenkinson
Photography Assistant Julie Stewart

Element samples prepared and supplied by RGB Research Ltd
www.periodictable.co.uk

First published in Great Britain in 2017 by
Dorling Kindersley Limited
80 Strand, London WC2R 0RL

Copyright © 2017 Dorling Kindersley Limited
A Penguin Random House Company
10 9 8 7 6 5 4 3 2 1
001–289022–April/2017

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written permission of the copyright owner.

A CIP catalogue record for this book is available from the British Library

ISBN: 978-0-2412-4043-4

Printed in China

A WORLD OF IDEAS:
SEE ALL THERE IS TO KNOW

www.dk.com

CONTENTS

Foreword 6
Elemental building blocks 8
Chemical discoveries 10
Inside an atom 12
Periodic table of elements 14
Reactions and uses 16

Hydrogen 18
Hydrogen 20

Alkali Metals 22
Lithium 24
Sodium 26
Salt flats 28
Potassium 30
Rubidium 32
Caesium, Francium 34

Alkaline Earth Metals 36
Beryllium 38
Magnesium 40
Calcium 42
Fly Geyser 44
Strontium 46
Barium 48
Radium 50

Transition Metals 52

Scandium, Titanium 54
Vanadium, Chromium 56
Manganese 58
Iron 60
Steelmaking 62
Cobalt 64
Nickel 66
Copper 68
Copper wires 70
Zinc 72
Yttrium 74
Zirconium, Niobium 76
Molybdenum, Technetium 78
Ruthenium, Rhodium 80
Palladium 82
Silver 84
Cadmium, Hafnium 86
Tantalum, Tungsten 88
Rhenium, Osmium 90
Iridium 92
Platinum 94
Gold 96
Golden Buddha 98
Mercury 100
Rutherfordium, Dubnium, Seaborgium 102
Bohrium, Hassium, Meitnerium 104
Darmstadtium, Roentgenium, Copernicium 106

Lanthanides 108

Lanthanum, Cerium, Praseodymium 110
Neodymium, Promethium, Samarium, Europium 112
Gadolinium, Terbium, Dysprosium, Holmium 114
Erbium, Thulium, Ytterbium, Lutetium 116

Actinides 118

Actinium, Thorium, Protactinium 120
Uranium, Neptunium, Plutonium, Americium 122
Curium, Berkelium , Californium, Einsteinium 124
Fermium, Mendelevium, Nobelium, Lawrencium 126

The Boron Group 128

Boron 130
Aluminium 132
Jet turbine 134
Gallium, Indium 136
Thallium, Nihonium 138

The Carbon Group 140

Carbon 142
Pink diamond 144
Silicon 146
Germanium, Tin 148
Lead, Flerovium 150

The Nitrogen Group 152

Nitrogen 154
Drag racing 156
Phosphorus 158
Arsenic, Antimony 160
Bismuth, Moscovium 162

The Oxygen Group 164

Oxygen 166
Sulfur 168
Danakil Depression 170
Selenium, Tellurium 172
Polonium, Livermorium 174

The Halogen Group 176

Fluorine 178
Chlorine 180
Ocean clean up 182
Bromine 184
Iodine, Astatine, Tennessine 186

Noble Gases 188

Helium 190
Nebula 192
Neon, Argon 194
Krypton, Xenon 196
Radon, Oganesson 198

Glossary 200
Index 204
Acknowledgements 208

Chunk of yttrium

Chunk of silver

Zirconium crystal bar

Foreword

Everything in nature, from the mountains and the oceans to the air we breathe and food we eat are made up of simple substances called elements. You may have already heard of several of them, including gold, iron, oxygen, and helium, but these are just four out of a total of 118. Many have unique – and sometimes surprising – chemical and physical properties. Gallium, for example, is a solid but melts in your hand. A compound of sulfur gives off a nasty smell of rotten eggs. Fluorine is a gas that can burn a hole straight through concrete!

The elements are rarely found in their pure form. Mostly, they are combined with each other to make compounds, which make up substances around us. For example, hydrogen and oxygen make water, sodium and chlorine form salt, and carbon is found in millions of compounds, many of which – including proteins and sugars – make our bodies work.

To find out more about the elements, we need to take a good look at the periodic table. This is used by scientists around the world to list and detail the elements. It shows the key information

Nickel balls

Cube of melting gallium

Iodine in a glass sphere

Barium crystals

Chunk of grey selenium

Magnesium crystals

Osmium pellet

for each element, grouping them into similar types. With this information, we can use the elements to make many things we need: a fluorine compound in toothpastes toughens our teeth and silicon crystals engineered into microchips operate our gadgets and phones.

Every element has its own story of where it comes from, what it can do, and how we use it. Let's begin a tour of every element one by one. It's going to be a fascinating journey.

Tom Jackson

Throughout this book you will find boxes with the following symbols. This is what each of them mean.

	This shows the structure of an atom of an element, with the nucleus (made of protons and neutrons) at the centre and electrons surrounding it in their shells.
⊖	Electron
⊕	Proton
○	Neutron
State	The state of the element at a temperature of 20°C (28°F). It can be a liquid, solid, or gas.
Discovery	This details the year in which the element was discovered.

Chunk of uranium

Gold crystals


Thulium crystals

Calcium crystals

Elemental building blocks

Elements are everywhere: some you can see, like gold, others are almost invisible, like oxygen gas. An element is a substance that cannot be broken up into simpler ingredients. Each one is made up of tiny building blocks called atoms, which are unique for every element. Most elements are joined with other elements to make compounds, which are made by combining two or more elements. This includes water, which is a compound of hydrogen and oxygen.

Elements in our world

There are 118 elements in the periodic table; 92 of them are found in nature, while the others are made by humans. Every element is unique. Most of the elements are solids, like the metals. At room temperature, 11 elements are gases, while bromine and mercury are the only two liquids.

Bromine liquid with bromine gas

Bismuth crystals

Earth


Water

Air

Fire

Ancient ideas

The idea of elements is very old, dating back about 2,600 years to ancient Greece. However, Greek thinkers believed that the world was made of just four elements: earth, water, fire, and air. Empedocles, an influential scholar, was the first to propose that these elements made up all structures. Only much later did scientists learn that none of these are actually elements. For thousands of years, everybody from ancient Egyptian priests to medieval European alchemists, speculated about the definiton and classification of an element.

Elements in and around us

About 99 per cent of the human body is made from just six elements, though they are combined together to form thousands of different compounds. On the other hand, Earth's atmosphere is a mixture of gases, most of which are pure elements. About 99 per cent of the air is made from nitrogen and oxygen.



Human body



Earth's atmosphere

Gold crystals


Iranian alchemists in their workshop

Alchemy and mysticism

Chemists are scientists who study elements and compounds. However, before they existed, the alchemists were medieval researchers. Believing in a mixture of science and magic, alchemists tried to change ordinary metals (such as lead) into gold. They failed because elements cannot be changed from one type to another. But, in the process, they discovered many new elements and developed several processes that chemists still use today.

ROBERT BOYLE

The first person to use science to understand the elements was the Irish scientist and inventor Robert Boyle. He pursued science through reason, and in the 1660s he performed the first chemistry experiments to show that much of what the alchemists believed was wrong.



Chemical discoveries

Humphry Davy
In the early 19th century, the English scientist Humphry Davy discovered several new metals. He used a revolutionary process called electrolysis, in which electric currents split chemical compounds into their elements. Davy discovered a total of nine new elements, including magnesium, potassium, and calcium.

The ancient concept of four elements – earth, water, fire, and air – expanded to a belief that every substance on Earth was made from a mixture of these elements. However, many substances including mercury, sulfur, and gold did not fit this idea. Over the last 300 years, chemists have followed a long series of clues to reveal the true nature of elements, their atoms, and what happens to them during chemical reactions.

Pioneering chemists

Many of the first breakthroughs in chemistry came in the 1700s, from investigations into the composition of air. Chemists such as Joseph Black, Henry Cavendish, and Joseph Priestly discovered several different "airs", which we now call gases. They also found that the gases could react with solid substances, which they called "earths". These discoveries began a journey that revealed that there were dozens of elements, not just four. Today, scientists have identified 118 elements, but more may be discovered in time.

Antoine Lavoisier
In 1777, the French scientist Antoine Lavoisier proved that sulfur was an element. This yellow substance was familiar for thousands of years, but Lavoisier performed experiments to show that it was a simple substance that could not be divided up any further. In the same year, he also found out that water was not an element, but a compound of hydrogen and oxygen.


Granule of pure sulfur

Magnesium crystals

JOHN DALTON

Like many scientists of his day, the English scientist John Dalton already believed that matter must be made of tiny particles. In 1803, he began to think about how these particles might join together. He came to realize that there are different particles for every element, and that the particles of one element all have the same mass. He also realized that the particles of different elements combine in simple proportions to make compounds. So, for example, the particles of the elements carbon and oxygen can combine to make carbon monoxide. He suggested that during a chemical reaction, the particles rearrange to make compounds. He formulated the first modern theory of atoms.



ELEMENTS

⊙	Hydrogen	1		Strontian	46
	Azote	5		Barytes	68
●	Carbon	54	I	Iron	50
○	Oxygen	7	Z	Zinc	56
	Phosphorus	9	C	Copper	56
⊕	Sulphur	13	L	Lead	90
	Magnesia	20	S	Silver	190
	Lime	24	G	Gold	190
	Soda	28	P	Platina	190
	Potash	42		Mercury	167

Dalton's table of elements

States of matter

Elements can exist in three states of matter: solid, liquid, and gas. At room temperature, most elements are solids, 11 are gases, and only two are liquids. However, elements can change from one state into another. These changes don't alter the atoms of these elements, but arrange them in different ways.



A solid keeps its shape and has a fixed volume.

In a solid, all the atoms are attracted to each other and locked in position.



A liquid takes the shape of its container, but its volume remains fixed.

In a liquid, the atoms begin to move around as the attraction between them weakens.



A gas will fill any container, no matter how large or small.

In a gas, the atoms are weakly attracted to each other, so they all move in different directions.

Jacob Berzelius
In the early 1800s, the Swedish doctor Jacob Berzelius investigated chemicals in rocks and minerals. He found two minerals that contained new elements. He named these elements cerium (after Ceres, the dwarf planet) and thorium (after Thor, the Viking god of thunder). Berzelius also invented a system of using symbols and numbers that chemists still use to identify elements and compounds today.

Chunk of pure cerium

Pure caesium inside a sealed container

Robert Bunsen
The German chemist Robert Bunsen is best known for inventing a gas burner that is often used in laboratories. In the 1850s, Bunsen used such a burner – which produced a hot, clean flame – to study the unique flame colours produced by different elements. When an unknown substance made bright blue flames, he named it caesium, meaning "sky blue".

Inside an atom

An atom is the smallest unit of an element. Atoms are too small to see (even with the most powerful microscopes) but they are everywhere. They consist of smaller particles called protons, neutrons, and electrons. Every element has a unique number of protons.

What's the atomic number?

The number of protons in an atom of an element is called the atomic number. The atomic number of an atom identifies the element it belongs to. Every atom also has an equal number of electrons. For elements found naturally on Earth, hydrogen has the smallest atomic number (1), while uranium atoms have the highest atomic number (92).

1
H

Atomic number



This shell is the space in the hydrogen atom where one electron circles the proton at the centre of the atom.

Hydrogen atom

3
Li



In a lithium atom, two shells house three electrons, which circle the protons and neutrons at the centre.

Lithium atom

92
U



Seven shells house the 92 electrons in a uranium atom.

Uranium atom

Electron ❯ The tiny, negatively charged particles in an atom are called electrons. They are involved in the way the atoms of an element react and form bonds with the atoms of other elements.

Shell ❯ The electrons in an atom move around the nucleus. They are arranged in layers called shells. When reacting with each other, atoms tend to fill up their outer shells to become more stable.

Neutron ❯ As its name suggests, neutrons are neutral particles, which means they do not have an electric charge. A neutron weighs the same as a proton, and much more than a electron.

Proton ❯ Protons have a positive electric charge. This charge attracts the negatively charged electrons, holding them in place around the nucleus. Because each proton's charge is cancelled out by the equal charge of an electron, the atom has no overall charge, and is therefore neutral.



Nucleus ❯ The central core, or nucleus, of an atom is made up of protons and neutrons. Nearly all the mass of the atom is packed into the nucleus, and this gives every element a unique atomic mass.

Atomic facts



Isotopes

While every element has a unique number of electrons and protons in its atoms, the number of neutrons can vary. These different forms are called isotopes. For example, helium has two isotopes: one contains three neutrons (He-3), the other has four (He-4).

Electromagnet attracts metal pieces

Electromagnetism

Atoms work like tiny magnets. A force called electromagnetism holds them together. It makes particles with opposite charges, such as protons and electrons, attract each other. Those with similar charges repel each other. A magnet is an object in which the magnetic forces of the atoms attract and repel other objects. An electromagnet develops magnetism when an electric current runs through it.

ATOMIC PIONEERS

During his atomic research in the early 20th century, Sir Ernest Rutherford, a New Zealand scientist, expanded our understanding of the structure of atoms. He discovered protons and proved that they were located in an atom's nucleus.



Sir Ernest Rutherford

Periodic table of elements

The periodic table is a useful way of organizing the elements. It arranges the elements in order of their atomic number, which is the number of protons in the nucleus of an atom, and is unique to every element. The table also divides the elements into rows, called "periods", and columns, called "groups". Dmitri Mendeleev, the chemist who devised the table, arranged the elements based on the similarity of certain physical and chemical properties.



1 **H** 1.0079											
3 **Li** 6.941	4 **Be** 9.0122										
11 **Na** 22.990	12 **Mg** 24.305										
19 **K** 39.098	20 **Ca** 40.078	21 **Sc** 44.956	22 **Ti** 47.867	23 **V** 50.942	24 **Cr** 51.996	25 **Mn** 54.938	26 **Fe** 55.845	27 **Co** 58.933	28 **Ni** 58.693	29 **Cu** 63.546	30 **Zn** 65.39
37 **Rb** 85.468	38 **Sr** 87.62	39 **Y** 88.906	40 **Zr** 91.224	41 **Nb** 92.906	42 **Mo** 95.94	43 **Tc** (96)	44 **Ru** 101.07	45 **Rh** 102.91	46 **Pd** 106.42	47 **Ag** 107.87	48 **Cd** 112.41
55 **Cs** 132.91	56 **Ba** 137.33	57-71 **La-Lu**	72 **Hf** 178.49	73 **Ta** 180.95	74 **W** 183.84	75 **Re** 186.21	76 **Os** 190.23	77 **Ir** 192.22	78 **Pt** 195.08	79 **Au** 196.97	80 **Hg** 200.59
87 **Fr** (223)	88 **Ra** (226)	89-103 **Ac-Lr**	104 **Rf** (261)	105 **Db** (262)	106 **Sg** (266)	107 **Bh** (264)	108 **Hs** (277)	109 **Mt** (268)	110 **Ds** (281)	111 **Rg** (272)	112 **Cn** 285
			57 **La** 138.91	58 **Ce** 140.12	59 **Pr** 140.91	60 **Nd** 144.24	61 **Pm** (145)	62 **Sm** (150.36)	63 **Eu** 151.96	64 **Gd** 157.25	65 **Tb** 158.93
			89 **Ac** (227)	90 **Th** 232.04	91 **Pa** 231.04	92 **U** 238.03	93 **Np** (237)	94 **Pu** (244)	95 **Am** (243)	96 **Cm** (247)	97 **Bk** (247)

***The actinides and the lanthanides** are placed between the alkaline earth metals and the transition metals, but have been moved below to give them more space.*

KEY

- 🟦 Hydrogen
- 🟪 Alkali Metals
- 🟨 Alkaline Earth Metals
- 🟧 Transition Metals
- 🟪 Lanthanides
- 🟩 Actinides
- 🟩 The Boron Group
- 🟦 The Carbon Group
- 🟧 The Nitrogen Group
- 🟨 The Oxygen Group
- 🟫 The Halogen Group
- 🟪 Noble Gases

Elements of this group *are semi-metals (elements with the properties of metals and non-metals): they are shiny like metals but crumble easily like non-metals.*

This group *contains the noble gases, which never form bonds with other elements, and are unreactive.*

					2 **He** 4.0026
5 **B** 10.811	6 **C** 12.011	7 **N** 14.007	8 **O** 15.999	9 **F** 18.998	10 **Ne** 20.180
13 **Al** 26.982	14 **Si** 28.086	15 **P** 30.974	16 **S** 32.065	17 **Cl** 35.453	18 **Ar** 39.948
31 **Ga** 69.723	32 **Ge** 72.64	33 **As** 74.922	34 **Se** 78.96	35 **Br** 79.904	36 **Kr** 83.80
49 **In** 114.82	50 **Sn** 118.71	51 **Sb** 121.76	52 **Te** 127.60	53 **I** 126.90	54 **Xe** 131.29
81 **Tl** 204.38	82 **Pb** 207.2	83 **Bi** 208.96	84 **Po** (209)	85 **At** (210)	86 **Rn** (222)
113 **Nh** 284	114 **Fl** 289	115 **Mc** 288	116 **Lv** 293	117 **Ts** 294	118 **Og** 294
66 **Dy** 162.50	67 **Ho** 164.93	68 **Er** 167.26	69 **Tm** 168.93	70 **Yb** 173.04	71 **Lu** 174.97
98 **Cf** (251)	99 **Es** (252)	100 **Fm** (257)	101 **Md** (258)	102 **No** (259)	103 **Lr** (262)

Reading the table

Element symbol

Every element has a unique symbol of one or two letters. These symbols ensure that scientists who speak different languages do not get confused while describing the same element.



The atomic number is the number of protons in the nucleus of this element's atoms.

The first letter of a symbol is always a capital, but the second is lower case.

The atomic mass number is the average of all the atoms of the element. It is not a whole number because there are different isotopes (forms) of each element, each with a different number of neutrons.

Periods

Elements in the same period, or row, have the same number of electron shells in their atoms. So elements in period one have one electron shell, while those in period six have six electron shells.



Periods run from left to right.



Groups run from top to bottom.

Groups

Members of a group, or column, all have the same number of electrons in their outermost shell. For example, group one elements have one outer electron, while group eight elements have eight outer electrons.

DMITRI MENDELEEV

The periodic table was developed by the Russian chemist Dmitri Mendeleev in 1869. Others had tried before, but his table was periodic, or repeating, because the characteristics of elements follow a pattern. The table was incomplete as some elements had not yet been discovered. However, Mendeleev predicted the positions of the missing elements, and was proved right when they were finally isolated many years later.

Reactions and uses

The elements can combine in different ways to make 10 million compounds, possibly more. As well as learning about the physical and chemical properties of elements, chemists also want to find out how and why certain elements react with each other to form compounds. Chemical reactions are happening all the time. During a reaction, substances change into new substances. The bonds that hold them are broken and then remade in a different combination.

Explosive reaction
In this chemical reaction, pure lithium reacts with air to make the compound lithium oxide. It takes energy to break the links between the lithium atoms and then make bonds with oxygen in the air. Reactions need energy to begin, but they often produce energy as heat and light.

1. This piece of pure lithium is placed on a surface and is exposed to the air.

2. A gas torch is used to heat the lithium, and in just a few seconds it turns red, which is a typical colour for this metal when it becomes hot.



3. Very quickly, the lithium catches fire. The white areas forming here are the compound lithium oxide, which is a combintion of lithium and oxygen.

Mixtures

A mixture is a combination of substances that can be separated by physical means, such as filtering. It is not the same as a compound, where the ingredients are connected by bonds and can only be separated using a chemical reaction. Mixtures can be classified as solutions, colloids, and suspensions.



Solution
In this mixture, a substance is completely and evenly mixed, or dissolved, into another substance. Seawater is a solution.



Colloid
This mixture contains unevenly spread particles and clusters that are too small to see. Milk is a colloid.



Suspension
This type of mixture consists of large particles of one substance floating in another substance. Muddy water is a suspension.



1. A sodium atom donates one electron to a chlorine atom. This gives both atoms full outer electron shells.



2. These are now charged atoms known as ions. The sodium ion has a positive charge and the chlorine ion has a negative charge.



3. Sodium is attracted to – and forms a bond with – chlorine, forming a molecule of the compound sodium chloride.

Forming compounds

There are two kinds of bonds formed between elements during a chemical reaction. In an ionic bond, such as in sodium chloride (above), one atom gives away its electron(s) and another accepts them. This results in each having full outer electron shells. The other type is called covalent bonding. In this, atoms sit together and share their electrons so they both have full outer shells.



As lithium burns in air, it becomes lithium oxide.

Reactions in the real world

Chemical reactions happen all around us. There are reactions when we cook, take medication, or breathe. The image above shows a rusty iron ship. Over time, the element iron develops this red, flaky layer when it reacts with oxygen present in water or air to form the compound iron oxide – more commonly known as rust.



Pure hydrogen (H) fills this glass sphere, and produces a purple glow when electrified.



Hydrogen

The first element, hydrogen (H), is located above the alkali metals in the first column of the periodic table. However, because it is so different to the elements below it, hydrogen is not included in their group. This gas has the simplest atoms of any element with one electron and one proton. It is highly reactive and forms compounds with all kinds of other elements.

Atomic structure
A hydrogen (H) atom has one electron moving around a nucleus consisting of a single proton.

Physical properties
Hydrogen gas is the lightest material in the Universe. Pure hydrogen is rare on Earth, as it escapes quickly from the atmosphere into space.

Chemical properties
Hydrogen is highly flammable. It forms compounds with both metals and non-metals.

Compounds
The most common hydrogen compound is water. Acids are compounds that contain hydrogen.

1 H Hydrogen



⊖ 1 ⊕ 1 ○ 0

State: Gas
Discovery: 1766

Forms



Pure hydrogen in a glass sphere

Hydrogen gas *is trapped inside this glass sphere, and gives off a purple glow when electrified.*

The Orion Nebula

This gaseous stellar nursery *is giving birth to thousands of stars.*

The Sun

The Sun *is four-fifths hydrogen.*

Jupiter



Three quarters of this planet *is made up of layers of gaseous and liquid hydrogen.*

Water

Each water molecule *has two atoms of hydrogen and one of oxygen.*

Hydrogen is the first member of the periodic table because it has the simplest atoms of all elements: they contain just one proton and one electron. **Pure hydrogen** is a transparent gas. The biggest planets, such as **Jupiter**, are vast balls of hydrogen mixed with other gases, such as helium and methane. On Earth, hydrogen is commonly found in **water**. Although it is rare in Earth's atmosphere, hydrogen is the most common element in the Universe. Stars, such as the **Sun**, contain large amounts of hydrogen. At the centre of a star, atoms of

Uses

Hydrogen-filled balloon

__This balloon__ can rise high into the atmosphere where sensors gather information about atmospheric pressure, temperature, and wind speed.

HOW ROCKET FUEL WORKS

Many space rockets use liquid hydrogen as a fuel. The hydrogen reacts with oxygen to form extremely hot steam, which blasts out of the nozzle. This creates thrust, which pushes the rocket upwards.



__1__. This chamber contains a fuel called liquid hydrogen.

__2__. This chamber contains liquid oxygen, which helps the hydrogen burn.

__3__. Pumps control the flow of the liquids as they enter the combustion chamber.

__4__. The combustion chamber is where the liquids mix together, creating an explosion.

__5__. The nozzle emits hot vapour, pushing the rocket upwards.

Margarine

__Margarine__ is made of vegetable oils thickened by adding hydrogen.

Hydrogen peroxide

__This liquid__ is used as a cleaner.

Delta IV rocket

__This powerful rocket__ uses 45,460 litres (12,000 gal) of liquid hydrogen as fuel.

The only **waste product** of hydrogen fuel is **steam**.



Hydrogen bomb explosion

__This powerful explosion was__ created by fusing hydrogen atoms.



Hydrogen-powered bus

__This energy-efficient bus__ runs on a fuel cell fed by hydrogen.

this element are fused together, releasing heat and light. New stars form inside **nebulae** – such as the **Orion Nebula**. They are clouds of hydrogen gas that slowly collapse in on themselves. Hydrogen gas is the lightest element of all, and much lighter than air. This is why **hydrogen-filled balloons** can fly higher than air-filled ones. Supercold liquid hydrogen is used as **rocket** fuel. Atoms of hydrogen fuse together to produce a lot of energy in **hydrogen bomb** explosions. Pure hydrogen is also a clean energy source used to power some **buses** and cars.

Potassium (K) tarnishes when exposed to air.



Alkali Metals

After hydrogen (H) – which is in a group of its own – the first column of the periodic table contains the alkali metals. This group gets its name from the way the elements react with water. These vigorous reactions always produce acid-attacking compounds called alkalis. None of the alkali metals are ever found in a pure form in nature. The first three metals are common in many minerals, while the last three are rarer.

Atomic structure
The atoms of all alkali metals have just one electron in their outer shell. Alkali metal atoms are among the biggest of all atoms.

Physical properties
These metals are soft enough to be cut with a knife. They are all silvery and very shiny when clean.

Chemical properties
Alkali metals are highly reactive. They form bonds with other elements, giving away their single outer electron.

Compounds
These metals react with water to form compounds called hydroxides. They react easily with halogens to form salts, such as sodium chloride.

3 Li Lithium



State: Solid
Discovery: 1817

Forms

Drinking water

***This water** contains tiny amounts of dissolved lithium minerals.*

Oyster mushrooms

***These mushrooms** absorb lithium from the soil.*



Lepidolite

Pale quartz

***Purple crystals** containing lithium*



Prawn

***Prawns** and other shellfish absorb lithium from seawater.*



Bar of pure lithium refined in a laboratory

***Shiny pure lithium** becomes dull when it is exposed to air.*

Petalite

Grey-white crystals

Lithium is the the lightest of all metals: in fact, it can easily float on water. **Pure lithium** is very reactive and exists in nature only in minerals, such as **lepidolite** and **petalite**. Many lithium minerals dissolve well in **water**, and the world's seawater contains millions of tonnes of dissolved lithium. Lithium is found in many foods, such as **mushrooms**, **prawns**, nuts, and seeds. It also has many everyday applications. Glass composed of lithium is resistant to heat and is used in scientific equipment, such as **mirrors inside**

Uses

***Smartphones** run on rechargeable batteries that use lithium to store electricity.*

Smartphone



Hale telescope mirror

***Lithium added to the glass in this mirror** stops the disc warping at extreme temperatures.*

LITHIUM-ION BATTERY

Lithium-ion batteries are widely used in digital devices. They store electrical energy to power gadgets and are rechargeable. This diagram shows a device's battery in use; when it is charging, this process is reversed.



***1**. Inside the battery, positively charged lithium ions move from the negative electrode (-) to the positive electrode (+).*

***2**. The positive electrode receives lithium ions as the battery loses charge.*

***3**. As ions move inside the battery, negatively charged electrons are pushed through the phone, providing the electricity to make it work.*

Syringe

***Lithium coating on the inside of some syringes** delays the clotting of the blood sample.*

***Lithium-rich grease** is used to keep mechanical parts of engines running smoothly, even when hot.*

TF2
LUBRICANT
Lithium Grease
40gms e

Grease

***Some artificial teeth** contain lithium disilicate, which makes them strong.*

Artificial teeth

This car runs for at least **64 km** (40 miles) on one charge of its lithium-ion battery.

***This charging point** can recharge an electric car in one hour.*

Electric car

***This air scrubber** used lithium hydroxide to purify the air inside the Apollo 13 spacecraft.*



Air scrubber

telescopes. The main use for lithium is in rechargeable batteries. Lithium-ion batteries are small but powerful, so they are ideal for **smartphones** and tablet computers. Larger lithium batteries can power **electric cars**, which are less polluting than petrol-powered ones. A soapy compound called lithium stearate is used to make **grease**, which helps automobile engines run smoothly. This element also forms hard ceramics that are used to produce strong **artificial teeth**. Lithium compounds are used in some medicines as well.

11 Na Sodium



− 11 + 11 ○ 12

State: Solid
Discovery: 1807

Forms



Clinoptilolite

***This sodium-rich mineral** is an example of a zeolite, a mineral with tiny holes that can trap gases.*



Pure halite crystals

***Cube-shaped** transparent crystals*



Laboratory sample of pure sodium in an airless vial

Soft, shiny metal

***This glass case** holding pure sodium has no air in it, to prevent the metal from reacting with oxygen in air.*

Sodalite cabochon

***Polished gemstone** made of the mineral sodalite*

Salar de Uyuni, Bolivia

***The thick, white crust** covering this salt flat contains sodium chloride and other salts.*

Everyday salt contains lots of sodium. Although abundant on Earth, sodium is never found in its pure form naturally: it forms compounds with other elements. Sodium chloride, which also contains chlorine, is the most common sodium compound. It is also known as the mineral **halite**, and it is what makes seawater salty. Other sodium minerals include **sodalite**, a soft blue stone that can be shaped and polished. **Pure sodium** is soft enough to be cut with a knife. It reacts with oxygen in the air, forming a compound called sodium oxide, and bursts

Uses

Common salt

Edible salt *is made by refining the mineral halite.*

Mummy

This mummified body*, or mummy, was preserved using sodium compounds.*

Sodium fireworks

Bright yellow lights in fireworks *get their colour from burning sodium compounds.*

Indigo dye powder

Indigo dyes *– often used in blue jeans – contain sodium.*

MUMMIFICATION

Ancient Egyptians believed in life after death and so preserved the bodies of their dead. A dead body was washed and the organs removed, then crystals of sodium compounds were used to dry it out. Finally, the body was wrapped, which completed the process of mummification.



1*. Organs, such as the stomach and lungs, were removed from the dead body.*



2*. Sodium compounds were spread over the body to dry it.*



3*. The body was wrapped in cloth to mummify it.*

This tube *glows bright yellow-orange when sodium gas is electrified.*

Sodium gas lamp

Cats were sacred in ancient Egypt, so their bodies were mummified.

Bar of soap

Some soaps *contain sodium hydroxide.*

Baking soda

Odourless white powder

De-icing

Spraying salt *keeps roads free from ice and frost.*

into flames when in contact with water. Sodium compounds in **fireworks** burn with a yellow-orange colour. In ancient Egypt, crystals of sodium compounds were used to preserve dead bodies as **mummies**. Another useful compound is sodium bicarbonate, or **baking soda**, which makes dough rise by releasing bubbles of carbon dioxide. When refined, sodium chloride, or **common salt**, has several uses. It makes ice melt so it is used in salty grit added to slippery, frozen roads. This helps **de-ice** them to make them safer. It is also an important seasoning for meals.



SALT FLATS Hundreds of artificial ponds dot the hillside near the small town of Maras, high in the Andes of Peru. The ponds fill with water from a stream that runs down from the nearby mountains. In the sunshine, the water evaporates, leaving behind a thick salt crust that can be collected. The people of Maras have been gathering salt in this way for at least 500 years.

The salt forms part of rocks deep underground before it is dissolved by the stream and flows into the pools. Evaporation can also be used to collect salt from seawater or other salty water sources (known as brines). Today, however, most of the world's salt comes from underground mines containing thick layers of salt that are a result of ancient seas drying out. Over millions of years, that dry salt has become buried under dense layers of rocks. This so-called "rock salt" is sometimes unearthed using excavators. At other mines, it is washed out by piping in warm water, which dissolves the salt. The brine is then pumped up to the surface for evaporation.

19 K Potassium



State: **Solid**
Discovery: **1807**

Forms



***This mineral** is rich in potassium chloride.*

Potash

***This glass case holding pure potassium** has no air in it, preventing the metal from reacting with oxygen in air.*



Laboratory sample of pure potassium in an airless vial

Soft and shiny solid

***The yellow and green colour** comes from impurities.*



Sylvite

***This mineral** contains potassium chloride, which gives it a salty taste.*

Potassium was first found in the dust of burnt plants. It was discovered by Sir Humphry Davy when he experimented with **potash** – a mixture of substances made from the ash of burnt plants soaked in water. The name potassium comes from potash but the element's chemical symbol, K, is taken from *kalium*, a Latin word for "ash". Potassium is never found pure in nature, but is present in minerals such as **aphthitalite** and **sylvite**. Potassium is vital for the human body, helping muscles and nerves work properly. For this, we rely on

Aphthitalite

Uses

Soda water

Soda water *contains potassium compounds for added flavour.*

Potassium salt

***This salt** contains potassium chloride, which helps lower blood pressure.*

REBREATHER

A rebreather is a machine used by expert divers so they can stay underwater for long periods.



***1**. Exhaled air, containing carbon dioxide, enters the rebreather.*

***2**. Carbon dioxide flows into the chamber and reacts with a compound called potassium superoxide.*

***3**. Oxygen is produced in the chamber.*

***4**. Oxygen flows out of the chamber.*

***5**. The diver breathes in this oxygen.*

Rebreather

***This cylinder** contains a compound called potassium superoxide.*

***Potassium solutions** are used to hydrate patients.*

Saline drip

***Potassium-rich fertilizer** is easily absorbed by the soil and boosts plant growth.*

Fertilizer

Potassium-rich food

Banana
Avocado
Sweet potato

Gunpowder

***This explosive mixture** contains powdered potassium nitrate.*

Liquid soap

***This soap** contains potassium hydroxide, which is a cleaning agent.*

Toughened glass screen

***This strengthened glass sheet** contains potassium nitrate.*

potassium-rich food, such as bananas, root vegetables, and avocados, which contain potassium chloride. In tiny amounts, this compound can enhance flavours, as it does in **soda water**. It is also a healthy alternative to sodium chloride, or common salt, and an important ingredient in **saline drips** for rehydrating patients who are seriously ill. Potassium nitrate is a compound of potassium, oxygen, and nitrogen, and is found in **gunpowder** and **toughened glass screens** for mobile phones.

37 Rb Rubidium



⊖ 37 ⊕ 37 ○ 48

State: Solid
Discovery: 1861

Forms



Laboratory sample of pure rubidium in an airless vial

This glass case contains pure rubidium, *preventing it from coming into contact with air and catching fire.*



Leucite

Pale, waxy mineral

Rubidium makes up only about **1 per cent** of this mineral.



Lepidolite

This soft mineral *contains up to 3.5% rubidium.*



Pollucite

This ore *contains caesium and rubidium.*

Rubidium was named after the Latin word *rubidius*, meaning "deepest red". This refers to the red-coloured flame it produces when burned. This highly reactive element ignites on contact with air. On contact with water, it reacts vigorously, producing hydrogen gas and a lot of heat. Rubidium is not often concentrated in particular minerals, but instead is spread in small amounts through a wide range of minerals, such as **leucite** and **pollucite**. The pure metal is sourced mainly from the mineral **lepidolite**. Another mineral called rubicline has even more

Uses

RUBIDIUM-STRONTIUM DATING

About a quarter of all rubidium atoms are radioactive. Slowly over time, they break down into strontium atoms. Comparing the amounts of these elements in a rock shows when that mineral was formed. Older rocks have less rubidium and more strontium in them.


Rubidium-87 atoms (red) decay at a predictable rate.
Only small amounts of strontium-87 (blue) in the rock.
The amount of strontium-87 has increased over time.
Millions of years ago
Present day

These lenses contain rubidium, which aids night vision.

Night-vision goggles



The structure of the brain *can be seen clearly because of the use of radioactive rubidium.*

PET scan

Photomultiplier

This sensitive device *detects light by using a rubidium compound.*

Fireworks

This purple colour *comes from burning a nitrogen rubidium compound.*

Ceramic insulator

Electricity cables *are hung from these rubidium-rich insulators.*

Magnetometer

This device *from the early 20th century used rubidium to measure the strength of magnetic fields.*

rubidium in it but is very rare. Rubidium atoms are sensitive to light and can be used in photoelectric cells (devices that convert light energy into electricity) and **night-vision equipment**. This element has radioactive forms, which can be used to measure the age of rocks. When injected into a patient's body, rubidium targets tumours, which show up clearly on **PET (positron emission tomography) scans**. Rubidium is also used by light-sensitive electronics called **photomultipliers**, and in making **insulators** for high-voltage cables and some special types of glass.

55 Cs Caesium



⊖ 55 ⊕ 55 ○ 78

State: Solid
Discovery: 1860

Forms



Pollucite

The crystals of this mineral *are used in jewellery.*



Laboratory sample of pure caesium in an airless vial

Shiny, silver-gold metal

Sealed glass tube

KIRCHHOFF AND BUNSEN

Caesium was discovered in 1860 by German scientists Robert Bunsen and Gustav Kirchhoff. They burned a sample of mineral water on a burner, which split the flame's light into individual colours. One of them was a distinctive light blue, which came from caesium.

Gustav Kirchhoff (left) and Robert Bunsen (right)

Uses

Atomic clock

This highly accurate clock *is also called a caesium clock.*

Drilling fluid

High-density caesium compounds *in this fluid stop toxic gases rising to the surface.*

As the most reactive metal on Earth, caesium explodes into flames if in contact with air or water. Therefore, **pure caesium**, is stored in a sealed glass tube from which all the air has been sucked out. This element is rare, and most of it is extracted from the mineral **pollucite**. Its name means "sky blue" and refers to the colour of caesium's flame when burning. Caesium is used in **atomic clocks**, which measure time down to a billionth of a second. These clocks are so accurate that they would gain or lose no more than one second every 300 years.

87
Fr

Francium



87 87 136

State: Solid
Discovery: 1939

This mineral *was discovered in 1828 in Norway.*

MARGUERITE PEREY

The French chemist Marguerite Perey discovered francium in 1939 while studying the way a pure sample of another radioactive metal – actinium – decayed. She found that actinium broke down to form thorium and a previously unknown element. She named this element francium after her home country.

The dark crust *is a uranium mineral that holds tiny amounts of francium.*

Earth's rocks have **one** francium **atom** for every million trillion uranium atoms.

Francium is the rarest natural element on Earth. Scientists think there may be just 30 g (1.1 oz) of francium in Earth's rocks. Francium atoms are created when radioactive elements break down. Francium can be extracted from radioactive ores such as **thorite** and **uraninite**, both of which contain tiny amounts of this element. Even so, to date the largest sample of the metal made contained only 300,000 atoms, and lasted only a few days. Francium has no known uses outside of research.

Barium (Ba) crystals turn black in air.



Alkaline Earth Metals

This group is a collection of reactive metals that were discovered as compounds inside common minerals in Earth's crust. Most of these minerals – known in the past as "earths" – are alkaline (alkali-producing), and this is how the group got its name. All alkaline earth metals were first purified in the 19th century.

Atomic structure
The alkaline earth metals have two electrons in their outermost electron shell. Radium (Ra) is the most radioactive member.

Physical properties
All members of this group are soft and shiny when pure. They are solid at room temperature.

Chemical properties
These metals are similar to the alkali metals, but not as reactive. Except for beryllium (Be), all alkaline earth metals react with hot water or steam.

Compounds
These elements form compounds with non-metals by losing their outermost electrons. Several compounds are found in teeth and bones.

4 Be Beryllium



⊖ 4 ⊕ 4 ○ 5

State: Solid
Discovery: 1797

Forms

Chrysoberyl

This mineral *can also be brown, green, or orange.*

Aquamarine

These crystals *have this pale blue colour due to iron impurities.*

Laboratory sample of pure beryllium

Lightweight metal

Beryllium is found in more than **30 kinds of mineral**.

This widely used element gets its name from the Greek word *beryllos*, after which the mineral beryl is also named. Beryllium is the lightest of the alkaline earth metals, but it does not share many of the group's properties. For example, it does not react with water and is much harder than the other metals in its group. Two common beryllium minerals are **chrysoberyl** and beryl. Beryl has different forms, such as **aquamarine** and emerald. Beryllium is useful in many ways. For example, some military **helicopters** use windows made

Uses

Apache attack helicopter

Beryllium alloy window

Fire sprinkler

__This seal__ made of a beryllium-nickel alloy is strong enough to stop high-pressure water supply leaking through.



__These beryllium mirror segments__ will not contract in the cold of space.

James Webb Space Telescope



__This beryllium pipe__ delivers beams of protons into this device.

ATLAS, a device at the Large Hadron Collider, CERN, Switzerland

__This airbag__ is triggered by a sensor that contains beryllium.

Airbag

Brake disc

__This beryllium disc__ can withstand higher temperatures than a disc made of aluminium.

LOUIS NICOLAS VAUQUELIN



Beryllium was discovered in 1798 by the French chemist Louis Nicolas Vauquelin. He extracted the pure metal from emerald, which is a valuable green form of the mineral beryl. He had already discovered the element chromium, which is also found in emerald and gives it its green colour.

of beryllium-rich glass to shield optical sensors to aid pilots flying at night or through fog. Objects made of this metal keep their shape well and hardly expand or contract if the temperature changes. This makes beryllium useful in valves for **fire sprinklers** and car sensors that trigger **airbags**. NASA's **James Webb Space Telescope** will use a large beryllium mirror that is light and strong. Beryllium is also used to make **brake discs** for racing cars. Alloys of beryllium and copper are used in springs as well.

12
Mg

Magnesium



⊖ 12 ⊕ 12 ○ 12

State: Solid
Discovery: 1755

Forms



This green, magnesium-rich mineral *forms deep underground.*

Serpentine



Feather-like appearance

Tremolite

Magnesium has **22 known isotopes**.



Shiny, grey crystallized form

Laboratory sample of pure magnesium



Dolomite

This ore *is a natural form of magnesium carbonate.*

Magnesium was named after Magnesia in Greece. This element largely exists deep inside Earth's mantle, but it can also be found in seawater and many minerals in our planet's crust, including **serpentine**. Another mineral, **dolomite**, is also a source of **pure magnesium**.

Magnesium has many important applications. Alloys of magnesium are not only strong, but also lightweight, so are used in a range of objects, from **car wheels** to **cameras**. For centuries, many naturally occurring magnesium minerals have been used in traditional medicines.

Uses

Alloy wheel

Magnesium alloy *makes this wheel strong and shiny.*

MAGNESIUM IN CHLOROPHYLL

Chlorophyll is an important molecule in plants and is what makes them green. At its centre sits a magnesium atom, which helps plants convert sunlight into energy in a process called photosynthesis.



Chlorophyll molecule

Digital camera

The magnesium alloy body *of this camera is lightweight and will not rust.*

Epsom salts

Crystals containing magnesium sulfate *are added to warm water for a soothing bath.*

This powder *makes skin smooth and soft.*

Talcum powder

This indigestion medicine *is a mixture of water and magnesium carbonate.*

Milk of magnesia

White lights *from burning magnesium compounds*

Magnesium fireworks

Portland cement

This widely used cement *contains powdered magnesium oxide.*

Laptop

The magnesium alloy case *of this laptop is strong but lightweight.*

Magnesium carbonate, or **magnesia**, reacts with acid in the stomach to settle indigestion. Heating magnesia produces magnesium oxide, which is one of the ingredients in **cement**. Magnesium compounds are also used in **fireworks**, and they burn hot with a white flame. Salts composed of magnesium, called **Epsom salts**, named after the place in England where they were first mined, work as a muscle relaxant. Magnesium silicate, known as **talc**, is a soft mineral used in body powders.

20
Ca

Calcium



⊖ 20 ⊕ 20 ○ 20

State: Solid
Discovery: 1808

Forms



Large, fang-like crystals

Calcite



These column-shaped crystals *contain calcium carbonate.*

Aragonite

__Bones__ are hardened by calcium phosphate.



Snake skeleton



__This crystal__ has a shiny surface.

__This pure metal__ is soft enough to cut with a knife.

Crystals of pure calcium refined in a laboratory

The most abundant metal in the human body, calcium is also the fifth most common element on Earth. It appears in many minerals: **calcite** and **aragonite** are made of a compound of calcium and carbon called calcium carbonate. Bones in animal **skeletons** contain the compound calcium phosphate. The hard, outer layers of many other animals, such as the **shells** of sea snails, are made of calcium carbonate. Calcium is very important in our diet. We get calcium by eating **calcium-rich food**, including dairy products, green

Uses

Antacid tablets

This tablet *contains calcium carbonate, which is an alkali – a substance that balances out acids.*

Sea shell

Shells of sea snails *are hardened by calcium carbonate absorbed from sea water.*

An adult **human** contains about **1 kg (2 lb) of calcium** in the body.

Writing chalk

These chalks *contain calcium sulfate.*



Calcium-rich food



Marble statue

Marble *forms when limestone comes under high temperature and pressure.*

CALCIUM CAVES

As running water flows into caves, it deposits calcium carbonate. These deposits build up to form structures called stalactites and stalagmites.



Water with dissolved calcium carbonate flows through a crack and into the cave.

Stalactite hangs from the ceiling.

Stalagmite grows up from the ground.

Water drips onto the ground.

Over time, calcium carbonate starts to build up on the ground and ceiling.

Plaster cast

This plaster of Paris cast *hardens when dry, supporting broken bones.*



The Sphinx, Egypt

This statue *is made of limestone, a natural rock containing calcium carbonate.*

Oranges are also a good source of calcium, and most orange juices have extra calcium added to them. **Antacid tablets**, used to settle indigestion, contain calcium carbonate. This compound reacts with acid in the stomach. Calcium compounds are also common in construction materials. Plasterboard, which is used to make walls smooth, **writing chalk**, and **Plaster of Paris** are all made from the mineral gypsum. Calcium oxide is an important ingredient in cement and helps turn it into hard concrete.



FLY GEYSER The multicoloured Fly Geyser in the Black Rock Desert of Nevada, USA, is made from a mound of calcium carbonate rock. Such mounds and pools are made naturally in many other places where springs gush out warm, calcium-rich waters. The amazing colours of the rocks are caused by algae and bacteria that live in this water.



Fly Geyser is not a natural wonder. It was made by accident in 1964 when engineers were drilling a well to find a source of hot water. They did find a small reservoir of water that is heated by volcanic activity deep beneath the surface, but they chose to cap the well and look elsewhere. Eventually, the hot water broke through, creating a natural fountain, or geyser. Over the decades, the calcium deposits have slowly built up. The central mound is now 1.5 m (5 ft) tall and nearly 4 m (13 ft) wide. The scalding water that gushes out can reach a height of 1.5 m (5ft).

38
Sr

Strontium



⊖ 38 ⊕ 38 ○ 50

State: Solid
Discovery: 1790

Forms

Strontianite

Soft, brittle crystals

Celestine

***This mineral** is found in some microorganisms.*



Crystals of pure strontium refined in a laboratory

***This grey metal** turns yellow in air.*

Some paints containing strontium absorb light during the day, **glowing at night**.

Strontium was discovered in 1791 in a mineral found near the Scottish village of Strontian. The mineral burned with a bright crimson flame, and Scottish chemist Thomas Charles Hope studied it and found that it contained a new element. This mineral was called **strontianite**, and it is the main ore of strontium. **Pure strontium** was first extracted by British chemist Humphry Davy in 1808, who conducted an experiment using electricity to obtain the element from the mineral. Strontium was once used in television screens, but today

Uses

Glazed ceramic

The bowl's smooth finish *is due to strontium oxide.*

Lights in unmanned buoys *can be powered by radioactive strontium.*

Navigation buoy

Loudspeaker

Magnets inside this loudspeaker *contain strontium.*

Strontium burns *in air with a bright red colour.*

Flare

Strontium compounds in some toothpastes *provide relief from pain.*

Toothpaste for sensitive teeth

GENERATING ELECTRICITY

A radioactive form of strontium, called an isotope, can be used to produce electricity. A radioisotopic thermoelectrical generator (RTG) converts heat from the element into electricity for use in spacecraft.



Radiator fin prevents the RTG from overheating.

A thermocouple is a device that converts heat from the radioactive metal into electricity.

Inside the capsule, atoms of radioactive strontium break down into those of lighter elements and produce heat.

RTG is insulated to stop radioactivity from leaking out.

Unmanned radar stations *run on electricity produced using a form of strontium called strontium-90.*

Weather radar station

there are fewer uses for it. Strontium oxide in pottery and **ceramic** glazes creates distinctive colours, while strontium carbonate produces a red colour in **flares** and fireworks. Magnets that contain iron oxide can be made stronger by adding strontium to them. These strong magnets are used in **loudspeakers** and microwave ovens. Strontium chloride is added to some kinds of **toothpaste**, while radioactive strontium is a source of electricity for **radar stations** in remote places where there are no power lines or fuel supplies.

56 Ba Barium



● 56 ⊕ 56 ○ 81

State: Solid
Discovery: 1808

Forms

Farmers used witherite as **rat poison** until the 18th century.

Witherite

***This mineral** is used to make ceramic glazes.*

***This soft metal** has a light, golden shine.*

***A grey layer of tarnish** forms when the metal comes into contact with air.*

Desert rose

***Petal-like shapes** form in the desert when sand mixes with barite or with gypsum.*



Benitoite

***These glassy, blue crystals** contain barium and titanium.*

Barium is named after the Greek word *barys*, which means "heavy", because barium and its minerals are dense. The **pure form** of this element was first discovered in 1808 by the English chemist Humphry Davy, who extracted it from an oxide of barium. This does not exist in nature. Davy obtained it by heating the mineral **witherite**. Today, the main source of barium is barite, a mineral of sulfur that forms in deserts and in rock deposits that come into contact with hot water. A rarer mineral called **benitoite** also contains barium. The element is used in **spark plugs** to make them produce more powerful sparks and is added to **glass** to increase its shine. Barium compounds are added to some types of clay used for making **pots** and vases. In oil wells, barium compounds are added to drilling fluids to increase their density. Doctors make use of barium's density by giving patients a solution of barium compound to swallow, before taking **X-rays** of their digestive system. The barium makes the soft digestive organs denser, allowing them to be seen clearly with an X-ray machine.

Laboratory sample of pure barium crystals

Uses

Spark plug


This plug *contains an alloy of barium and nickel.*

Glass-making

This glass *can be made shinier by adding barium oxide and barium carbonate.*

Jasperware pot

This pot *is made from clay that is rich in barium.*


Vacuum tube

The barium in the metallic strip *absorbs gases in the tube, maintaining a vacuum.*


X-ray scan

The intestine *is filled with a barium solution.*

BARIUM SOLUTION

Barium is used in a medical test for checking a patient's digestive tract for problems. In this test, a patient swallows a barium liquid solution, which fills the organs in the digestive tract.


1*. The barium solution is ingested.*

2*. The solution enters the stomach and begins to fill it.*

3*. Under an X-ray scan, the barium-filled stomach shows up clearly.*

88
Ra

Radium



⊖ 88 ⊕ 88 ○ 138

State: **Solid**
Discovery: **1898**

Forms



This ore *contains just 0.7 g (0.02 oz) of radium in every 1,000 kg (2,205 lb) of rock.*

In **100 years** time, only 4% of the radium atoms in this watch would have broken down.

Radium is the only radioactive member of the alkaline earth metals. It is also the rarest element in this group, and forms in small amounts when the atoms of more common metals – such as uranium and thorium – break down. Radium atoms do not survive for long, with most of them quickly decaying into radon, a radioactive noble gas. This element is highly dangerous and is rarely used today. However, in the early 20th century, radium compounds were in common use. Luminous paints, like those used to make **watch dials**

Uses

PIERRE AND MARIE CURIE

Radium was discovered in 1898 by Marie and Pierre Curie. They found that uranium ores produced more radioactivity than expected from samples of uranium. They realized another radioactive metal was present and named it radium.

12
1
2
3
4
5
ILTMORE
UMINOU

The radium paint *in this clock makes the numbers glow green-blue in the dark.*

Pocket watch with a luminous dial

This vial *contains a liquid called radium chloride.*

Vials for radium treatment

RADIUM-EMANATO
GUARANTEED

This machine *from the early 20th century mixed radium into water, which was thought to make it healthier to drink.*

Radium emanator

Cosmetics

Nº 1
RADIUM
VITAE

Skin lotions *containing radium were common in the 1920s.*

Radium face powder *was once thought to be good for the skin.*

glow in the dark, were created using radium. People working with this paint often became ill, especially with cancer, because the radiation produced by radium damages DNA. Nevertheless, until the 1940s, many people thought radium's radioactivity made them stronger, not weaker. They injected themselves with **vials containing a radium compound**, believing it gave them an energy boost. They also thought that creams and **cosmetics** with radium in them made the skin healthier, even though they did exactly the opposite.

Oddly shaped piece of pure cobalt (Co).



Transition Metals

This is the largest set of elements in the periodic table. This block of metals contains useful elements, such as gold (Au), iron (Fe), and copper (Cu). Many of these metals are easy to shape. The fourth period of the block – from rutherfordium (Rf) to copernicium (Cn) – are artificial and do not occur in nature. They were created by scientists in laboratories.

Atomic structure
Most transition metals have two outer electrons, but a few, such as copper (Cu), have just one.

Physical properties
These elements are generally hard and dense metals. Mercury (Hg), the only element that is liquid at room temperature, also belongs to this group.

Chemical properties
Transition metals are not as reactive as alkali and alkaline earth metals. However, they form many varied and colourful compounds.

Compounds
Many compounds of transition metals are brightly coloured. These metals are often used in alloys, such as brass and steel.

21 Sc Scandium



⊖ 21 ⊕ 21 ○ 24

State: Solid
Discovery: 1879

Forms



Greasy texture

Gadolinite



Euxenite

These crystals contain only tiny amounts of scandium.



The silvery colour of this metal turns yellow in the air.

Laboratory sample of pure scandium

Uses

This lightweight alloy handle does not bend.

Lacrosse stick

The scandium iodide gas inside the tube glows with a bright bluish light.

Metal halide lamp

MiG-29 aircraft

Some high-speed jets have a fuselage made of scandium alloys.

A soft and lightweight metal, scandium is similar to aluminium. It is spread so thinly in Earth's rocks that it is very difficult to collect a large amount of this element. Scandium is only used for specialist applications. Its main ores are the minerals **gadolinite** and **euxenite**, which also contain small amounts of many other rare metals, such as cerium and yttrium. Scandium mixed with aluminium makes a strong alloy, which is used in lightweight equipment for sports, such as **lacrosse**, and to make high-speed jets, such as the **MiG-29**.

22
Ti

Titanium



⊖ 22 ⊕ 22 ○ 26

State: Solid
Discovery: 1791

Forms



Perovskite

This grey, cubic crystal *is made of the compound calcium titanium oxide.*



Brookite

This large, deep red crystal of brookite *contains titanium dioxide.*

These are crystals *of the mineral albite.*

This metal's shine fades to grey *when exposed to air.*

Laboratory sample of pure titanium

Uses

Body armour

The titanium plate *placed inside acts as as shield.*

Artificial hip joint

This titanium joint *can replace damaged bone in body.*

Sunscreen

The titanium dioxide *in this sunscreen blocks damaging ultraviolet (UV) radiation in sunlight.*

Drill bit

This drill bit *is hardened with a coating of titanium nitride.*

Wristwatch

This watch casing *is made of a titanium alloy.*

Roller blades

This titanium frame *is lightweight but strong.*

Named after the Titans, a race of mythic Greek gods, titanium is a silvery metal. It is as strong as steel but much lighter, and it is not corroded by water or chemicals. This strong metal also makes excellent protective shields in **body armour**. Titanium is commonly used to prepare titanium dioxide, a compound of titanium and oxygen that is used in paints and **sunscreen**. Titanium is not toxic so it can be used to make medical implants, such as artificial **hip joints**. **Wristwatches** made with titanium alloys are light and strong.

23
V

Vanadium



⊖ 23 ⊕ 23 ○ 28

State: Solid
Discovery: 1801

Forms



Vanadinite

These brittle crystals are the main source of vanadium.

Fly agaric mushroom

This mushroom contains high levels of vanadium.

Carnotite

This powdery yellow crust contains tiny amounts of vanadium.



Laboratory sample of pure vanadium crystals

Silvery surface

Uses

Spanners

Tools made with alloys of vanadium and steel are durable.

About
85% of all vanadium
is used to toughen steel.

Damascus Steel knife

This knife has been strengthened by the addition of vanadium.

Vanadium can be hammered and stretched without breaking. This hard, strong metal is easy to shape. **Vanadium** was first **purified** in 1869 by the British chemist Henry Roscoe. Today, it is commonly extracted from its ore **vanadinite**. Ancient metalworkers used tiny amounts of vanadium compounds to make a very tough substance called **Damascus Steel**. This was named after the capital city of Syria, where ironworkers made the world's sharpest swords. Vanadium is still used to toughen tools, such as **spanners** and knives.

24 Cr Chromium



⊖ 24 ⊕ 24 ○ 28

State: Solid
Discovery: 1798

Forms



Chromite

Chromite *is dark grey to brown in colour.*



Crocoite

These large red crystals *contain chromium and lead.*



Laboratory sample of pure chromium

This metal stays shiny *even when exposed to air and water.*

Uses

Stainless steel kitchenware

This grater *can resist corrosion because it contains chromium.*

Ruby

This red colour *is due to the presence of tiny amounts of chromium oxide in the crystal.*

Motorcycle

The chromium plating *protects this motorbike from rusting.*

Chromium is named after *chroma*, the Greek word for "colour". Many minerals of chromium, including **chromite** and **crocoite**, are brightly coloured. An artificial form of crocoite, known as "chrome yellow", was once used in paints, but it was banned when scientists discovered it to be poisonous. **Pure chromium** doesn't corrode easily, so it is combined with iron and carbon to produce **stainless steel**. Chromium also gives gemstones, such as **rubies**, their deep-red colour. Some **motorcycles** have chromium-plated bodywork, giving them a shiny finish.

25 **Mn** Manganese





⊖ 25 ⊕ 25 ○ 30

State: **Solid**
Discovery: **1774**

Forms



Transparent, rose-coloured crystal

Rhodochrosite

Manganese was **purified** from **pyrolusite** for the first time in 1774.

Shiny, silvery metal



Pyrolusite

This mineral *is made of manganese dioxide.*

Like magnesium, this element gets its name from the Greek region of Magnesia. There are many manganese minerals, including the colourful mineral **rhodochrosite**. The pure form of the metal is obtained mainly from the ore **pyrolusite**. **Pure manganese** is dense, hard, and brittle. This element is present in seawater as the compounds manganese hydroxide and manganese oxide, which have built up in layers over millions of years to form masses on the sea bed. The human body needs a tiny amount of manganese, which we can get

Pineapple
Oats
Mussel
Hazelnut

Manganese-rich food

Laboratory sample of pure manganese

Uses

Jefferson nickel

This US coin *from World War II was made using manganese and silver because nickel was in short supply.*

Dry cell battery

This battery *contains manganese dioxide.*



Railway tracks

These steel tracks *have manganese added to them to make them stronger.*

Unleaded petrol

This petrol *contains a manganese compound, which is less toxic than lead.*

Lascaux cave paintings, France

The black colour *comes from manganese dioxide.*

Purple glass bottle

This glass is coloured *by adding a manganese compound called permanganate.*

JOHAN GOTTLIEB GAHN

In 1774, Swedish chemist Johan Gottlieb Gahn discovered manganese by reacting manganese dioxide with charcoal – which contains carbon – under a lot of heat. The carbon took the oxygen away from the compound, leaving behind pure manganese.



from mussels, nuts, oats, and pineapples. The applications of manganese include its use in strengthening steel, which is used in making **railway tracks** and tank armour. Certain **dry cell batteries** carry a mixture containing manganese oxide. Manganese compounds are also added to **petrol** and used to clean impurities from **glass** to make it clear or to give it a purple colour. In prehistoric times, the compound manganese dioxide was crushed to make the dark colours used in **cave paintings**.

26

Fe

Iron



26 26 30

State: Solid
Discovery: c. 3500 BCE

Forms



Pyrite

Cube-shaped crystal

***This mineral** is a compound of iron and sulfur.*



Spinach leaves

***Spinach leaves** provide not only iron but other important elements, such as potassium, calcium, and manganese.*

Iron is the **most common metal** on our planet.



Iron meteorite

Solid lump of pure iron



Chunk of pure iron refined in a laboratory

***Pure iron** is a brittle metal that can shatter easily.*

Blood sample

***Blood** contains almost 70% of the iron in the human body.*

Most of the iron on our planet is locked away in Earth's hot, molten core. This element is widely found in rocks worldwide, and almost 2.5 billion tonnes of iron is purified every year. Mineral ores rich in iron include **pyrite**. Other ores, including haematite, are used to extract **pure iron** in a process called smelting. **Iron-rich meteorites** – chunks of rock from outer space that crash to Earth – are one of very few sources of naturally pure iron. The human body uses iron to make haemoglobin, a substance in blood that carries oxygen around our body (oxygen helps

Uses

Chrysler Building, New York City, USA

Stainless steel is quite resistant to rain and wind.

Nuts and bolts

This fastener is made of strong steel.

Tractor

This steel body resists rusting.

Steel wool

Thin wires of steel are used to clean hard surfaces.



Transmission towers

These tall structures are made from stiff steel girders.

Cast iron pot

This iron pot retains heat well while cooking.

Sickle

A steel blade stays sharp longer than a blade of another alloy or metal because of the iron in it.

Iron filings and magnet

These small grains of pure iron are magnetic and are attracted to the end of a magnet.

SMELTING



1. Iron ore and coal are added to the furnace.

2. Hot air is added here to raise the temperature.

3. Impurities float on the pure metal, then released.

4. Pure iron sinks to the bottom, then removed.

Pure iron is separated from its ores in a process called smelting. During this process, iron reacts with carbon in coal at a high temperature. As the mixture burns, the carbon takes the impurities out of the ore, leaving behind a layer of pure iron.

our cells produce energy for the body to work). Foods containing iron include meats and green vegetables, such as **spinach**. When pure iron comes into contact with air and water, it develops a flaky, reddish-brown coating called rust, which weakens the metal. In order to make iron tougher, tiny amounts of carbon and other metals, such as nickel and titanium, are added to it. This forms an alloy called steel, which is used to make **bolts** and strong **tractor** bodies, among other applications. Adding the element chromium to steel creates a stronger alloy called stainless steel.

STEELMAKING A stream of red-hot, liquid metal pours from a furnace at a steelmaking workshop. This is the end of a long process in which iron ore is transformed into steel, a tough alloy that is strong enough to make girders for supporting skyscrapers and bridges. The steel may even be moulded into car bodies, woven into superstrong cables for elevators, or turned into powerful magnets that can levitate maglev trains.

Steel is an alloy of iron that contains about two per cent carbon and some other elements. The carbon locks all the atoms together and prevents the metal from cracking. This makes steel harder than iron: it bends before it breaks and doesn't shatter easily. To make steel, iron ore is smelted in a blast furnace to remove its impurities, such as nitrogen, sulfur, or phosphorus. Other elements can be added to create different varieties of steel. For example, chromium in steel stops it from rusting, while manganese makes it harder. Adding silicon to steel can make the alloy more magnetic, while nickel makes it less brittle at extremely low temperatures.

27 Co Cobalt



State: Solid
Discovery: 1739

Forms



Erythrite

The distinctive purplish colour *gives it the nickname "red cobalt".*

Discs of pure cobalt refined in a laboratory

This shiny metal *is fairly hard.*

Cobaltite

These cubic crystals *contain a sulfur compound of cobalt.*

Skutterudite

This silvery mineral *smells like garlic when crushed due to the presence of arsenic.*

Medieval German miners often mistook ores of cobalt for precious metals. When they tried to purify these, the arsenic gas released made them sick. This unwanted side-effect led to the name *kobold*, which is German for "goblin", a mischievous spirit.

Pure cobalt is hard and shiny, and is added to steel and other alloys to make them stronger. Alloys containing cobalt are used in the blades of **jet engines** and in **artificial joints**, such as hip and knee joints. Cobalt is one of the few elements

Uses

Artificial hip joint

Tough and lightweight artificial joints *can be made from an alloy of cobalt and chromium.*

This part of the joint *is screwed into the hip bone.*



Permanent magnet

This magnet *can work at temperatures as high as 800°C (1,400°F).*

These blades *made of a cobalt alloy stay hard even when very hot.*

Jet engine turbine

Tiffany lamp

This blue glass *is manufactured using cobalt compounds.*

Cobalt blue paints have been in use **since 3000 BCE**.

Cobalt blue paint

This intense colour *does not fade easily over time or upon exposure to light.*

FORMING AN ISOTOPE

Cobalt-60 is an isotope, or form, of this element. It is created artificially in nuclear reactors. Because of its radioactivity, it is useful in some cancer treatments.



A neutron is fired at the cobalt-59 nucleus.

Added neutron

Cobalt-59 is a stable atom with 59 neutrons.

Cobalt-60 is a radioactive atom with 60 neutrons.



Irradiated food

This symbol *shows that this fruit has been treated with radioactive cobalt-60.*

that can be used to make a permanent magnet. Large **permanent magnets** are made from a tough alloy of cobalt, nickel, and aluminium, called alnico. A radioactive form of cobalt, called cobalt-60, is produced in nuclear reactors. This form is widely employed to **irradiate food**, a process by which food is exposed to a tiny dose of radiation to kill harmful germs. Cobalt can also produce a deep shade of blue: **cobalt blue paints** and dyes are formed by reacting aluminium with cobalt oxide.

28 Ni Nickel



⊖ 28 ⊕ 28 ○ 30

State: Solid
Discovery: 1751

Forms



***This green colour** comes from the presence of nickel.*



***This reddish mineral** is made of iron and nickel sulfide.*



***This nickel ore** also contains arsenic.*



***These silvery white metal pellets** have a yellowish tinge.*

Nickel is named after Old Nick, a demonic spirit from Christian lore that was believed to live underground. In the 18th century, German miners mistook a poisonous nickel mineral, now known as **nickeline**, for a copper ore. When this mineral failed to yield copper, they named it *Kupfernickel*, meaning “Old Nick’s copper”. Nickel is also found in other ores, such as **garnierite** and **pentlandite**. This element is one of the most useful metals, with a number of applications. Because **pure nickel** does not rust, it is used to coat objects to make

Uses

Nickel goblet drum

This nickel-plated *instrument has a shiny finish.*

Ship propeller

Nickel-copper alloy plating *makes propellers strong and durable.*

Nickel-plated dagger



Rust-resistant handle

Nickel-based coin

The US five cent coin *is made of an alloy of 75% copper and 25% nickel.*

This **coin** from the **USA**, made of a nickel-copper alloy, is called a **nickel**.

Electric guitar

These nickel-plated guitar strings *help create a clear tone.*

Nickel cutlery



This silver-coated fork *is made of an alloy of nickel, copper, and zinc.*

Toaster

Nickel alloy wires *heat up to make toast.*

PERMANENT MAGNETS

A temporary magnet works when it is put in a magnetic field, but a permanent magnet retains its charge even when it is taken out of that field. Nickel is one of only a few elements that can be used to make permanent magnets.



1. *Atoms in a piece of nickel metal are arranged randomly.*



2. *When a magnetic field is applied, the atoms align in one direction.*



3. *The atoms then stay aligned and produce a magnetic field of their own, even after the external field is removed.*

them look like silver – a trick still used to make inexpensive ornamental objects. Nickel is also mixed with copper to make an alloy called cupronickel. This is used as plating on **propellers** and other metallic parts of ships, as the alloy does not corrode in seawater. The same alloy is used in most of the world's silver-coloured **coins**. Nickel is used in the strings of **electric guitars**. This element is added to chromium to make an alloy called nichrome. Wires made of this alloy conduct heat very well, so are used in **toasters**.

29 Cu Copper



Forms


Copper growth on limonite

Branchlike crystals *of copper*


Malachite

In caves, feather-like crystals *are often formed.*


Pellets of pure copper refined in a laboratory

Unique reddish orange colour


Chalcopyrite

These golden yellow crystals *contain copper sulfide.*


Bornite

Colourful tarnish *develops when the mineral reacts with air.*

Crustacean blood

Crustacean blood is blue *because it contains copper.*

Copper is a soft, bendy metal that is an excellent conductor of electricity and heat. Although it is one of the few elements found pure in nature, most of it exists in ores such as **chalcopyrite**. Other copper minerals, such as **malachite** and azurite, are brightly coloured.

Copper is the only metal that has a reddish colour in its pure form. **Pure copper** is mainly used as **wires** in electrical equipment. Copper wire wrapped around an iron core and then electrified helps create an **electromagnet**. Because they can be switched on or off, electromagnets can

Uses



Computer motherboard

Giant electromagnet

Massive crane-mounted electromagnets contain huge coils of copper wire.

Electroplated nails

Copper coating on steel *slows down corrosion.*

ELECTROPLATING

A thin layer of copper can be added to metal, usually iron, to stop it from corroding easily. This process is called electroplating.



Electrons flow from the positive to the negative electrode.

This positive electrode is made of copper and slowly dissolves in the liquid.

This solution contains dissolved copper ions.

This electrode is made of iron. Copper ions form a protective coating over the metal.



Statue of Liberty, New York City, USA

A verdigris layer *protects pure copper from additional weathering.*



Brass trumpet

The brass tube *contains air that vibrates to produce musical sounds.*

Bronze helmet

This tough alloy *does not weaken over time.*

Copper-glazed vase

A copper glaze *on the vase gives it a metallic shine.*



Copper electrical wires

Pure copper *can be stretched to form long wires.*

be magnetic as and when they are needed. They can be much more powerful than normal magnets and can lift heavy objects. Pure copper does not rust, but it reacts with air over time to form a layer of grey-green copper carbonate called verdigris. This can be seen on copper statues, such as the **Statue of Liberty**. Copper is often mixed with other metals to produce tougher alloys. Bronze, a copper-tin alloy, is more durable than pure copper and has been used since ancient times. Brass, a copper-zinc alloy, is used in musical instruments, such as **trumpets**.

COPPER WIRES Not much thicker than a human hair, these copper wires are twisted together and woven into a tight bundle. One of the main uses for these wires is to shield a thicker copper wire that transmits a signal to a television. As the signal carries pictures and sounds in the form of electrical currents, the wires wrapped around it prevent interference from other electrical sources nearby.



Copper is a very good conductor of electricity, but not the best; silver is better. However, copper is more widely used because it is much cheaper to find and purify. Each year, about 15 million tonnes of pure copper is produced, and more than half of it is used to make electrical components, such as this mesh. Today, more than a billion kilometres of copper wiring is running unseen in power supplies, buildings, and electronics. Copper is now the most common electrical metal, but it has a long history. It was the first element to be refined from ores in large amounts about 7,000 years ago in the region that is now Iraq. Today, Bingham Canyon in Utah, USA, is the world's largest copper mine.

30

Zn

Zinc



● 30 ⊕ 30 ○ 35

State: **Solid**

Discovery: **1746**

Forms



Sphalerite

This ore *is the main source of zinc.*



Smithsonite

This zinc mineral *forms rough nodules inside cracks.*



Laboratory sample of pure zinc

Hard, shiny metal

Zinc was used in India and China hundreds of years before the German chemist Andreas Marggraf identified it as a new element in the 18th century. This element is a rare transition metal that is never pure in nature, but is found in many minerals.

The mineral **sphalerite**, containing zinc sulfide, is the major source of **pure zinc**. Another principal mineral, **hemimorphite**, contains zinc and silicon. Zinc is essential in our diet. We consume it from food such as cheese and sunflower seeds. Zinc compounds have a wide



Supernova

Along with many other elements, zinc atoms *are formed inside supernovae (exploding giant stars).*

Hemimorphite

This mineral *contains zinc carbonate.*

Hemimorphite was discovered by James Smithson, the founder of the **Smithsonian** Institution.

Zincite

Zinc oxide crystals *are generally colourless.*

Uses



First-aid tape

Medical tapes *that contain zinc oxide stop wounds from getting infected with microbes.*

The zinc coating *on this steel bridge protects it from rust.*

Akashi Kaikyo Bridge, Kobe, Japan

American penny

This zinc coin *is coated with copper.*

Rubber boots

This flexible rubber *is made stronger by adding zinc oxide.*

Calamine lotion

This soothing skin lotion *contains a mixture of zinc compounds.*

GALVANIZED STEEL

Steel is protected from corrosion by coating it with zinc. Alloys of iron and zinc form in layers between the steel and pure zinc. This process is called galvanization.



range of applications. For example, a compound of zinc and oxygen called zinc oxide is used in **medical tape** and sunscreen. Zinc oxide can also be used to toughen the rubber used in **boots** and tyres. A compound of zinc and sulfur called zinc sulfide is used to make some paints that glow in the dark. When pure zinc is exposed to air, the metal reacts with oxygen to form a protective layer of an oxide. This coating can prevent objects covered in zinc, such as **bridges**, from corroding easily.

39
Y

Yttrium



⊖ 39 ⊕ 39 ○ 50

State: Solid
Discovery: 1794

Forms

This mineral *contains trace amounts of uranium, which is radioactive.*

Yttrium is **400 times more common** in Earth's crust than silver.

This rock sample *was brought to Earth by NASA's Apollo 16 mission.*

This vegetable *contains yttrium.*



This silvery element *does not corrode easily.*

This reddish-brown mineral *contains about 2% yttrium.*

The samples of rock brought back from the Moon by astronauts in NASA's Apollo missions contained higher levels of yttrium than rocks on Earth. This element is never found in pure form in nature, but small traces of it are present in many minerals, including **xenotime** and **monazite**. Yttrium was discovered in a compound in 1794 by the Finnish chemist Johan Gadolin, but it wasn't isolated until 1828. Other yttrium compounds have since been found in vegetables, including **cabbage**, and in seeds of woody plants. In

Uses

LED lamp

This bulb *contains yttrium compounds that enable it to produce a warmer, more yellow glow.*


Laser

This laser *is powered using crystals composed of yttrium and silicon, and can cut through metal.*

FRIEDRICH WÖHLER

In 1828, the German chemist Friedrich Wöhler became the first person to purify yttrium. He did so by extracting it from the compound yttrium chloride. He was also the first person to extract the metals beryllium and titanium from their ores.

Yttrium-90

This radioactive form of yttrium *is used to treat cancers in the body.*

Digital camera lens

Shock-proof lenses *are made from yttrium-infused glass to make them tough.*

Yttrium gas mantle

This fabric mantle *holds the hot flame inside.*


Yttrium superconductor

A small magnet *floats over the superconductor.*

This superconductor *produces a magnetic field that repels the magnet above it.*

NASA spacecraft use yttrium lasers to map the **surface of asteroids** in space.

LED lamps, yttrium converts blue light to other colours. Many **lasers** use an artificial mixture of yttrium and aluminium inside a silicon-rich crystal called garnet. Powerful yttrium lasers are used for treating some skin infections, as well as by dentists during tooth surgery. A radioactive form of this element has medical applications. Yttrium is added to the glass in a **camera lens** to make it tough. Yttrium compounds are also used in **superconductors** – materials that conduct electricity easily when cooled to very low temperatures.

40
Zr

Zirconium



40 40 51

State: Solid
Discovery: 1789

Forms



Zircon crystals

This dark brown colour *is caused by iron impurities.*



Bar of pure zirconium refined in a laboratory

This greyish-white pure element *is easy to shape.*

Uses

Dental crowns

These tough dental crowns *are made of a zirconium-rich ceramic.*

Ceramic knife

This hard, non-metallic blade *does not require frequent sharpening.*

Camera flash from the 1960s

This zirconium-filled bulb *produces a bright light.*

Zirconia crystal ring

This ring *contains cubic zirconia crystals.*

This element is named after the mineral zircon, which means "golden" in Persian, a reference to the golden-brown colour of its crystals. The Swedish chemist Jacob Berzelius was the first person to isolate **pure zirconium**, in 1824. Today, however, the element is mostly used in the form of the compound zirconium dioxide, or zirconia. Powdered zirconia is heated to produce a hard glass-like ceramic, which is used to create **dental crowns** and sharp **ceramic knives**. Powdered zirconia also forms sparkling **zirconia crystals** that look like diamonds.

41 **Nb** Niobium





⊖ 41 ⊕ 41 ○ 52

State: **Solid**
Discovery: **1801**

Forms



Columbite

This dark, dense ore *has a light metallic shine.*

Rods of pure niobium refined in a laboratory

This greyish pure metal *is soft.*

Columbite is named after the country of **Columbia**.

Uses

Pacemaker

The niobium case *houses a battery that regulates the beating of a human heart.*

Command Module from the Apollo 15 mission

This nozzle *made of a niobium alloy kept its shape even when very hot.*

Spectacle lenses

This pair of spectacles *has thin, powerful lenses made of a niobium compound.*

Niobium is so similar to the metal tantalum that the two were wrongly thought to be the same element for almost 40 years. The mineral **columbite** is the main source of this shiny metal. Niobium is not found naturally in its **pure form**. When extracted, it has many uses. As the element does not react adversely in the human body, it is used in implants, such as **pacemakers**. Niobium also does not expand when hot, so it is used to make parts of rockets, such as the one on the **Command Module** from NASA's Apollo 15 spacecraft that went to the Moon in 1971.

42
Mo

Molybdenum

Forms



Molybdenite

***This mineral** feels greasy to the touch.*



Chunk of pure molybdenum refined in a laboratory

***This metal's pure form** is silver-grey and has a very high melting point: 2,623°C (4,753°F).*

Uses

Lubricant

***This slippery lubricant**, which contains finely powdered molybdenite mixed with oil, protects fast-moving mechanical parts in engines.*

Chrome-Moly steel bike

***This lightweight but stiff frame** is made from a steel containing molybdenum and chromium.*

Ratchet set

***These closely fitting parts** are hard so they do not get damaged easily.*

Molybdenum gets its unusual name from the Greek word *molybdos*, which means "lead". Miners once mistook **molybdenite**, a dark mineral containing this metal, for an ore of lead. This element is much harder than lead, so it is easy to distinguish between these two elements when they are pure. Molybdenite is soft and slippery, and it is the main molybdenum ore. **Pure molybdenum** is mainly used to make alloys that are resistant to corrosion. These are lightweight so are ideal for constructing **bike frames**, but



⊖ 42 ⊕ 42 ○ 54

State: **Solid**
Discovery: **1781**

This experimental sports car *is built with a rust-resistant alloy that contains molybdenum.*

Vencer Sarthe

are hard enough for making sturdy tools, too. Molybdenum alloys are used in the latest designs of supercars, such as the **Vencer Sarthe**.

43
Tc

Technetium



⊖ 43 ⊕ 43 ○ 55

State: **Solid**
Discovery: **1937**

This pure form of the metal *is produced inside nuclear reactors.*

Foil of pure technetium produced in a reactor



This body scan *was created using the radioactive effects of technetium.*

Technetium-based imaging

This box *contains radioactive molybdenum, which breaks down into technetium.*

Generating technetium

Technetium was the first element to be produced artificially by researchers. It is named after the Greek word for artificial, *tekhnetos*. Technetium does not exist in nature: any of its atoms that once existed on Earth broke down millions of years ago. Tiny amounts of this element were discovered in the waste produced by early nuclear reactors. Technetium is the lightest radioactive element. It is used extensively in **medical imaging**. It is injected into a patient's body, where it emits radiation for a short while. Some machines use this radiation to show bones clearly.

44
Ru

Ruthenium



− 44 + 44 ○ 57

State: **Solid**
Discovery: **1844**

Forms



Pentlandite

This yellow-brown mineral *is often found deep underground.*



Pure ruthenium refined in a laboratory

These crystals *have a bright, silver colour.*

Uses



Electronic circuit board

This component *contains ruthenium dioxide.*

Toggle switch

The metal alloy in the switch *is toughened by adding ruthenium.*



SwissTech Convention Centre, Switzerland

These low-cost solar panels *are made using ruthenium.*

Ruthenium is named after *Ruthenia*, an old Latin name for Russia. This rare metal is found in the mineral **pentlandite**, and its **pure form** is commonly extracted from this ore. A compound called ruthenium dioxide is used in several components in **electronic circuits**, including resistors and microchips for computers and other digital devices. Adding a small amount of ruthenium makes softer metals, such as platinum and palladium, much tougher. Moving parts in devices such as **switches** benefit from this property.

45
Rh

Rhodium



⊖ 45 ⊕ 45 ○ 58

State: Solid
Discovery: 1803

Forms

Pure rhodium pellet refined in a laboratory

***This metal** is shiny and silvery when pure.*

Millerite

***This golden mineral** is defined by its needle-shaped crystals.*

Uses

Rhodium-plated jewellery

***The rhodium plating** prevents jewellery from losing its shine.*

Headlight reflector

***This rhodium-alloy reflector** provides a bright light.*

Rhodium-plated microscope

***Parts of this microscope** are coated with rhodium and can resist corrosion.*

Fibreglass production

***These fibreglass strands** are made by passing molten glass through rhodium-enriched trays.*

The rosy red colour of one of its compounds inspired the name rhodium. The Greek word *rhodon* means "rose-coloured". Rhodium is unreactive and does not form compounds easily. It is a rare metal. Most of the **pure form** is extracted when platinum is mined. Pure rhodium is hard and is used to toughen precious **jewellery**, mirrors, and optical devices, such as **microscopes**. It is mainly used in the production of catalytic convertors for cars. **Fibreglass**, which is often found in protective gear – like helmets – also contains rhodium.

46 Pd Palladium



⊖ 46 ⊕ 46 ○ 60

State: Solid
Discovery: 1803

Forms

The mines *in this area have a high concentration of palladium.*

Blue Ridge mines, South Africa

Palladium absorbs **hydrogen**, like a sponge soaking up water.

Pure form *can be produced by separating it from the ores of other metals, such as copper and nickel.*

Pure palladium pellet refined in a laboratory

Uses

The converter *gets hotter as more pollutants enter the exhaust.*



Catalytic converter

This device *uses palladium compounds that change colour when poisonous carbon monoxide is detected, which triggers an alarm.*

CARBON MONOXIDE ALARM
TEST/RESET
Power
Alarm

Carbon monoxide detector

This commemorative coin *is made from the palladium produced by the Stillwater Mining company in Montana, USA.*

STILLWATER PALLADIUM
2004

Palladium coin

Palladium is a rare, precious metal: it is 10 times rarer than silver and twice as rare as gold. Like these metals, palladium has a shiny surface and does not corrode easily. Palladium is found **pure** in nature, but it also has a few rare minerals, such as braggite. Of its many applications, the element's main use is in **catalytic converters**, which are devices used in vehicles to convert poisonous exhaust gases into less harmful ones. A compound called palladium chloride is used in **carbon monoxide detectors**. Because the element is

CATALYTIC CONVERTER

Many cars contain engines that are attached to catalytic convertors. These important devices convert toxic exhaust gases into less harmful pollutants. Palladium plays a key role in the process.



2. A chemical reaction occurs in the palladium mesh, which reduces harmful pollutants.

1. Polluting gases enter the converter.

3. Gases with less harmful fumes exit through the exhaust pipe.

White gold ring

***Palladium is added to gold** to remove its colour.*



Fountain pen nib

***This palladium nib** is decorated.*

Watch spring

***This tiny spring,** which keeps time in a watch, is made of palladium alloys.*



Surgical tools

***These tools** are made of palladium alloys, which keep them sharp for a long time.*



Glucometer test strip

***This test strip** contains palladium, which contributes to a reaction that measures glucose in a drop of blood.*

***This flute** contains palladium that enables it to resist corrosion.*

Orchestral flute

precious, it is used to make **commemorative coins** in some countries. Palladium is alloyed with steel to make it more resistant to corrosion. These alloys are used to make **surgical tools** and expensive musical instruments, such as some **flutes**. Palladium is often mixed with gold to form an alloy called white gold, which is used in jewellery. Some fountain pens have **nibs** decorated with palladium. The element is also used in **glucometer test strips** so that patients can check the level of glucose in their blood.

47

Ag

Silver



● 47 ⊕ 47 ○ 61

State: Solid

Discovery: c. 3000 BCE

Forms



This mineral's colour *changes to purple when it is exposed to bright light.*



These large opaque crystals *have a glistening sheen.*

1 g (0.03 oz) of silver can be drawn into a **2-km- (1.2-mile-) long** wire.



The bright surface tarnishes *after reacting with air.*



Black silver sulfide *forms twisted crystals.*

Silver gets its symbol "Ag" from its Latin name *argentum*, which means "shiny white". It is considered a precious metal because its pure form has a grey shine that does not corrode quickly, and it stays untarnished if cleaned regularly. Silver can be found pure in nature, but mostly it is mined from ores, such as **pyrargyrite** and **acanthite**. Because this element is valuable and can be moulded easily, pure silver was used historically to make **coins**. This metal is also ideal for making **bracelets** and settings for gems. Some people even use

Uses

MAKING CLOUDS

Rain is crucial to our Earth, especially for growing healthy crops. Where there are no clouds, scientists can form tiny water droplets that cling to silver iodide powder, forming artificial rain clouds.



1. *Aircraft releases silver iodide powder.*

2. *Ice and water droplets produce a cloud.*

3. *Rain falls when the water droplets in a cloud become heavy enough.*

Silver coating *is used on some circuit board parts.*

Circuit board

Silver coin

Soft silver *is easily pressed into coins.*



The polished surface *has a pale, metallic shine.*

Antique silver spoon

Silver bracelet

Pure silver *moulded and cut into varying shapes*

Edible silver foil

These thin sheets of silver *called "vark" are edible.*

SILVER
NITRATE (V)
AgNO₃

Silver nitrate

Silver nitrate *is mixed with water to clean cuts and scrapes.*

Photochromatic glasses

Glass infused with silver chloride *turns brownish when exposed to sunlight.*

Photography plate

An image forms *when silver bromide darkens quickly on exposure to light.*

flattened **silver foil** to decorate food. **Silver spoons** and forks were the only pieces of cutlery that did not create a nasty metallic flavour in the mouth in the days before the invention of stainless steel. Silver conducts electricity better than copper, and is used in some **circuit boards**. **Silver nitrate** (a compound of silver, nitrogen, and oxygen) is a mild disinfectant used in some anti-bacterial soaps. Silver forms light-sensitive compounds with chlorine (used in **sunglasses**) and bromine (used in old **photography plates**).

48 Cd Cadmium



State: Solid
Discovery: 1817

Forms

This mineral *contains a rare form of cadmium sulfide, a compound of cadmium and sulfur.*

Greenockite

This soft metal *has a bluish tinge.*

Pellet of pure cadmium refined in a laboratory

The yellow colour *of this zinc mineral is due to cadmium impurities.*

Smithsonite

Uses

Cadmium and nickel layers *create electricity in this rechargeable battery.*

Nickel-cadmium battery

This deep red pigment *contains powdered cadmium oxide.*

Red paint containing cadmium

This electronic component *used in circuits contains a compound of cadmium and sulfur.*

Light-sensitive resistor

Cadmium-covered screws *do not rust.*

Cadmium-plated screws

This research sample *is being viewed under ultraviolet (UV) light produced by a cadmium laser.*

Fluorescent microscope

Cadmium is a highly toxic metal, and is known to cause cancer. This rare element is found in the ore **greenockite**, but it is mostly obtained as a by-product of zinc extraction. **Cadmium** was discovered in 1817 from a mineral called calamine. Today, this metal is mainly used in conjunction with nickel in **rechargeable batteries**. The compound cadmium oxide was once used in preparing **red paints**, but not anymore because of its toxicity. Cadmium is also used to create lasers for use in powerful **microscopes**.

72 Hf Hafnium



⊖ 72 ⊕ 72 ○ 106

State: Solid
Discovery: 1923

Forms

Zircon crystals

Hafnium *uses up 4% of the mass of this zircon crystal.*

A zircon crystal can be up to **4 billion years** old.

Laboratory sample of pure hafnium

This element's pure form *is resistant to corrosion in air.*

Uses

Metal cutter

Sections of this cutter *are made of hafnium.*



Microchip

Small electronic components *in this microchip contain hafnium.*

Hafnium is named after *Hafnia*, the Latin word for the city of Copenhagen in Denmark. It took a long time to distinguish hafnium from zirconium because the two elements are present together in crystals of the mineral **zircon** and their atoms are similar sizes. Hafnium is used in powerful **cutters** that pierce metallic objects with a hot stream of sparks. It is also used to make ultra-small electronics – only a few millionths of a millimetre wide – in **microchips**.

73
Ta

Tantalum



⊖ 73 ⊕ 73 ○ 108

State: Solid
Discovery: 1802

Forms

Tantalite

The mineral *has a dark, waxy surface.*

These yellow crystals *contain the mineral stibiotantalite.*



The pure metal *barely reacts with air, so stays shiny.*

Rods of pure tantalum refined in a laboratory

Uses

Artificial joint

The tantalum shell *of this hip implant is lightweight and flexible.*

Tantalum capacitors *are used to store a lot of electric charge in small circuits, such as the ones inside mobile phones.*

Electronic capacitor

Metallic watch

The case and strap of this watch *are made of an alloy of tantalum, gold, and copper.*

Tantalum is a hard metal named after Tantalus, a man from Greek mythology who was punished by the gods. It is extracted from a rare mineral called **tantalite**. This tough metal is not harmful to the human body, so it is used to make **artificial joints** and other body implants. Tantalum powder is used in **capacitors** – devices used in electronic circuits to store electricity. This strong metal toughens **watches** made of softer, precious metals. Tantalum is also used to create strong turbine blades that do not corrode.

74
W

Tungsten



⊖ 74 ⊕ 74 ○ 110

State: Solid
Discovery: 1783

Forms

*This dark, metallic **mineral** contains tungsten and iron.*

Ferberite

***This mineral** is the main source of pure tungsten.*

Wolframite

***Pure tungsten** is a hard, grey metal.*

Cylinder of pure tungsten refined in a laboratory

Uses

Drill bit

***This drill bit** has a coating of tungsten carbide, which protects it from damage.*

Tungsten pigments were in use in Chinese porcelain 350 years ago.



Light bulb

***Tungsten filaments** are becoming less popular as they are not energy-efficient.*

Fishing sinker

***A tungsten sinker** is preferred to a lead one because it is not poisonous.*

Tungsten has the highest melting point of any metal: it turns to liquid at a searing 3,414°C (6,177.2°F). It is a very dense metal, and its name comes from the Swedish phrase for "heavy stone". This metal is usually obtained from the mineral **wolframite**. A compound called tungsten carbide is used to harden objects such as **drill bits**. Tungsten's high melting point allows it to be used in the filaments of **light bulbs**. This element is also useful in producing weights, such as **sinkers** used with fishing lures.

75 Re Rhenium



⊖ 75 ⊕ 75 ○ 111

State: Solid
Discovery: 1925

Forms

Molybdenite

This ore *contains molybdenum and small amounts of rhenium.*

Pure rhenium pellet

Pure rhenium *is denser than gold.*

Uses

X-ray tube



These tubes *contain a rhenium alloy that produces X-rays when a stream of electrons smashes into it.*

Rhenium has the **highest boiling point** of any element.

F-22 Raptor fighter plane

This plane *has jet engines containing a heat-proof rhenium alloy.*

Rhenium is very rare in nature: only one atom out of every billion in Earth's crust is a rhenium atom. Discovered in Germany in 1925, and named after the Rhine river – it was the last stable, non-radioactive element to be found. Rhenium has a very high melting point, and can stay solid at extreme temperatures. This allows alloys made of this element to be used in very hot conditions, such as those inside the tubes of **X-ray machines**, as well those in the exhaust nozzles of rockets and the jet engines of **fighter planes**.

76 Os Osmium



⊖ 76 ⊕ 76 ○ 114

State: Solid
Discovery: 1803

Forms

Osmiridium sand

This is a natural alloy *of osmium and iridium.*

Pellet of pure osmium refined in a laboratory



The pure form *is hard but shatters easily.*

Uses

Transmission electron microscope (TEM) image



Osmium oxide *is used to highlight objects inside a cell.*

Fingerprint powder in use

Black osmium oxide powder *clings to oily fingerprints.*

The needle *of this old record player is made of osmium.*

Record player

Fountain pen

The nib of this pen *moves smoothly because of its hardy osmium alloy.*

Osmium is the densest of all naturally occurring elements: 250 ml (8.5 fl oz) of this metal (in its liquid form) weighs 5.5 kg (12 lb). This rare element is found in the ore **osmiridium**. **Pure osmium** reacts with oxygen in the air to form a poisonous oxide, so the metal is used safely by combining it with other elements or alloys. A red osmium oxide stains cells so they can be seen clearly under a powerful **microscope**, while a black oxide powder allows **fingerprints** to be revealed in crime investigations. A hard osmium alloy is used in **fountain pen** nibs.

77
Ir

Iridium



Forms


Pure iridium crystals

This metal *is 22 times as dense as water.*

These rocks contain a layer of iridium-rich clay.

Badlands National Parks, South Dakota, USA

Willamette meteorite

This meteorite*, found in Oregon, USA, contains just 0.00047% iridium.*

Iridium is the rarest natural element on Earth: there is one iridium atom out of every billion atoms in Earth's rocks. This dense metal can be found in its **pure** form in nature as well as in other common ores that contain nickel and copper. Iridium is present in **meteorites** and other space rocks. A layer of iridium-rich clay is found in Earth's crust all over the world, especially in the **Badlands of South Dakota, USA**. Scientists believe this small quantity of iridium in our planet's crust was deposited by the dust from an

Uses

Chandra X-ray Observatory



This door *protects the equipment from the Sun's glare.*

This telescope *is used to study X-rays from objects in space.*

The iridium coating *on the mirror is only a few atoms thick.*



Spark plug



This spark plug *contains a tiny amount of iridium, and can resist the high temperatures created during sparking in vehicles.*

Iridium is the **second densest metal**, after osmium.

Compass



The moving parts of *some compasses are made of the alloy osmiridium.*

LUIS WALTER ALVAREZ

In 1980, the American physicist Luis Walter Alvarez and his son Walter discovered a layer of iridium-rich clay in rocks all over the world. They suggested that this was the result of a meteorite impact about 66 million years ago, which led to the extinction of the dinosaurs.

explosion 66 million years ago when a large meteorite hit our planet. The applications of this element include coating the mirror of NASA's **Chandra X-ray Observatory**, an Earth-orbiting telescope that studies X-rays from distant stars. Iridium is more durable than platinum and copper, and is therefore preferred over these metals for use in spark plugs. Iridium is also mixed with osmium to make an alloy called osmiridium, which is used in **compasses** and put in nibs for some fountain pens to make them hardy.

78 Pt Platinum



Forms

Sperrylite

This dense, shiny mineral *consisting of platinum and arsenic is the most common ore of platinum.*

Platinum melts at the high temperature of **1,768°C** (3,214°F).

Nugget of pure platinum refined in a laboratory

Large nuggets *of pure platinum are rare.*

Spanish explorers first found platinum in the mines of South America in the 1700s. They obtained a whitish substance that the locals living near there called *platina*, meaning "little silver". This precious metal has a silvery white shine. Platinum rarely reacts with other elements, even at high temperatures. This makes it difficult to extract from its ores, such as **sperrylite**. **Pure platinum** does not corrode or tarnish. It is, however, not easy to shape or mould, so use of platinum was limited to the making of simple jewellery and **watches**. By the 20th century,

Uses

Platinum resistance thermometer

This thermometer *records temperature by measuring the electric current flowing through a fine platinum wire.*



Platinum watch

Expensive watches *use the precious metal platinum.*

Platinum prints *have a wider range of shades than silver prints.*



Black and white photographic print

Jewellery *made of platinum does not lose its shine.*

Platinum ring

Dental fillings *once contained platinum and mercury.*



Dental crown

This drug *contains platinum and kills cancer cells in the body.*

Cisplatin
50 mg
50 ml

Cancer drug



This fuel cell *contains platinum, which speeds up the reaction between hydrogen and oxygen.*

Fuel cell

This stent made of platinum *is not harmful to the body and anchors a damaged blood vessel as it heals.*



Medical stent

Platinum was found in an Egyptian casket from the **7th century BCE**.

ANTONIO DE ULLOA

Although platinum had been in use in jewellery on the west coast of South America for more than 2,000 years, it was Spanish naval officer Antonio de Ulloa who made the first major study of it. In 1735, while on a South American expedition, he found grains of the metal in river sands. He brought them back to Spain to examine them.



more applications were discovered. Platinum can be used in place of silver to generate **photographic prints**, and in place of gold for making **dental fillings**. Today, platinum plays an important role in various technologies. For example, it is used in **fuel cells** – devices that generate electricity by combining hydrogen and oxygen. These cells do not need to be recharged like other batteries. Powerful **drugs for treating cancer** contain this element, while **stents** made of pure platinum help heal damaged blood vessels.

79

Au

Gold



⊖ 79 ⊕ 79 ○ 118

State: Solid

Discovery: c. 3000 BCE

Forms

Gold's chemical symbol **Au**, comes from its **latin name**, *aurum*.



Crystals of pure gold refined in a laboratory

__Pure gold__ has a dark yellow colour unlike any other metal.

__These crystals__ may be elongated, rectangular, or cubic.



Calaverite

__This mineral ore__ contains gold and tellurium.



Natural gold in quartz

__These flakes of pure gold__ are locked into quartz crystals.

People were making gold ornaments more than 6,000 years ago. This was many centuries before they learned how to purify copper, iron, and other metals. Gold is believed by many to be the first metal element to be identified. It is a dense, unreactive metal with a distinctive deep yellow colour. Gold is naturally **pure** and seldom makes compounds in nature; the compound in the mineral ore **calaverite** is an exception. **Pure gold** found in nature may form nuggets but mostly is found as tiny specks embedded in rocks. Gold miners crush up these rocks and wash out the

Uses

This very thin layer of gold *protects the astronaut from the Sun's heat.*

Astronaut's visor

This mask *was placed over the pharaoh's mummified face.*

Tutankhamun's death mask

THE HOLTERMANN NUGGET

The largest piece of natural gold was found on 19 October, 1872, near the small town of Hill End in Australia. Named after its discoverer, Bernhardt Holtermann, the piece contained moe than 90 kg (198 lb) of pure gold.



Holtermann Nugget **Child aged 10 years old**

Royal Crown Derby plate

This glass plate *contains specks of gold.*

FINE GOLD
999.9
NET WT 1000 g

Gold bars

Gold bars *stored in banks are a sign of wealth.*

Edible gold flakes

The flakes *decorating this expensive chocolate are edible.*

Gold teeth

These replacement teeth *are made of gold and mercury.*

Wat Phrathat Doi Suthep temple, Thailand

A thin layer of gold *covers this entire temple.*

Gold foil *keeps this car engine at a stable temperature.*

McLaren F1 car engine

Ancient gold jewellery

This neck ornament *is made from cast gold.*

gold dust with water or strong acids. The applications for gold include heat shields in **astronaut's visors**. This metal has always been seen as valuable and many ancient artefacts, such as the **3,300-year-old death mask** of Egyptian pharaoh Tutankhamun, were forged from it. Some of the earliest coins, found in Turkey, were made of it. Gold is used to cover important buildings, such as Thailand's **Wat Phrathat Doi Suthep** temple. This precious metal is most commonly used today in **jewellery** or decorations.



GOLDEN BUDDHA A precious statue of Buddha with one thousand eyes and one thousand hands stands in Long Son Pagoda, a temple in Nha Trang, Vietnam. The Buddha is depicted as holding a range of sacred objects, including scrolls and white lotus flowers. This statue is completely covered in a layer of pure gold, and it draws in hundreds of devotees from across the world.

Although humans have discovered many strong metals and useful elements, gold has remained one of the most valuable. Before people knew what it was, they saw glittering gold dust in river beds or dug large gold nuggets out from rocks. They found that gold has many valuable qualities: it is soft enough to hammer into any shape and can be melted down for moulding into ornaments. Best of all, its gleaming golden colour never fades away. Ancient cultures prized items made of gold: in ancient Egypt, gold was used to make coins as well as to cap the tops of pyramids. Gold is, however, so rare that if all the world's mined gold were forged into a cube, it would fit inside the penalty area of a soccer pitch.

80 **Hg** Mercury



State: **Liquid**
Discovery: **c. 1500 BCE**

Forms



Cinnabar

This bright red mineral *is the main ore of mercury used today.*



Liquid form of pure mercury

The "ribbed" effect *is due to mercury's extremely high density.*

This metal *melts at −39°C (−38°F).*

Solid mercury is soft enough to be **cut with a knife**.

Mercury is the only metal that is liquid at room temperature. Along with water, it is one of the few liquids found naturally on Earth's surface. **Pure mercury** forms around volcanoes where the heat separates it from its minerals, such as **cinnabar**. This red mineral has been used for many centuries: ancient Romans roasted cinnabar to release a liquid they called *hydrargyrum*, meaning "silver water". This was the element mercury. It was later known as quicksilver because of how fast it flowed as a stream of liquid. This metal is very poisonous:

Uses

This thermometer *contains mercury, which expands as it gets warmer and contracts as it cools.*

Mercury thermometer

Pills containing mercury *were commonly used to treat constipation and toothache.*

Mercury pills

This bulb *glows when the mercury vapour inside it is electrified.*

CFL bulb

Mercury has been in use for more than **4,000 years**.



This large, low-cost mirror *made of a pool of pure mercury is used in an astronomical telescope.*

Liquid mirror inside telescope

HOW DOES A BAROMETER WORK?


This part of the tube has no air.
Glass tube
Mercury rises when the air pressure is high and falls when it is low.
Air presses down on mercury.
Mercury in a container

A barometer is an instrument used to measure air pressure to forecast the weather. The simplest – and earliest – designs used a column of mercury inside a glass tube.

This bright red paint *is made with powdered cinnabar.*

Red paint


CHANGE
RAIN
FAIR
STORMY
VERY DRY
29
30
28
31

The needle moves *with the rise and fall of mercury.*

Mercury barometer, c. 1660

it can damage organs and nerves if inhaled or swallowed. As a result, the use of this metal is carefully monitored today. Mercury is used in some batteries, some **thermometers**, and in low-energy, **compact fluorescent light (CFL) bulbs**. Its compounds are used to prepare strong, **red paints**. Until the early 18th century, mercury was used in **pills** for treating some common ailments. It gradually fell out of use when it was found to be toxic. The first accurate **barometers** also contained this liquid, but such devices are rarely seen today.

104 Rf Rutherfordium



Ernest Rutherford



− 104 + 104 ○ 163

State: Solid
Discovery: 1964

Rutherfordium was the first superheavy element to be discovered. In this type of element, each atom has 104 or more protons in its nucleus. It is named after the New Zealand scientist **Ernest Rutherford**, who, in 1913, suggested that every atom has a nucleus, or core. Pure rutherfordium is synthesized by researchers in a laboratory.

105 Db Dubnium



Albert Ghiorso



− 105 + 105 ○ 163

State: Solid
Discovery: 1968

The US scientist Albert Ghiorso discovered **12 elements** in the 20th century.

It took scientists nearly 30 years to agree on a name for this element. Dubnium was finally named after the Russian city of Dubna, where the first atoms of this artificial, radioactive element were created, in 1968. However, a team of American scientists led by **Albert Ghiorso** also produced samples of the element at the same time. This radioactive element has 12 isotopes, or forms, with different numbers of neutrons.

106 Sg Seaborgium



State: Solid

⊖ 106 ⊕ 106 ○ 163 Discovery: 1974

Atoms of seaborgium break apart in about three minutes, so little is known about it. Scientists think it may be a metal. The element was isolated in 1974 in a machine called the **Super Heavy Ion Linear Accelerator** at the Lawrence Berkeley National Laboratory. It was named after the US scientist Glenn T Seaborg.



Glenn T Seaborg

This huge machine was used to discover **five new elements**.

***This giant tube** forms part of the Super Heavy Ion Linear Accelerator, which is a type of particle accelerator – a machine in which atoms are smashed together.*

Super Heavy Ion Linear Accelerator, Lawrence Berkeley National Laboratory, California, USA

NOBEL PRIZE IN CHEMISTRY

Glenn T Seaborg and his fellow US researcher Edwin McMillan were awarded the Nobel Prize for Chemistry in 1951 for their work in creating neptunium. This was the first element to be isolated that was heavier than uranium – the heaviest natural element.



Nobel Prize medal

107
Bh

Bohrium



⊖ 107 ⊕ 107 ○ 163

State: **Solid**
Discovery: **1981**

Niels Bohr

Bohrium is an artificial element named after the Danish scientist Niels Bohr. This was to honour his model of the structure of atoms' electron shells. Bohrium was first produced by firing chromium atoms at bismuth atoms in a particle accelerator (a machine in which atoms are smashed together). Atoms of this metal are unstable: half of any sample of bohrium atoms breaks apart in 61 seconds. As a result, it is not very well understood.

108
Hs

Hassium



⊖ 108 ⊕ 108 ○ 169

State: **Solid**
Discovery: **1984**



Peter Armbruster

__Hassium__ was produced inside this chamber.



A chamber at Centre for Heavy Ion Research, Darmstadt, Germany

Scientists think hassium is a metal, but they have not been able to produce enough of its atoms to study it in any detail. Hassium is very radioactive, and most of its atoms break apart within a few seconds. This element is named after the German state of Hesse, the location of the **Centre for Heavy Ion Research**, where hassium was first created artificially by a team led by the German physicist **Peter Armbruster**.

109
Mt

Meitnerium



Meitner Haus building,
Humboldt University, Germany



⊖ 109 ⊕ 109 ○ 169

State: Solid
Discovery: 1982

Researchers think meitnerium might be the densest of all elements. It is very unstable, and even the atoms of its most stable isotope, or form, break apart in a matter of seconds. Meitnerium is named after the Austrian physicist **Lise Meitner**, to honour her achievements in physics. Several universities, such as **Humboldt University** in Berlin, Germany, also have buildings in her name.



Lise Meitner (left) works with the German chemist Otto Hahn

110
Ds

Darmstadtium



Sigurd Hofmann



This artificial element is named after the German city of Darmstadt – the home of the Institute for Heavy Ion Research where this element was first produced. A team led by the German physicist **Sigurd Hofmann** created darmstadtium by smashing nickel atoms into lead atoms in a particle accelerator (a machine in which atoms are smashed together).

111
Rg

Roentgenium



Wilhem Röntgen



Scientists believe that this metal shares many characteristics with precious metals, such as gold and silver. However, its atoms break apart within seconds, so this has not yet been confirmed. Roentgenium was created in Darmstadt, Germany. It was named after **Wilhelm Röntgen**, the German scientist who discovered X-rays in 1895.

112
Cn

Copernicium



⊖ 112 ⊕ 112 ○ 173

State: Solid
Discovery: 1996

***This statue** stands in front of the Polish castle in which Copernicus lived.*

Statue of Nicolaus Copernicus

Some scientists think copernicium could be the **only gaseous metal**.

This German research institute is where copernicium was discovered.*

Heavy Ion Research Centre, Germany

The atoms of this radioactive element survive only for a few minutes, before breaking down. Copernicium is created in particle accelerators by smashing together atoms of lead and zinc. Only a few atoms of this artificial element have ever been produced. Copernicium is named after **Nicolaus Copernicus**, the Polish astronomer who theorized that our planet orbits the Sun.



Europium's (Eu) colour changes when left in the air.



Lanthanides

This set is named after lanthanum, the first element in this series. The name “rare earth metals” is also given to these elements because they were discovered mixed together in complex minerals in Earth’s crust, and were thought to be uncommon. However, they are actually not rare but abundant. These metals – between barium (Ba) and hafnium (Hf) – should fit between the alkaline earth metals and the transition metals, but they are normally shown underneath the main table to save on space.

Atomic structure
Atoms of every element in this group have two outer electrons. The lanthanides have large atoms, all with six electron shells.

Physical properties
The lanthanides are dense, shiny metals, which tarnish easily when exposed to air. They do not conduct electricity very well.

Chemical properties
These elements react slowly with oxygen (O) at room temperature, but the reactions speed up when heated.

Compounds
Many lanthanides form compounds with oxygen called oxides. These are often used in lasers and magnets.

57
La

Lanthanum



⊖ 57 ⊕ 57 ○ 82

State: **Solid**
Discovery: **1839**

Forms

Bastnasite

This reddish-brown mineral is also found in other colours, including white, tan, and grey.

Lanthanum carbonate is used to treat patients with **kidney disease**.



Laboratory sample of pure lanthanum

Black tarnish *forms on pure metal when it comes into contact with air.*

***This metal** burns easily when ignited.*

Uses

Fluorescent lamp

***This lamp** uses lanthanum to reduce the yellow colour in its light.*

Molten lanthanum

***In its molten state**, lanthanum is used to smooth rough diamonds.*

Camera lens

***This lens** can better focus light on an object due to the presence of lanthanum oxide in the glass.*

Although the word “lanthanum” means “to lie hidden”, it is more abundant than most metals. For example, it is three times more common than lead. This element was discovered in the mineral cerite in 1839. However, it took chemists almost another 100 years to find a way to purify the metal. Today, the mineral **bastnasite** is a source of **pure lanthanum**. The element’s applications range from its use in film studio lights and **lens-making** to refining petroleum.

58

Ce

Cerium



⊖ 58 ⊕ 58 ○ 82

State: Solid
Discovery: 1803

Cerium was the first of the lanthanides to be discovered. It is named after the dwarf planet Ceres, which was discovered two years before the element was isolated. Cerium is highly toxic when **pure**, but safer cerium compounds have some uses. The main use of cerium is in making phosphors, which are chemicals that produce lights of different colours. Phosphors are present in **flatscreen TVs** and bulbs.

Television

The inside of this screen *is coated with cerium-containing phosphors, which emit red, green, and blue light.*

Laboratory sample of pure cerium

The pure form *of the metal tarnishes on contact with air.*

Kitchen spatula

This red colour *comes from a compound called cerium sulfide.*

59

Pr

Praseodymium



⊖ 59 ⊕ 59 ○ 82

State: Solid
Discovery: 1885

Part of this element's name comes from *prasinos*, the Greek word for "green". Normally a grey colour when pure, the element reacts slowly on contact with air to form a green coating. Praseodymium compounds give a yellow colour to glass and heat-resistant **ceramics**, and provide a green colour to some **artificial jewels**. This element also boosts the strength of magnets that contain it.



This piece of the element's pure form *is often stored in mineral oil to stop it from reacting with oxygen in the air.*

Laboratory sample of pure praseodymium

Yellow ceramic pot

This yellow colour *is produced by a solution containing praseodymium.*

Green cubic zirconia

This artificial gem *gets its green colour from tiny amounts of a compound of praseodymium and oxygen.*

60 **Nd** Neodymium



State: Solid
Discovery: 1885

Pink glass

This glass *gets its colour from very tiny amounts of neodymium.*

Strong magnets made of neodymium can be used to lift thousands of times their own mass. This element was discovered in 1885 by the Austrian chemist Carl Auer von Welsbach, and it was originally used to colour glass. Small amounts of neodymium turn **glass** pinkish purple. Today, this element is also employed in lasers used in eye surgery.


Laboratory sample of pure neodymium

The pure element *turns black when it reacts with air.*

61 **Pm** Promethium



State: Solid
Discovery: 1945


This paint *glows as a result of radioactive promethium.*

Promethium-rich paint in a tin seen from above


Missile

This missile *uses radioactive promethium for electrical power.*

Promethium is the rarest lanthanide element. Any promethium that was in Earth's rocks decayed billions of years ago. Promethium is therefore produced artificially in nuclear reactors. Being very radioactive, it is used in some **missiles**, because it converts this radioactivity into electrical power. The addition of promethium also makes some **paints** glow in the dark.

62

Sm

Samarium



− 62 + 62 ○ 88

State: Solid
Discovery: 1879

This element is named after the mineral samarskite from which it was first purified. However, another lanthanide-rich mineral called monazite is the main source of this element today. Samarium is mixed with cobalt to make permanent magnets that are often used in **electric guitars**.

Guitar pickups

These pickups *(components that sense vibrations produced by guitar strings) are made of samarium-cobalt magnets.*

Laboratory sample of pure samarium

This silvery white metal *darkens on contact with air.*

63

Eu

Europium



− 63 + 63 ○ 89

State: Solid
Discovery: 1901

Europium was named after the continent of Europe. However, most of the world's supply of the element comes from the USA and China, where the mineral bastnasite is mined for the extraction of **pure europium**. A compound called europium oxide is used in euro and **British bank notes**. When placed under ultraviolet (UV) light, the compound gives off a red glow.

Laboratory sample of pure europium

The crystals of this yellowish metal *often have patches of dark oxides.*

Bank of England
I PROMISE TO PAY THE BEARER ON DEMAND THE SUM OF FIFTY POUNDS
50
Fifty

This red glow *proves this note is real.*

Section of British note under UV light

64
Gd
Gadolinium



⊖ 64 ⊕ 64 ○ 93

State: Solid
Discovery: 1880

Gadolinium, and its mineral ore gadolinite, are named after the Finnish chemist Johan Gadolin, who discovered the element. Gadolinium compounds are used to obtain clear **MRI scans**. It is also used in electronics, and to make rust-resistant steel.

This soft, silvery metal *darkens when exposed to air.*

Laboratory sample of pure gadolinium

Gadolinite

This mineral *contains tiny amounts of gadolinium.*



This image of the brain *is clear because a gadolinium compound was injected into the patient's blood.*

MRI scan of the human brain

65
Tb
Terbium



⊖ 65 ⊕ 65 ○ 94

State: Solid
Discovery: 1843

Terbium is named after the village of Ytterby in Sweden. It is a silvery metal that can be obtained from the ore monazite. This element has only a few uses. **Pure terbium** is added to other metals to make powerful magnets used in sound-producing devices, such as the **SoundBug™**. Its compounds are used to line **mercury lamps**.

SoundBug™ device

This device *uses magnets to turn any flat surface, like a window, into a loudspeaker.*

The mercury vapour in this lamp *produces ultraviolet light when electrified, and this is turned into a bright yellow glow by terbium.*

Mercury lamp

The pure metal *is soft enough to be cut with a knife.*

Laboratory sample of pure terbium

66
Dy

Dysprosium



● 66 ⊕ 66 ○ 97

State: Solid
Discovery: 1886

Dysprosium reacts more easily with air and water than most other lanthanide metals. Although it was discovered in 1886, it took until the 1950s to purify it. This metal is often used with neodymium to produce magnets that are used in **car batteries**, wind turbines, and generators.

Fergusonite

This mineral *contains tiny amounts of dysprosium.*



This pure metal *remains shiny at room temperature.*

Laboratory sample of pure dysprosium

Some hybrid car batteries *contain dysprosium.*



Hybrid car battery

67
Ho

Holmium



● 67 ⊕ 67 ○ 98

State: Solid
Discovery: 1878

The Swedish chemist Per Teodor Cleve named holmium after the Swedish city of Stockholm. Pure holmium can produce a strong magnetic field and is therefore used in magnets. Its compounds are used to make lasers, and to colour glass and artificial jewels, such as **cubic zirconia**.



Bright, silver shine

Laboratory sample of pure holmium

This artificial gemstone *is coloured red by small amounts of holmium.*

Red zirconia gemstone

68

Er

Erbium


⊖ 68
⊕ 68
○ 99
State: Solid
Discovery: 1843


Laboratory sample of pure erbium
This silvery element slowly tarnishes on contact with air.

This glass contains erbium, which protects a welder's eyes from heat and bright light.
Welding goggles

The rose pink finish of this vase is from an erbium chloride glaze.
Pink pottery

Like terbium and ytterbium, erbium is also named after the Swedish village of Ytterby, near which it was discovered. This element does not occur in its **pure form** in nature, but it can be obtained from the mineral monazite. Many erbium compounds are pink in colour and are used to colour **pottery** and glass.

69

Tm

Thulium


⊖ 69
⊕ 69
○ 100
State: Solid
Discovery: 1879


Laboratory sample of pure thulium
This soft metal glows blue under ultraviolet (UV) light.

This machine emits X-rays using a very small amount of thulium.
Portable X-ray machine

Thulium is the least abundant of all the lanthanide metals. It is used to create lasers that surgeons use to cut away damaged body tissue. Thulium also has a radioactive form that can produce X-rays: **portable X-ray machines** make use of this form.

70 **Yb** Ytterbium



State: **Solid**

⊖ 70 ⊕ 70 ○ 103 Discovery: **1878**

Ytterbium tends to be more reactive than other lanthanide metals. It is stored in sealed containers to stop the metal from reacting with oxygen. The **pure metal** has only a few uses. A small amount of ytterbium is used in making steel, while its compounds are used in some **lasers**.

Laser cutting



***An ytterbium laser** can cut through metals and plastics.*

Laboratory sample of pure ytterbium

***This bright, shiny metal** can be hammered into thin sheets.*



71 **Lu** Lutetium



State: **Solid**

⊖ 71 ⊕ 71 ○ 104 Discovery: **1907**

Laboratory sample of pure lutetium



***This element** is the hardest and densest lanthanide metal.*

***Some oil refineries** use lutetium to break down crude oil to make fuels, such as petrol and diesel.*

Oil refinery

Lutetium was the last of the rare earth metals to be discovered. It is also the final member of the lanthanides. In its **pure form**, lutetium is very reactive and catches fire easily. It is rare and has few uses, mainly as a substance mixed with crude **oil**.



This uranium (U) sample is waste material from a nuclear power plant.



Actinides

These metals are named after actinium (Ac), the first member of the group. Although this group is often shown as the bottom row in the periodic table, to save space, they actually sit between radium (Ra), an alkali earth metal, and Rutherfodium (Rf), a transition metal. All the elements in this group are radioactive, and the final nine members are artificially produced in laboratories.

Atomic structure
All the elements in this group have two electrons in their outer shell. Their atoms all have seven electron shells.

Physical properties
Natural actinides are dense metals with high melting points. The physical properties of most of the artificial ones are unknown.

Chemical properties
The actinides are reactive metals and are never found in pure form in nature. They react easily with air, the halogens, and sulfur (S).

Compounds
Actinides form colourful compounds with halogens. Most actinide ores also contain compounds of oxygen (O) called oxides.

89

Ac Actinium



⊖ 89 ⊕ 89 ○ 138

State: Solid
Discovery: 1899

Autunite



This radioactive mineral *glows brightly in ultraviolet light.*

Uranite

This ore *contains uranium, which breaks down into actinium.*

This device *uses radioactive actinium to measure the amount of water.*

Neutron probe

Rare in nature, actinium is a metal formed by the decay of other radioactive elements. Its atoms are unstable and break down to make the elements francium and radon. Actinium is found in tiny amounts in uranium ores, such as **uranite**, and has limited applications. Its isotopes are used in radiation therapy to treat cancer.

90

Th Thorium



⊖ 90 ⊕ 90 ○ 142

State: Solid
Discovery: 1829

The most common natural radioactive metal, thorium is used inside vacuum tubes to allow an electric current to flow. It can also undergo nuclear fission, a process in which atoms split in two and release energy. Scientists are exploring ways of making thorium-powered nuclear reactors that produce electricity.

Monazite

This durable rock *made of solidified lava contains 12% thorium.*

Thorianite

This ore *contains small crystals of thorium compounds.*



This thorium coating *creates an electric current by releasing electrons.*

Vacuum tube

91 Pa Protactinium



State: Solid
Discovery: 1913

This vibrant green radioactive mineral *contains tiny amounts of protactinium.*
This brittle, shiny ore *feels waxy.*

Torbernite


This bottle *contains a protactinium sample.*
A Geiger counter *measures the sample's radioactivity.*

Protactinium research

The name protactinium means "before actinium". This is because a uranium atom decays to form a protactinium atom, which then quickly breaks down into an actinium atom. Small quantities of protactinium are found in ancient sands and mud. Geologists use Geiger counters to carry out **research** to calculate how old the sands are.

These used nuclear fuel rods *contain protactinium.*

Nuclear waste

92 U Uranium



⊖ 92 ⊕ 92 ○ 146 State: Solid Discovery: 1789

Named after the planet Uranus, uranium was the first known radioactive element. In the early 20th century, some manufacturers used uranium in **glass bowl** glazes, only to realize later that it was a harmful metal. An unstable form, called uranium-235, is used as fuel in nuclear reactors and in atomic bombs.

Chunk of pure uranium

__This sample of pure uranium__ is waste from a nuclear plant.

These black sections *contain uranium dioxide, which is the main source of uranium.*

Uraninite

__Uranium mixed into glass__ makes this bowl glow bright green under ultraviolet (UV) lamps.

Glass bowl

93 Np Neptunium



⊖ 93 ⊕ 93 ○ 144 State: Solid Discovery: 1940

__The radioactive elements__ in this mineral decay to form neptunium.

Uraninite



__This cyclotron__, built in 1938, was used to discover neptunium.

Cyclotron at the University of California, Berkeley, USA

Sitting next to uranium in the periodic table, neptunium was named after the planet Neptune. It exists in small amounts in radioactive ores, such as aeschynite. It forms during nuclear explosions and was first identified inside a machine called a **cyclotron**. There are no known uses for neptunium.

94
Pu

Plutonium



⊖ 94 ⊕ 94 ○ 239

State: Solid
Discovery: 1940

Hardly any plutonium exists in nature: most of it has decayed into other elements over time. It was discovered during the development of nuclear bombs in World War II. Today, plutonium is used mostly as a nuclear fuel.

Uraninite

This ore *contains trace amounts of plutonium.*

NUCLEAR BATTERY CORP
COLUMBIA, MARYLAND

This plutonium battery *was used in early pacemakers.*

1970's pacemaker battery

This Martian rover *uses the heat given off by a supply of plutonium to generate electrical power.*

Curiosity Rover

95
Am

Americium



⊖ 95 ⊕ 95 ○ 148

State: Solid
Discovery: 1944

Smoke detector component

This smoke detector *contains tiny, harmless quantities of americium.*

This metallic element is not found in nature. Instead, it is produced inside nuclear reactors when uranium or plutonium atoms are bombarded with neutrons. Remarkably, americium is the most common radioactive element used in the home. Radioactivity emitted by americium atoms causes the air inside **smoke detectors** to conduct electricity. When smoke disrupts the electric current, an alarm goes off.

96
Cm

Curium



⊖ 96 ⊕ 96 ○ 151

State: Solid
Discovery: 1944

Marie Curie working in her laboratory

This lander studied the surface composition of the comet 67P.



Philae lander

Curium is a silvery, radioactive metal that glows reddish purple in the dark. This element was discovered by the US scientist Glenn T Seaborg at the University of California. It was named after **Marie Curie**, the scientist who discovered the element polonium. Several space probes, such as the **Philae comet lander**, use X-ray devices containing curium to study their environment.

97
Bk

Berkelium



⊖ 97 ⊕ 97 ○ 150

State: Solid
Discovery: 1949

University of California, Berkeley campus, USA

This element was named after the city of Berkeley – home to the University of California – where this artificial element was discovered. It was first synthesized by **Glenn T Seaborg**. Berkelium has no uses other than the creation of heavier elements, such as tennessine.

Seaborg helped develop the atom bomb, but **opposed using it** in World War II.



Glenn T Seaborg

98 Cf Californium

Water detector

This machine *uses californium to find water underground.*

This isotope, or form, of californium *produces a lot of neutrons.*

Pellets of radioactive californium



State: Solid
Discovery: 1950

Californium is named after the US state of California. This soft, silvery metal does not exist in nature and is made by smashing berkelium atoms with neutrons in a particle accelerator (a machine in which atoms are smashed together). This **radioactive element** is used in the treatment of cancer.

99 Es Einsteinium



Albert Einstein in his study

Only a **few milligrams** of einsteinium are made **every year**.



State: Solid
Discovery: 1952

Einsteinium was discovered in the chemicals left over after the first hydrogen bomb test in 1952. The huge explosion fused smaller atoms together to make larger ones, including einsteinium. This element was named after the great German-born scientist **Albert Einstein**, and was found to be a silvery, radioactive metal that glows blue in the dark. It is only used for making heavier elements, such as mendelevium.

100 Fm Fermium



⊖ 100 ⊕ 100 ○ 157

State: Solid
Discovery: 1953

This artificial element was named after the Italian scientist Enrico Fermi. He built the first nuclear reactor in 1942, starting the American effort to build nuclear weapons during World War II. Fermium was first identified in the debris of an atom bomb test in 1953. This unstable element has no known uses beyond research.



Some scientists call Enrico Fermi the “father of the **atomic age**”.

Enrico Fermi

---

101 Md Mendelevium



⊖ 101 ⊕ 101 ○ 157

State: Solid
Discovery: 1955



Dmitri Mendeleev



Mendeleev's periodic table

***Mendeleev's notes** from 1869 show his method of arranging elements in columns and rows.*

Mendelevium is named after the Russian chemist Dmitri Mendeleev, who invented the periodic table. Mendelevium is produced in very small amounts by firing parts of helium atoms at einsteinium atoms in a particle accelerator (a machine in which atoms are smashed together).

102 **No** Nobelium





⊖ 102 ⊕ 102 ○ 157

State: Solid
Discovery: 1963



Albert Ghiorso, Torbjørn Sikkeland, and John R Walton

This artificial metal is named after the Swedish chemist Alfred Nobel, who started the Nobel Prize. It was discovered in 1963 by a team of scientists working in California, USA. This team included **Albert Ghiorso**, **Torbjørn Sikkeland**, and **John R Walton**. They used a particle accelerator to fire carbon atoms at curium atoms, creating nobelium atoms, which broke apart within minutes.

---

103 **Lr** Lawrencium



⊖ 103 ⊕ 103 ○ 163



State: Solid
Discovery: 1965



An early cyclotron

Lawrencium was produced at the **Berkeley lab** set up by Ernest Lawrence.

Lawrencium is named after the US scientist Ernest Lawrence, who developed the first cyclotron particle accelerator. This is a machine in which parts of atoms are smashed together by making them spin round in circles. Lawrencium atoms were produced in a similar machine by firing boron atoms at californium atoms.

Pure gallium (Ga) becomes liquid at 29°C (84.2°F).



The Boron Group

This group contains five natural elements and one artificial element called nihonium (Nh). Although these elements are not very reactive, none of them are found in a pure form in nature. Boron (B), the first member, is a semi-metal (an element that has properties of both metals and non-metals), while the rest are metals. The second member, aluminium (Al), is the most common metal in Earth's rocks.

Atomic structure
Members of this group have three electrons in the outer shell of every atom. Some elements have unstable isotopes.

Physical properties
All elements, except boron, are shiny solids. Every member of this group is soft, except for boron (B), which is one of the hardest elements.

Chemical properties
Most of the elements don't react with water. Aluminium (Al) forms an oxide layer in water, and can react with it when this layer is corroded.

Compounds
They form compounds by losing electrons to other elements. All of them react with oxygen (O) by bonding to three oxygen atoms.

5
B

Boron



⊖ 5 ⊕ 5 ○ 6

State: **Solid**
Discovery: **1808**

Forms



Ulexite

This translucent mineral *is found in dried lakes.*



Kernite

This is a colourless form *of a compound of sodium and boron.*



Laboratory sample of pure boron

This metal *is dark and slightly shiny.*



Corn

Boron-rich corn

Boron-deficient corn *does not grow properly.*

Colemanite

Some boron compounds are among the toughest artificial substances on Earth, with only diamond being harder. This element is a very hard material and becomes even harder when made to react with carbon or nitrogen. **Pure boron** can be extracted from various minerals, including **ulexite** and **kernite**. The demand for this element was once so high that people moved to live in the extreme heat of **Death Valley, USA**, to work in boron mines there. Compounds of boron in soil are essential for plants to grow healthily. We use boron in our homes every day.

This searing desert *is one of the main places on Earth where boron is found.*

Death Valley, USA

Needle- and leaf-shaped crystals

Uses

Measuring cup
CUPS
16 OZ.
1 PINT LIQUID
12
1½
CUP
8
½
4

This tough glass *contains boron oxide.*

These white crystals *are obtained from sodium borate.*

This screen *is composed of boron-rich glass, which makes it scratch-resistant.*

THÉNARD AND GAY-LUSSAC

The salt sodium borate, also called borax, was already in use 1,000 years ago. In 1808, the Frenchmen Joseph Louis Gay-Lussac and Louis Jacques Thénard isolated pure boron by heating borax with potassium.

Louis Jacques Thénard
Born into a poor family, Thénard excelled as a scientist. He also discovered a compound called hydrogen peroxide.

Joseph Louis Gay-Lussac
This French chemist is also remembered for discovering that the pressure of a gas goes up with its temperature.

This clay *is bouncy but also firm because it contains boron.*

Modelling clay

Boron carbide is one of the **hardest** materials in use today.

The protective body of this tank *contains boron carbide, a compound of boron and carbon.*

Military tank
IIB
CHURCHILL
IIB

Tough, heat-resistant glassware, such as **measuring cups**, are strengthened with boron. **Boric acid** is a natural antiseptic and can be used to treat minor cuts and scrapes. A flexible layer of boron-based glass fibres is used to toughen thin **LCD screens** for televisions and laptops. Even some kinds of **modelling clay** and bouncy silly putty contain boron compounds. Boron is named after a crumbly white salt called borax, which is used in detergents. The element is also present in a diverse range of objects, from insecticides to armour for **military tanks**.

13
Al

Aluminium



⊖ 13 ⊕ 13 ○ 14

State: Solid
Discovery: 1825

Forms



Variscite

This slice of ***aluminium phosphate mineral*** *has a turquoise green colour.*



Alum crystal

This crystal *contains aluminium and sulfur compounds.*



Bauxite

This aluminium ore *is the world's main source of the element.*



Pellets of pure aluminium refined in a laboratory

Reflective surface

Although aluminium is the most common metal in Earth's rocks, scientists did not discover it until the early 1800s. Even then, it took a further 80 years for scientists to work out how to use the ore **bauxite** to extract large amounts of **pure aluminium**. It can also be found in other minerals, including **variscite**. Today, aluminium is often recycled because producing it anew requires 15 times more energy. The metal makes a strong, shiny **foil** when rolled flat, and is useful for storing foods. A **fire protection suit** made from

Uses

Tennis racket



This aluminium frame *makes the racket light.*

Aluminium foil

This foil *does not break even as it is bent and twisted.*

Fire protection suit

This suit *protects against temperatures up to 1,000°C (1,800°F).*

Aluminium can

This can *is produced from recycled aluminium.*

RECYCLING ALUMINIUM

Aluminium is expensive to purify, so it is often recycled instead. Drinks cans are almost 100 per cent pure aluminium and can be shredded, melted down, and made into new cans.



1. Used cans are collected for processing.

2. They are crushed into small bricks.

3. The blocks are shredded into tiny pieces.

4. The pieces are then melted into large blocks.

5. The blocks are then cast into smaller sections.

6. These are pressed into metal sheets.

7. New cans are made from these sheets.

Recycling one aluminium can saves enough energy to run a TV for three hours.

Smartwatch

The aluminium casing *protects the touchscreen.*

Parts of this dome *are made of aluminium.*

Esplanade Theatre, Singapore

Aluminium cables *are lightweight.*

Overhead cables

Boeing 737

This plane's fuselage *is built from sheets of aluminium stretched around a frame.*

this foil reflects away heat. Aluminium is the most widely used metal after iron. It is very lightweight compared to iron's alloy steel and almost as strong. A dome made from aluminium, such as the one in the **Esplanade Theatre** in Singapore, can be much larger than a steel-based one, which would collapse under its own weight. Aluminium is also a good electrical conductor and so is used in **overhead cables**. Tough aluminium alloys are used to produce parts of some aircraft, including the **Boeing 737**.

JET TURBINE The curved blades of this jet engine are shaped very precisely to catch the air, and they are also strong enough to stay stiff when working at high temperatures. There are several tough metals that fit these requirements, but most are very dense, making them too heavy for an engine powering an aeroplane into the air. That leaves only one metal for the job: aluminium.



Aluminium is what makes high-speed, long-range air travel possible. Easily moulded, it is one-quarter the weight of steel, and it never rusts. Steel is stronger, but a plane made from it would be too heavy to fly. Instead aluminium is mixed with titanium and steel to produce tough yet lightweight alloys, which are used in the engines and bodies of jet aircraft. There is almost twice as much aluminium in Earth's rock as there is iron. However, purifying aluminium takes a lot of energy. Once pure, though, it can be recycled over and over again. So, one day these engine blades might transform into a fizzy drink can.

31
Ga

Gallium



⊖ 31 ⊕ 31 ○ 39

State: **Solid**
Discovery: **1875**

Forms



Diaspore

The needle-like crystals *form on the surface.*



Cube of melting gallium

Pure gallium *has a very low melting point.*

Uses

36
38
40
42
35
37
39
41
°C

Thermometer

This medical thermometer *uses a gallium alloy instead of mercury.*



Blu-ray disc

A gallium laser *is used to read Blu-ray discs.*

Red LED lights

The red LED *gets its colour from gallium compounds.*



Opportunity rover

The solar panels *powering this rover, which is exploring Mars, contain gallium and arsenic.*

Gallium melts at just 29°C (84.2°F), which means it soon becomes liquid when held in the hand. This element is found in small amounts in ores of zinc and aluminium, such as **diaspore**. **Pure gallium** is isolated when the other elements from this ore are extracted.

Gallium has a number of uses. It is mixed with indium and tin to form a liquid alloy called galinstan, which can be used in **thermometers**. Gallium is also found in **Blu-ray lasers**, **LEDs**, and some solar panels, such as those on NASA's Mars **rovers**.

49

In

Indium





⊖ 49 ⊕ 49 ○ 66

State: Solid
Discovery: 1863

Forms

When bent, indium produces a **"tin cry"** – a sound similar to a **scream**.

Sphalerite



This zinc mineral *is the main source of indium.*

Pure indium mould cast in a laboratory

Pure indium *is soft enough to draw lines on paper.*

Uses

This touchscreen *has a grid of very thin, transparent wires made of indium tin oxide.*

Touchscreen tablet

Welder's goggles

Protective goggles *coated with indium stop the heat damaging the welder's eyes.*

Transistor

The tiny electronic switches *inside this transistor contain indium.*



This glass coated with indium oxide *is shiny but still lets light through.*

Windows in a building

Indium is named after indigo, which is the colour of the light its atoms release when electrified. Its minerals are rare, and most of the metal is obtained from lead and zinc ores, such as **sphalerite**. **Pure indium** is very soft, and the element is mostly used in compound form. For example, a compound called indium tin oxide used on a **touchscreen** allows the computer to detect when a finger makes contact with the screen. Indium is also required in microchips, and to produce **welder's goggles** and **windows** that are heat- and glare-proof.

81
Tl
Thallium



State: Solid
Discovery: 1861

Forms



The grey crust *on this aluminium mineral contains small amounts of thallium.*



This mineral *contains iron, sulfur, and tiny amounts of thallium.*



Laboratory sample of pure thallium in an airless vial

This soft and silvery metal *is kept in a sealed glass tube as it is highly toxic and reacts easily with air.*

Thallium was named after the Greek word *thallos*, which means "green shoot": it was first identified from the colours in its flame, which includes a bright green light. Thallium was discovered in 1861 by William Crookes and Claude-Auguste Lamy. Although both chemists worked separately, they found the element in the same way – as a residue while making strong acids using the mineral **pyrite**. Thallium was later found to exist in larger amounts in other minerals, including **thallium alum**. **Pure thallium** is toxic and has to be handled

Uses

Heart function scan



Blood injected with a thallium compound *shows up on a patient's heart scan.*

Spectacles

These thin lenses *contain strong, thallium-infused glass.*

Until the 1970s, thallium salts were commonly used as **ant poison**.

toxic and has to be handled with care when used. A chlorine compound of thallium is used in **scans** to study a patient's blood circulation. Thallium oxide also helps make glass stronger for use in **spectacles** and cameras.

113 Nh Nihonium



● 113 ⊕ 113 ○ 183

State: Solid
Discovery: 2004

Kozuka Morita (left), with a visiting official at the RIKEN Nuclear Research Centre, Wako, Japan

Nihonium was named after the Japanese word *nihon*, which means Japan. A metallic element, nihonium was first detected in 2003 by teams studying the artificial element moscovium, which has the atomic number of 115. They noticed that atoms of moscovium broke apart after only a few seconds into atoms of an element with an atomic number of 113. In 2004, Kozuka Morita and a team of scientists at the **RIKEN Nuclear Research Centre** in Japan isolated this element in a different way: they fused bismuth and zinc atoms together.



Glassy carbon (C) has a high resistance to rust.



The Carbon Group

This group contains one non-metal, two semi-metals, and three metals. The non-metal carbon (C) is the main element in all living things. The semi-metals – silicon (Si) and germanium (Ge) – are elements that have the properties of both metals and non-metals, and they are essential in electronics. Two of the metals – tin (Sn) and lead (Pb) – have been used by humans for centuries. Flerovium (Fl), an artificial element, has no known uses.

Atomic structure
Members of this group have four electrons in the outer shell of each atom. These atoms can bond with up to four other atoms.

Physical properties
At room temperature, all natural elements in this set are solid. Flerovium (Fl) is an artificial element, and scientists think it may be a solid.

Chemical properties
All natural elements in this group can react with hydrogen (H). Carbon (C) and silicon (Si) can react with both metals and non-metals.

Compounds
These elements react with hydrogen to form compounds called hydrides. Each element can lose up to four electrons when forming compounds.

6
C

Carbon



⊖ 6 ⊕ 6 ○ 6

State: **Solid**
Discovery: **Prehistoric**

Forms

Coal

This compressed form of sooty carbon *is formed underground.*

Glassy carbon

Glossy surface



Crude oil

Mixture *of liquid, carbon-rich compounds*

Raw diamond

This colourless crystal *forms in magma deep underground.*

Laboratory sample of graphite

The shiny, metallic surface *feels soft and slippery.*



Cut diamond

This diamond's brightness *depends on its cut, which determines how many times light entering the gem will reflect inside.*

Carbon has the largest number of compounds of any element – with more than nine million known. Carbon is the fourth most common element in the Universe. Each carbon atom can bond to four others, allowing them to form chains and rings. Pure carbon exists in three forms on Earth – **graphite**, **diamond**, and buckminsterfullerene (a structure based on 60 interlinked carbon atoms). Diamond is the hardest substance in nature. It is often used in jewellery. The blades of some **saws** are coated with diamonds, and

Uses

Diamond blade saw

This sharp blade *is coated with tiny diamonds.*

Water purifier filter

This carbon filter *absorbs harmful chemicals in water.*

Battery

This battery *has a graphite core that carries electric current.*

Carbon-fibre bicycle

LOTUS Sport
MAVIC
3G

Sturdy and lightweight frame

This wheel *is composed of carbon fibre and some other materials, which make it rigid.*

This **strong** but **light** frame is made by fusing together carbon fibres.

Pencil “lead” containing graphite, not lead

Soft graphite *leaves a mark when pressed against paper.*

Kerosene lamp

This flame *is fuelled by carbon-rich oil.*

Polythene bag

This flexible plastic material *is composed of chains of carbon and hydrogen atoms.*

HARD AND SOFT CARBON

Diamond and graphite have different properties because of the arrangement of their atoms – tetrahedrons in diamond, and sheets of hexagons in graphite.



Hard as diamond
The tetrahedron, or pyramid structure, of atoms creates a rigid shape that is equally strong in all directions.



Soft as graphite
Graphite contains layers of carbon atoms that slide over each other easily, as there are only weak forces between them.

can cut into anything. Only a diamond can cut another diamond. Graphite is much softer, which is why it is used in **pencil “lead”**. It is also used in some batteries. Coal is currently the largest source of fuel for the generation of electricity, but its fumes are also known to have harmful environmental and health effects. Crude oil, natural gas, and **coal** are hydrocarbons (compounds containing only hydrogen and carbon) that occur in nature. They can be used as fuels and as plastics for objects such as **polythene bags**.

PINK DIAMOND With a mass of only just over 3 g (0.1 oz), this jewel – known as The Sweet Josephine – is one of the largest pink diamonds ever sold. Diamonds are normally colourless forms of pure carbon, and if there is any colour, it comes from tiny amounts of another substance. For example, boron makes the gem appear blue. Strangely, pink diamonds have no impurities, and no-one knows why they are pink.

The Sweet Josephine was cut from raw diamond that is more than 1.5 billion years old. This formed 150 km (93 miles) beneath Earth's surface and was then pushed up by a volcanic eruption, before eventually being dug out at a mine in Australia. Diamonds form when carbon is squeezed and heated to more than 1,000°C (1,832°F). This process rearranges the carbon atoms into a rigid crystal that makes diamond the world's hardest substance. The process also gives diamond the ability to bend light, a property that gives these jewels their glorious sparkle. With the right cut and polish, a diamond can be made into a beautiful gem that is prized throughout the world.

14 Si Silicon



State: Solid
Discovery: 1824

Forms



Amethyst

This purple form of quartz *gets its colour from iron impurities.*

Fulgurite

This glassy mineral tube *is formed when quartz-rich sand is struck by lightning.*

Laboratory sample of pure silicon

The pure element *can shatter easily.*

Stinging nettle

Tiny hairs on these leaves *have silica tips that break off when you touch them, releasing chemicals that sting.*

Sand

Sand *is mostly tiny grains of quartz that have broken away from rocks.*

About 90 per cent of the minerals that make up Earth's rocks contain silicon, a common element in our planet's crust. Nearly all silicon minerals are compounds of silicon and oxygen, known as silicates. The most common silicate is quartz, the mineral form of silicon dioxide, or silica. It is also the most common substance in **sand**. **Amethyst** is a type of quartz. Quartz deposits are widely found in rocks such as granite and sandstone. A valuable type of silica is **opal**, which is used as a gemstone. The clays used to make pottery and **ceramics** are also silicates.

Uses

Opal ring

Opal is a jewel *containing both silicon oxide and water molecules.*


Silicon wafer

Thin slice of silicon

SILICON IN SPACE

Earth and Mars contain similar amounts of silicon. This element forms on the outer layer, or crust, of both planets. In contrast, the Moon is almost half silicon. Astronomers think this tells us that the Moon was formed from Earth's surface after an asteroid smashed into our planet about 4.4 billion years ago.



Screens of silicon-based smoke *can be used in battles.*

Smokescreen

Sunlight-powered plane

Solar panels

The engines *run on electricity produced using sunlight.*

This silicone tray *is soft, but it does not melt in the oven.*

Silicone baking mould

Ceramic vase

Ceramic *is made of a silicon-based clay that has been shaped and permanently hardened by heat.*


Silicate aerogel in an experiment

Aerogel *conducts the heat from the flame poorly, preventing it from passing to the flower.*

Silicone watch

This silicone band *is flexible and strong.*

One of the most important uses of silicon is in electronics. Thin slices called **silicon wafers** drive electronic circuits. This versatile element is also used to turn sunlight into electricity in solar panels. Artificial silica is used to create **aerogel**, a lightweight but tough substance that does not conduct heat well. It is used in fire-fighting suits, and prevents flames reaching a firefighter. Another silicon compound is silicone, which can be moulded into any shape, and is used in a wide range of products from **baking moulds** to **watches**.

32 Ge Germanium



⊖ 32 ⊕ 32 ○ 41



State: **Solid**
Discovery: **1886**

Forms

Germanite



This sulfur mineral *is rich in germanium.*

Disc of pure germanium refined in a laboratory

The pure form *is shiny like a metal, but brittle.*



Uses

Camera lens

The germanium oxide in the glass of this lens *bends surrounding light from a large area into the camera.*

Smartphone microchip



This microchip *is made of silicon and germanium.*

Germanium is found in the **atmosphere** of **Jupiter**.

Car with germanium sensor

This car contains a germanium-based sensor *that measures its distance from obstacles.*

This semi-metal is named after the country Germany. It was discovered there in 1886 by chemist Clemens A Winkler, nearly 20 years after Russian chemist Dmitri Mendeleev predicted its existence and properties. **Germanite** is a mineral rich in germanium, but this element is mainly extracted from the ores of silver, copper, and lead. One of its compounds, germanium oxide, is used in wide-angle **camera lenses**. It is also used in some **microchips** and in a number of **car sensors** that aid in navigation.

50

Sn

Tin



● 50 ⊕ 50 ○ 69

State: **Solid**

Discovery: **c. 2100BCE**

Forms



Cassiterite

***The black colour** of the crystals is due to iron impurities.*



Laboratory sample of pure tin

***This pale, silvery metal** is easily moulded.*

Uses

Watering can

***Tin plating** over steel makes the can more resistant to corrosion.*

Pewter figurine

***This shiny alloy** contains around 90% tin.*

Pipe organ

***The large pipes** of this organ are made of tin and lead.*

Tin whistle

***The tin plating** on this steel whistle prevents rusting.*

Tin was one of the first metals used by humans. As long as 5,000 years ago, tin was mixed with copper to make bronze, an alloy that was stronger than either pure metal. The ore **cassiterite** is the main source of **pure tin**. Uses for tin are many, including plating steel objects, such as **cans**, to stop them corroding. A compound called tin chloride is used for dyeing silks. This metal continues to be used in a variety of tough alloys, including **pewter**, soft solder, and bronze.

82 **Pb** Lead



⊖ 82 ⊕ 82 ○ 126 State: Solid Discovery: Ancient

Forms



Brown crocoite

This soft, crumbly mineral *is made of lead chromate.*



Anglesite

The prism-like crystals *of this mineral contain a lead-sulfur compound.*



Galena

This mineral *has a bright, silvery shine.*

Uses

Lead crystal glass mug

This crystal glass *sparkles more than regular glass because it contains lead oxide.*

Lead pipe

Rust-resistant pipe

For many years, lead and tin were thought to be different forms of **the same metal**.

The chemical symbol for lead, Pb, comes from the Latin word *plumbum*. This is where the word "plumber" comes from: in ancient Roman times, water pipes used in plumbing were made from this soft metal. Lead compounds are found in the minerals **crocoite**, **anglesite**, and **galena** – the main source of **pure lead**. Lead was used far more commonly in the past as an important ingredient in paints, hair-dyes, and insecticides. A common historical use was in **glassware**. It has limited applications today. Lead can

Pure strip of lead refined in a laboratory

This pure form of the metal has a dull grey colour.

These pale crystals on the galena are a calcium mineral.

***Flashings**, or "lead sheets", cover exposed corners on roofs to make them waterproof.*

Flashings

because it absorbs radiation. It is also used in weights for diving, car batteries, and bendy **"flashings"** for sealing roofs. Lead fell out of favour because it turned out to be poisonous.

114
Fl

Flerovium



● 114 ⊕ 114 ○ 175

State: Solid
Discovery: 1999

This machine produces flerovium by **smashing together** atoms of calcium and plutonium.

Particle accelerator at Joint Institute for Nuclear Research, Dubna, Russia



Georgy Flerov

Flerovium takes its name from the Russian scientist Georgy Flerov. He founded the **Joint Institute for Nuclear Research** in Dubna, Russia, where this element was first produced in a particle accelerator (a machine in which atoms are smashed together). Flerovium is highly radioactive and its atoms last for only a few seconds before breaking apart.



Molten bismuth (Bi) solidifies to form hopper crystals.



The Nitrogen Group

This group includes different types of natural element – non-metals, semi-metals, and dense metals – as well as moscovium (Mc), an artificial element. The group is also known as “pnictogens”. This derives from the Greek word *pnígein*, which means “to choke” and refers to the potential toxicity of nitrogen (N) in certain forms.

Atomic structure
Members of this group have atoms with five electrons in the outer shell. These atoms can form up to three bonds at the same time.

Physical properties
All the members are solids, except nitrogen (N). The density of elements increases down the group: bismuth (Bi) is 8,000 times denser than nitrogen.

Chemical properties
Phosphorus (P), which exists in two main forms, is reactive, but the others in this group are fairly stable.

Compounds
When reacting with three hydrogen (H) atoms, all members of the group form reactive gaseous compounds called hydrides.

7 N Nitrogen



State: Gas
Discovery: 1772

Forms

Pure nitrogen in a glass sphere

Pure nitrogen gas *is trapped inside this glass sphere.*

Nitrogen gas gives off a purple glow when electrified.



Saturn's largest moon *has an atmosphere containing 48% nitrogen.*

Liquid nitrogen

This clear and colourless liquid *forms when nitrogen is cooled to below –195°C (–319°F).*

This is a naturally *occurring form of sodium nitrate.*

Microscopic image of root nodule

Bacteria living inside plant roots *can take nitrogen from the air for use by the plant.*

Nitrogen surrounds us all the time because it is the transparent gas that makes up nearly three-quarters of Earth's atmosphere. Since **pure nitrogen** does not react easily, its **liquid form** can be used to freeze and preserve items such as blood and tissue samples.

Nitratine is one of the few minerals rich in nitrogen. Some useful nitrogen compounds can be made by industrial processes. A group of nitrogen compounds is used in explosives, including **TNT** and **nitroglycerine**. When ignited, they explode because the bonds

Uses

Trinitrotoluene (TNT) *does not explode below 240°C (464°F).*



TNT

This lander *used 12 hydrazine-powered thrusters to land on Mars.*



Phoenix Mars Lander

Nitroglycerine *can be used to treat heart conditions.*

Nitroglycerine spray

Motorcycles *use nitromethane to fuel their powerful engines.*

Kawasaki
HEL

Drag bike

These nitrogen-based azo dyes *are often used to colour textiles.*

Textile dye

Superstrong glues *contain small nitrogen compounds that link together.*

SUPER GLUE
NET WT. 0.11 OZ. (3g)

Super glue

NITROGEN CYCLE

Nitrogen is essential for life. The nitrogen cycle is a process that constantly recycles nitrogen between Earth's atmopshere and all living things.



__1__. Lightning turns nitrogen in the air into nitrogen compounds, which dissolve in rainwater and fall to the ground.

__2__. Bacteria in the soil and plant roots produce nitrogen compounds from pure nitrogen in the air.

__3__. Animals take in nitrogen compounds when they eat, and release it in their dung.

__4__. Fungi, such as mushrooms, break down dead plants and animals, which release their nitrogen compounds back into the soil.

__5__. Bacteria break apart nitrogen compounds in the soil, returning pure nitrogen into the air.

These fertilizers *contain compounds called ammonium nitrates that promote growth in plants.*

Nitrogen fertilizer

between nitrogen atoms detach very quickly. Nitrogen fuels, such as nitromethane, are used in **drag bikes**, providing a lot more power than carbon-and-hydrogen only fuels, such as petrol. The compound hydrazine is used in thrusters on spacecraft, such as the **Phoenix Mars Lander**.

Some nitrogen compounds are put in **dyes** and **glues**. An industrial technique called the Haber process turns nitrogen and hydrogen gas into ammonia, a liquid commonly used to make **nitrogen fertilizers**. When mixed with soil, these fertilizers boost plant growth.



DRAG RACING

Zooming along a dead straight track, these all-powerful dragsters accelerate all the way to the finish line. They contain massive engines filled with an extra-powerful fuel called nitromethane, which is often shortened to "nitro". Burning eight times faster than regular petrol used in most cars, this super fuel can push dragsters to speeds in excess of 480 km/h (300 mph).



Nitromethane contains carbon, hydrogen, and nitrogen, but it is the latter element that really gives this fuel its immense power. During the process of combustion – when oxygen is mixed with the fuel in the race car's mighty engine – nitromethane burns so violently that nitrogen escapes from the fuel and returns to its pure form. This chain of events leads to a release of energy, which propels the dragsters to breakneck speeds. Although these races are an incredible spectacle to behold, driving using nitromethane can be dangerous due to the explosive nature of nitrogen when used in this way: drag racers are taking a risk to win.

15
P

Phosphorus



State: Solid
Discovery: 1669

Forms

Phosphate mining in Nauru

Deep phosphate mines *make up 80% of this tiny Pacific island.*


Apatite

This purple colour *of the crystals is due to metal impurities.*

Red phosphorus

This is the most common form *of the pure element.*


White phosphorus

This element *remains stable in water, but catches fire on contact with air.*

Chunk of violet phosphorus

This form of phosphorus *is made in a laboratory by heating red phosphorus.*

Human skull

All bones, including those in the skull*, are hardened by calcium phosphate.*

Tuna

This fish *is rich in phosphorus.*

Phosphorus was accidently discovered by German alchemist Hennig Brand. In 1669, in his quest for the mythical Philosopher's Stone (a material some believed could turn any metal into gold), he boiled a large pot full of urine for days. This produced a mysterious glowing substance, which he called phosphorus, meaning "giver of light". Phosphorus is the first element to have a discoverer with a recorded name. It is never pure in nature, and occurs in different minerals. Phosphorus has several flammable,

Uses

This light, strong china *contains calcium phosphate.*

China tea set

LIFE'S BUILDING BLOCKS

DNA – short for deoxyribonucleic acid – is like a mini database packed with instructions telling your body how to work properly. It consists of a chain of molecules and looks like a twisted ladder called a double helix. The edges are sugar molecules linked together by units containing phosphorus.




Fibre optics

These flexible fibres *are composed of phosphate-rich glass.*

Safety match box

The striking surface on the sides of the box *contains phosphorus, which ignites the match upon contact.*

Spraying ammonium phosphate *over burning material cuts off its supply of oxygen. This extinguishes the fire.*

Fire extinguisher

Spraying crops with phosphates *kills pests, such as insects.*

Pesticides

Fertilizer

This fertilizer *contains ammonium phosphate to boost plant growth.*

solid forms, including **red**, **white**, black, and **violet**. The glow seen by Brand was caused by white phosphorus reacting with oxygen. Phosphorus is mainly found in **phosphate** minerals (in which phosphorus links to oxygen), such as **apatite**, its main ore.

Phosphates are present in **fine china**, and are an important ingredient in **fertilizers**. The strips on the sides of **safety match boxes** contain pure phosphorus. More complex phosphorus compounds used in **pesticides** are poisonous.

33
As

Arsenic





⊖ 33 ⊕ 33 ○ 42

State: **Solid**
Discovery: **c. 1250**

Forms



Orpiment

Until the 1800s, *this mineral was powdered for use in paints.*



Chinese brake fern

These leaves *absorb arsenic from soil.*

Pure arsenic refined in a laboratory

Metallic shine

Realgar

This ore *is found in hot volcanic springs.*

Uses

Bullets

This tip *is an alloy of arsenic and lead.*

Rat poison

This poisonous arsenic compound *kills rats.*

When heated, arsenic **doesn't melt**, instead it **turns into a gas**.

Car battery

The electrodes *inside this battery contain arsenic.*

Arsenic is often called the "king of poisons". Every form of arsenic – either pure or in a compound – is poisonous to animals. In fact, arsenic poisons have been used for centuries. This semi-metal is found in several minerals with striking colours, including **orpiment**. Naturally occurring **pure arsenic** has a shiny, grey colour. Arsenic compounds are used in making some **rat poisons**. The leading use of arsenic today is for strengthening lead. This is done by mixing arsenic with lead to create a tough alloy that is often used in **car batteries**.

51
Sb

Antimony



51 51 71 State: Solid Discovery: c. 1600 BCE

Forms

Jamesonite

These needle-like crystals *contain antimony, lead, and iron.*



Stibnite

This mineral *tarnishes on contact with air.*

Pure antimony crystals refined in a laboratory

This silvery semi-metal *is hard but brittle.*

Uses

Printing press metal type

These metallic letters *are used by some printing presses, and are made of an antimony-tin alloy.*

Safety matches

These matches *with antimony in the tip burn brighter than the ones without it.*

Egyptian kohl

Kohl *is a dark eyeshadow.*

Kohl makes it **easier to see** in strong sunlight.

Antimony gets its name from the Greek word *anti-monos*, meaning "not alone". This may refer to the fact that the element is never found pure in nature, but is always found combined with heavier metals, such as lead. The element's symbol, Sb, comes from *stibium*, the Latin word for kohl, a form of eye make-up. The mineral ore **stibnite** is the largest source of **pure antimony**. Its pure form is mostly used to make hard alloys, such as that in the **metal type** used by some printers. Ancient **Egyptian kohl** was made from powdered stibnite.

83

Bi

Bismuth



⊖ 83 ⊕ 83 ○ 126

State: Solid
Discovery: c. 1500

Forms

***This mineral** is the main source of pure bismuth.*

Bismuthinite

In Earth's crust, bismuth is about **twice as abundant as gold**.

Hopper crystals refined in a laboratory



***These rainbow colours** form when the metal on the surface begins to react with oxygen.*

***These bismuth crystals** were produced in a laboratory.*

Bismuth is a radioactive element but its atoms are relatively stable and last for millions of years. People have known about bismuth for centuries. The Incas of South America added it to weapons made of the alloy bronze to harden them, while ancient Egyptians used a bismuth mineral to make their cosmetics glittery. Pure bismuth forms an oxide in air that is seen as colourful crystals called **hopper crystals**. This element is very brittle and has few uses when not in a compound form. Yellow bismuth

Uses

This cold box uses a compound called bismuth telluride, which becomes cold when electrified, and keeps items cool.

Portable refrigerator

This nail polish gives a pearly effect because of bismuth compounds.

Yellow cosmetics

This medicine contains a bismuth compound that helps settle an upset stomach.

Digestive medicine

Unlike most elements, bismuth's liquid state is **heavier** than its solid.

pigments are used in paints and **cosmetics**, while several bismuth compounds are also in **medicines**. An alloy of bismuth and tin is an ingredient in fire sprinklers.

115 Mc Moscovium



− 115 + 115 ○ 174

State: Solid (predicted)
Discovery: 2004

This is one of the machines in this research centre.



Joint Institute for Nuclear Research, Dubna, Russia

Only about a hundred or so atoms of this heavy, artificial element have been made. Moscovium was first created at the **Joint Institute for Nuclear Research** in Dubna, Russia. A team of Russian scientists, led by Yuri Oganessian, created this element by smashing americium atoms with parts of calcium atoms. It is named after the Russian capital city of Moscow. This element is extremely radioactive, and its atoms break up within a fraction of a second. Scientists think that moscovium would be a dense, metallic solid but with such small samples, they can only measure how big the atoms are before they break up.



Pure tellurium (Te) can form silvery crystals.



The Oxygen Group

This group does not include any natural metals. The first two members, oxygen (O) and sulfur (S), are non-metals widespread in nature. The remaining three natural elements are semi-metals. Only the artificial member, livermorium (Lv), is thought to be a metal, but chemists don’t really know for sure.

Atomic structure
All members have six electrons in the outer shell of each atom. This electron structure makes these elements highly reactive.

Physical properties
The members of this group are solids, except oxygen (O), which is a gas at room temperature. The density of the elements increases down the group.

Chemical properties
The reactivity of these elements decreases down the group. Oxygen is always involved in the process of combustion.

Compounds
These elements can form compounds with each other. They all react with carbon (C) to form compounds, some with strong smells.

8
O

Oxygen



State: **Gas**
Discovery: **1774**

Forms



This glass sphere *traps pure oxygen, which produces a silver-blue glow when electrified.*

Streaks of light *adorn the sky as atoms of oxygen in the air are hit by a stream of particles blasting from the Sun.*

Northern lights

Plants *release oxygen in sunlight.*

Flames *are produced when oxygen reacts with fuel, such as wood.*



Each water *molecule has two atoms of hydrogen and one of oxygen.*

WHAT IS COMBUSTION?

Combustion is a chemical reaction that produces heat and light. Oxygen is essential for combustion to take place.



A beaker is placed over a candle, starving the flame of oxygen.

The flame is steady in the presence of oxygen.

The flame goes out when the oxygen supply is cut off.

Candle wax is made of a flammable carbon compound, which acts as a fuel.

Oxygen is the most common element in Earth's crust. Oxygen and its compounds make up half of all rocks and minerals on our planet. In the atmosphere, **pure oxygen** makes up around one-fifth of the air. This element is a transparent gas. Life on Earth depends on oxygen for survival. Animals breathe in air to collect the oxygen in it. Our bodies' cells then use that oxygen to break apart sugars to release energy, which powers our bodies. Another process that involves oxygen is the burning reaction called combustion, in which oxygen

Uses



This cylinder *takes in oxygen along with the fuel.*

The piston *then squeezes the mixture of oxygen and fuel.*

This piston *is pushed down when the mixture explodes.*

The up-and-down motion of the pistons *makes the wheels of a car spin.*

Internal combustion engine

Hot steel *may have impurities that are burned away using pure oxygen.*

Steelmaking



The oxygen in this cylinder *can last for up to 30 minutes.*

Scuba diver

This rocket *carries liquid oxygen that mixes with the fuel to produce hot gases, which help the rocket lift off.*

Atlas V rocket

Antifreeze

This liquid *contains an oxygen compound that prevents water from freezing in an engine.*

Oxygen is **colourless** as a gas, but looks **pale blue** as a liquid.

Medical oxygen cylinder

The oxygen in this cylinder *is given to patients in controlled amounts.*

This flammable gas-oxygen mixture *burns hot enough to melt metal.*

Welding torch



Mountaineers *have to adjust slowly to changing levels of oxygen as they climb higher.*

Mountaineer with oxygen supply

reacts with a fuel and produces **fire**. Oxygen is also used up when it reacts with other elements to form compounds called oxides. However, it is replenished by **plants** through a process called photosynthesis, which releases fresh oxygen. Car **engines** are powered by the combustion of petrol or other fuels. Oxygen is also useful in the **making of steel**. Tanks of oxygen let **mountaineers** breathe easily in environments that have low levels of this gas. Rockets, such as the **Atlas V**, carry liquid oxygen to burn fuel in the absence of air in space.

16 S Sulfur



⊖ 16 ⊕ 16 ○ 16

State: Solid
Discovery: Prehistoric

Forms



Natural sulfur

These yellow sulfur crystals *often attach to volcanic mud.*

Liquid sulfur

Hot liquid sulfur *is pumped up from an underground mine.*

This grey-blue crystal *contains a sulfur compound called strontium sulfate.*

Celestine

Laboratory sample of pure sulfur

Soft, brittle granules

Mud volcano

Hydrogen sulfide bubbles *form in volcanic mud.*

Skunk

Skunks *release a foul spray that contains three kinds of sulfur compounds.*



Onions

Cut onions *release sulfur compounds that make our eyes water.*

Known since ancient times, sulfur is one of the few non-metals that can be found pure in nature. This yellow, crystalline element is found in large amounts near volcanic craters. Another name for sulfur is "brimstone", which refers to the way its crystals burn, melting into a blood-red liquid. In some religions, brimstone is thought to be the fuel that burns in the underworld. **Pure sulfur** is extracted from underground deposits using hot water. The hot **liquid sulfur** is then pumped to the surface. This element is a common ingredient in many

Uses

Vulcanized rubber *– made by heating sulfur with natural rubber – is weatherproof.*

Vulcanized tyre

Preserved dried fruits

Some dried fruits *are preserved using powder containing a sulfur compound.*

DeadFast
GREENHOUSE
SULPHUR CANDLE
• GREENHOUSE DISINFECTANT
• TREATS A STANDARD 3m x 2m GREENHOUSE

When burned, sulfur in this candle *drives away pests.*

Sulfur candle

ACID RAIN

Sulfur dioxide gas produced by burning fuel dissolves in rain water, making a sulfur acid. This falls to the ground as acid rain.



1*. Burning coal in power stations releases sulfur dioxide.*

2*. The wind carries pollutants.*

3*. Sulfur dioxide mixes with water in clouds and forms a sulfur acid.*

4*. Acid rain corrodes buildings and harms plants.*

5*. Acid rain changes soil chemistry.*

6*. It also makes rivers and lakes acidic.*

Lead acid battery

This battery *contains strong sulfuric acid.*

Clearasil
ULTRA
Deep Pore Treatment Scrub
100%

Creams that contain sulfur compounds *can disinfect skin.*

Skin cream



This plant *emits a rotting smell to attract meat-eating insects.*

Titan arum

Penicillin pills

Some antibiotics *contain sulfur compounds that kill harmful bacteria.*

Sulfur acid rain damage

This limestone sculpture *has been weathered by acid rain.*

Acid rain **destroys forests** by removing nutrients in the soil and in the leaves.

minerals, such as **celestine**. Many sulfur compounds smell bad. For example, the rotten-egg smell of volcanic pools is due to hydrogen sulfide gas. Other examples include **skunk** spray, the gaseous substance emitted by chopped **onions**, and the odour of the **titan arum** flower. There are many uses for this non-metal. Its compounds can harden natural rubber for use in **tyres**, preserve **dried fruits**, and make strong **battery** acids. The element has anti-bacterial properties and is used in antibiotic medicine, such as **penicillin**.



DANAKIL DEPRESSION This hot spring in Africa's Danakil Depression is surrounded by a yellow crust of pure sulfur. The sunken region between Ethiopia and Eritrea in East Africa is a wild volcanic area, packed with erupting craters, arid deserts, boiling mud, and pools with unusual colours caused by the presence of sulfur and many mineral salts.



At more than 100 m (330 ft) below sea level, the Danakil Depression is one of the lowest points on Earth's surface. This area receives little or no rainfall and the weather is hot and dry, with temperatures soaring above 50°C (120°F). The scalding green water of the springs inside the depression contains pure sulfur as well as a toxic sulfur compound called sulfuric acid. As the water evaporates, sulfur deposits build up around the edges of the pools, making beautiful shapes across the vast landscape. Tourists visit to marvel at the remarkable sights at Danakil, even though the inhospitable conditions in the area give it the title of the "cruellest place on Earth".

34
Se

Selenium



⊖ 34 ⊕ 34 ○ 45

State: Solid
Discovery: 1817

Forms



Chunk of pure grey selenium refined in a laboratory

This form of the element *has a metallic sheen on its surface.*

Brazil nuts

These nuts *are the richest food source of selenium.*



Berzelianite

These dark areas *contain selenium and copper.*

Uses

Calculator

This calculator *is powered by a solar cell made of selenium and nickel.*

Anti-dandruff shampoo

A selenium compound *in this shampoo treats dandruff.*



Ceramic vase

This bright colour *comes from the red selenium in the glaze.*

Photocopier

Many office photocopiers *use selenium in powdered form.*

Selenium is named after Selene, the Greek goddess of the Moon. This element is a semi-metal and so has the properties of both metals and non-metals. Selenium has two main pure forms: **grey selenium**, which is a hard substance, and red selenium, which is a soft powder. The most common use of selenium is as an ingredient that provides colour in glass and **ceramics**. Selenium is sensitive to light, so it is used in solar cells that convert sunlight into electricity. It is also utilized in **photocopy machines**.

52

Te

Tellurium



− 52 + 52 ○ 76

State: Solid
Discovery: 1783

Forms

Melonite

This ore *is a soft but dense solid.*

Sylvanite

This metallic crust *contains tellurium, gold, and silver.*



Pure tellurium crystals refined in a laboratory

This semi-metal *can form silvery white crystals.*

Uses



Fibre optics

These glass fibres *contain tellurium.*

Red-tinted glass bottle

This deep red colour *comes from adding tellurium.*

Tellurium **protects** bronze **from corroding** easily in air.

Topaz solar farm, California, USA

The solar panels *are linked to power cells containing tellurium.*

Tellurium is one of the 10 rarest elements on this planet. It gets its name from the Latin word *tellus*, which means Earth. This element is often found as a compound with another element, such as the metal nickel, as in the case of the ore **melonite**. Tellurium is also produced as a waste product when lead and copper are refined. **Pure tellurium** can take on two forms: a shiny, metallic solid or a brown powder. This element is mainly used in the glass of **fibre optics**, which carry high volumes of information much faster than copper cables.

84 Po Polonium



− 84 + 84 ○ 125

State: Solid
Discovery: 1898

Forms

This uranium ore contains **0.0000001 per cent** polonium.

***This mineral** contains uranium atoms that break apart to form atoms of polonium.*

Uses

Anti-static brush

***This brush** is used to remove static electric charge from camera lenses and music records.*

***This bomb** can be detonated when the polonium inside it ignites.*



***This robotic lunar buggy** was kept warm on the Moon's surface by the heat produced by the polonium inside it.*

Polonium is very radioactive: 1 g (0.03 oz) of this metal quickly heats up to 500°C (932°F) because of the radiation it emits. This element was discovered by Marie and Pierre Curie in 1898. Marie named it after Poland, her homeland. It is rare in nature, and is normally produced in nuclear reactors. Despite its radioactivity, this element is used in a few ways. It can trigger the explosion of **atom bombs**. It heats and powers spacecraft, such as the Russian **Lunokhod rovers**, which landed on the Moon in the 1970s.

116

Lv

Livermorium



State: **Solid**
Discovery: **2000**



Heavy ion cyclotron,
Joint Institute of Nuclear Research, Dubna, Russia

Livermorium has been **named after** this **laboratory**.

Lawrence Livermore National Laboratory, California, USA

When livermorium atoms were first produced in 2000, they broke apart in a fraction of a second. The first successful attempt to create atoms of this element was made at the **Joint Institute of Nuclear Research** at Dubna, Russia. The team worked with material provided by the **Lawrence Livermore National Laboratory** in California, USA. This highly radioactive element was produced by firing calcium atoms at curium atoms in a particle accelerator (a machine in which atoms are smashed together).

This glass sphere contains pure iodine (I).



The Halogen Group

One of the most reactive groups in the periodic table, this set includes non-metals. The name “halogen” means “salt former”, which refers to the way that elements in this group react with metals to form salts, such as sodium chloride, widely known as common salt. Scientists don’t know much about tennessine (Ts), an artificial halogen.

Atomic structure
All members have seven electrons in the outer shell of each atom. There is space for one more electron in each outer shell.

Physical properties
Bromine (Br) is the only halogen that is liquid. Fluorine (F) and chlorine (Cl) are gases, while iodine and astatine (At) are solids.

Chemical properties
Every halogen atom receives one electron from other atoms to form a compound. Reactivity decreases down the group.

Compounds
The halogens react with hydrogen (H) to form acidic compounds. Halogen compounds are used in products such as bleach.

9
F

Fluorine



State: Gas
Discovery: 1886

Forms

***This soft mineral** is brittle, which means it breaks easily into lots of pieces.*

Cryolite

Laboratory sample

***This sealed case** contains a mixture of fluorine and helium.*

Topaz **means “fire”** in the ancient Indian language of Sanskrit.

***These cubic crystals** are green due to impurities.*

Fluorite

Topaz

***This precious gemstone** contains 20.7% fluorine.*

This highly reactive element is incredibly dangerous when pure: just a tiny amount added to the air can kill a person. A pale yellow gas, fluorine reacts with brick, glass, and steel, burning a hole straight through them. Because it is so dangerous, pure fluorine is often stored in nickel containers that can resist its attack. Minerals such as **cryolite** and **fluorite** contain this element. This gas and its less harmful compounds have a wide variety of uses. Hydrofluoric acid is a toxic liquid used to etch patterns on glass, as seen in some **glass vases**.

Uses

Etched glass vase

These patterns *form after the surface of the glass is burned by an acidic fluorine compound.*

These circuit breakers*, containing a compound of fluorine and sulfur, cut electricity supply in an emergency.*

Circuit breakers

Ceramic pot

The shiny coating *on this ceramic dish is from a fluorine-containing glaze.*

Upon injection, this fluorine-rich liquid *heals damaged tissues by carrying oxygen to them.*

Oxycyte

Fluorine-rich plastic clothing *repels water.*

Waterproof clothing

PTFE was used by NASA to make **spacesuits** because it protected against heat.

This pan *has a PTFE coating that resists heat.*

Non-stick pan



Some toothpastes *contain fluorides that harden tooth enamel.*

Toothpaste

Some glazes used to coat ceramics contain fluorine minerals. When heated, these glazes release fluorine, which hardens the ceramic underneath. Another compound called polytetrafluoroethylene (PTFE) is commonly used to make **non-stick pans**: this material is slippery and prevents food that has burned while cooking from sticking to the pan. Thin fibres made of PTFE are also used to make lightweight, **waterproof clothing**. One of the most common uses of fluorine compounds is in **toothpaste**: they toughen teeth against decay.

HENRI MOISSAN



In the early 1800s, chemists in Europe realized that minerals such as fluorite contained an unknown element. However, it took another 70 years before the French chemist Henri Moissan extracted pure fluorine following a series of dangerous experiments that even poisoned him several times.

17
Cl

Chlorine



⊖ 17 ⊕ 17 ● 18

State: Gas
Discovery: 1774

Forms



Halite

***This orange colour** is due to the presence of the mineral hematite.*

Cube-shaped crystals

Carnallite

***The intense red colour** is due to impurities.*

Red-eyed tree frog

***The skin** of this tree frog contains a chlorine compound.*



Pure chlorine in a glass sphere

***This glass sphere** traps pure chlorine so as to prevent any reactions with air.*

***Pure chlorine** is heavier than air.*

Chlorine is named after the Greek word *chlóros*, which means "pale green", a reference to the colour of this gaseous element. Chlorine is a highly reactive gas that forms a number of compounds, and does not exist pure in nature. The most common chlorine compound is sodium chloride, found in nature as the mineral **halite**. Chlorine compounds are important for the body and are used by muscles and nerves. They are also present in sweat. As it is poisonous in its pure form, chlorine gas was used as a weapon during World War I: soldiers had to wear masks for protection

Uses

Running shoes

The soles of some running shoes *contain chlorine compounds.*

Sodium chloride *is used to season meals.*

Common salt

CHLORINATION

The process of cleaning dirty water with chlorine is called chlorination. This method involves passing the water through a filter.


1*. Dirty water enters the tank.*

2*. The filter traps tiny particles of impurities.*

3*. Chlorine mixed in water kills the remaining germs.*

4*. Clean water for drinking, cooking, and washing is released.*

Chloroform

Breathing in this chlorine-infused liquid *makes people fall unconscious.*

PVC pipes

Strong water pipes *are composed of thick PVC.*

Safety goggles

This chlorine-rich plastic *is tough.*


Swimming pool

The chlorine levels in this pool *need to be regulated carefully to maintain the quality of water.*

Bleach

This bleach cleaner *contains a compound called sodium hypochlorite.*

PVC suitcase

This case *is tough but flexible.*

against this weapon. Today, chlorine is used in many ways. Its compounds are present in everything from **running shoes** to **choloroform**. It reacts with hydrogen to make hydrochloric acid, an industrial cleaner. This corrosive liquid eats away at most metals, releasing hydrogen gas. A weaker chlorine acid is used to clean water in **swimming pools**, while **bleach** and other cleaners use chlorine compounds to kill germs. One of the most widely used plastics, **polyvinyl chloride (PVC)**, contains chlorine. It is a tough plastic, used to make many rigid objects.

SPIRO
NARVAL

OCEAN CLEAN UP Chlorine is a common ingredient in cleaning products, and can be used for scrubbing everything from bathroom tiles to ocean floors. These divers are trying to remove harmful seaweed in the Mediterranean Sea using the power of chlorine. This green weed grows quickly and can potentially kill other sea plants by depriving them of their essential nutrients. Some fish are also poisoned if they eat this toxic weed.



The two divers use chlorine twice in the cleaning process. First, they cover the thick seaweed with a sheet made of PVC, a tough plastic containing chlorine. Next, they pump a compound of sodium and chlorine called sodium hypochlorite under the sheet. This powerful liquid bleach kills the unwanted seaweed. Several weeks later, the divers return to remove the PVC sheets. The invading seaweed will not regrow, and the plants on the seabed will gradually return. Although chlorine is highly reactive and can damage skin and other body parts, divers are well-protected by their rubber wetsuits.

35
Br

Bromine



⊖ 35 ⊕ 35 ○ 45

State: Liquid
Discovery: 1826

Forms



Bromine vapour

This sealed glass container *prevents bromine vapour from escaping.*

Pure bromine is *a red-brown liquid.*

Potassium bromide



Bromine is named after the Greek word for **"stench"** because of its strong smell.

Bromine is the only non-metal that is a liquid at room temperature. A thick vapour given off by this liquid is dangerous if breathed in. **Pure bromine** is never found in nature. Its compounds can easily mix in water, and are found dissolved in seawater and extremely salty lakes, such as the **Dead Sea** in the Middle East. Solid bromine salts, including **potassium bromide**, collect as the water evaporates away, leaving behind crusts of white crystals. Bromine can then be extracted from the solid salts. A common

This bromine salt *was used in the late 19th century to help patients sleep.*

The Dead Sea Coast

Crusts of bromine salts *form along the Israeli shoreline.*

Uses



Bromine chemical test kit

The colours on this test kit *show how much bromine is in the water.*

Chubb Fire
HALON
Pull out pin
Free hose
Squeeze levers
Aim at fire base

Fire extinguisher

This fire extinguisher *uses a non-flammable, bromine-rich gas to extinguish fires.*

Photograph negative

This image *was created when light reacted with silver bromide.*

Bromine was used as a **weapon** in World War I.

Fireproof suit

The fabric *used to make this suit contains bromine compounds that make it fireproof.*

ANTOINE-JÉRÔME BALARD

In 1826, French chemist Antoine-Jérôme Balard discovered bromine. He heated seawater from salt marshes, and after most of the water had evaporated, he passed chlorine gas through what was left. The remaining liquid turned orange-red: this was bromine.

use of this element is as a disinfectant to clean water. It works better than chlorine in hot tubs as chlorine escapes into the air easily from the warm water. The concentration of bromine in swimming pools can be regulated using **chemical test kits**. Bromine compounds can be used in film photography in which images are printed using chemicals on **negatives**. Today, bromine is mainly used in **fireproof material**, such as firefighter suits or furnishings, because it doesn't catch fire easily.

53
I

Iodine



53 53 74

State: Solid
Discovery: 1811

Forms

Pure iodine in a glass sphere



This sealed glass container prevents iodine from reacting with air.

Purple iodine vapour

Purple-black solid iodine

Solid iodine **does not melt** when heated, but turns into a vapour.

Crab



This crab absorbs iodine from seawater.

Uses

Printing ink

***These coloured inks** are made using iodine compounds.*

Polarizing sunglasses

***These lenses** contain iodine, which filters out bright, reflected light.*

Candied cherries

***The bright red colour** of these cherries is due to an iodine dye.*

Betadine

Betadine® dermique 10%
Povidone iodée
Solution pour application locale
MEDA Pharma 08920.3 10 ml

***This disinfectant** is applied to wounds to stop the spread of infection.*

Iodine is the only halogen that is solid at room temperature. The element forms a purple gas when heated, and is named after the Greek word *iodes*, which means "violet". Iodine was first discovered in seaweed, and many plants and animals in the sea have high levels of iodine. Seafood, including **crabs** and fish, provide the element in our diet. The human body needs small amounts of iodine to make an important substance called thyroxine, which helps us grow. Iodine is also used to make **printing ink**, red and brown food dyes, and disinfectants.

85
At
Astatine



⊖ 85 ⊕ 85 ○ 125 State: Solid Discovery: 1940

Atoms of astatine are unstable, and typically break down after just a few hours, into atoms of lighter elements, such as bismuth. This radioactive element itself forms in a similar way when atoms of a heavier element called francium break apart. Tiny amounts of this rare element are found in uranium ores, such as **uraninite**. The Italian physicist Emilio Segrè was one of the first scientists to isolate a sample of pure astatine. He was able to do so by using a particle accelerator: this is a machine that smashes together atoms and then studies the results.

__Inside this mineral__, unstable atoms of the element francium are breaking apart, forming astatine atoms.

Uraninite

117
Ts
Tennessine



⊖ 117 ⊕ 117 ○ 177



State: Solid
Discovery: 2011 (predicted)



Nuclear Reactor, Oak Ridge National Laboratory, Tennessee, USA

Atoms of tennessine **existed for a few seconds** after they were formed.

Tennessine is the youngest element in the periodic table. It was produced in 2011, in the Russian city of Dubna. The element was named after the US state of Tennessee, home to the **Oak Ridge National Laboratory**, which houses one of the first, large-scale nuclear reactors ever built. Only a few atoms of this halogen element have ever been made. Even so, scientists have predicted it to be a semi-metal, not a non-metal like all the other halogens.

Krypton (Kr) becomes visible only when it is electrified.



Noble Gases

The group on the far right of the periodic table belongs to the noble gases. These elements are described as "noble" because they do not react with the other "common" elements, such as oxygen (O). Their atoms never form bonds in nature, not even with atoms of their own kind, and so they are always gases at room temperature.

Atomic structure
Apart from a helium (He) atom that has two electrons in its outer shell, all other elements in this group have atoms with eight electrons.

Physical properties
All the members of this group are colourless gases. Going down the group, the density increases – radon (Rn) is 54 times denser than helium.

Chemical properties
Noble gases never react in nature. In the laboratory, heavier noble gases can be forced to form compounds with fluorine (F).

Compounds
These gases form no natural compounds. However, xenon (Xe), krypton (Kr), and argon (Ar) can be made to form compounds.

2 He Helium



● 2 ⊕ 2 ○ 2

State: Gas
Discovery: 1895

Forms



Pure helium in a glass sphere

This sample of helium *is trapped in a glass sphere.*

Helium is a transparent gas*, but it glows purple when electrified.*



Saturn

Saturn's atmosphere *is made up of clouds of hydrogen and helium.*

Natural gas *often contains some helium.*

Gas flare rig

Uses

A particle accelerator *is a machine that smashes atoms together: this one uses liquid helium to cool its parts.*



Large Hadron Collider, CERN, Switzerland

Helium-cooled MRI scanner

Helium is the second lightest element after hydrogen. This transparent gas was first discovered in 1868 by Sir William Ramsay, a Scottish chemist. Today, we know that a quarter of all the atoms in the Universe are helium. It is one of the main gases in the atmospheres of giant gas planets, such as **Saturn**. Being so light, however, helium is very rare on Earth: it escapes from our atmosphere into space. It was not until 1895 that chemists managed to collect a sample of helium gas coming from uraninite, a radioactive uranium mineral. Today, helium is

Airship

This airship *contains large quantities of helium to make itself lighter than air.*

Party balloon

This balloon *contains a mixture of helium and air.*

Helium-ion microscope



This powerful microscope *can zoom in to view much smaller details than most other microscopes.*

SUN GAS

In 1868, during a total solar eclipse (when the Moon passes directly in front of the Sun), helium was discovered in the cloud of gas seen around the Sun. The yellow colour of this cloud showed it contained an unknown gas, which was named after Helios, the Greek god of the Sun.



The Moon blocks the Sun's light from reaching Earth.

This outer gas cloud can only be seen clearly during a solar eclipse.

The edge of the Sun's disc is still visible.

This high-speed train *uses a pair of magnets: one to move forward and one to float over the track.*

Helium-cooled maglev train

The track is lined with a magnet *that repels the one on the train, making it float.*

Rocket helium tank

Helium in this container *will fill up a rocket's fuel tanks as they empty out during liftoff.*



This machine *contains a system that scans the organs of patients.*

Helium has the **lowest melting point** of any element.

collected from underground reservoirs or is found mixed in natural **gas** and oil. Unlike hydrogen, which is very reactive, helium is a noble gas and does not react at all. This property makes it safe to use in objects such as **party balloons** and **airships**. To turn helium into a liquid, it must be cooled to an extreme temperature of –269°C (–452°F). Liquid helium is used to make things very cold, including the powerful magnets used to make **maglev trains** float along special tracks. **MRI scanners** also use liquid helium for cooling.

NEBULA This glowing nebula (cloud of gas and dust) is the Crescent Nebula. It is so vast that our entire Solar System would fit inside it seven times over. The nebula's light comes from a super-heated star at its centre. Known as WR 136, this star is 15 times heavier than our Sun and 250,000 times brighter. Its immense power comes from its fuel – helium.

Helium makes WR 136 hot and bright. The star once burned using hydrogen, like our Sun. Hydrogen atoms smashed together in the star's core until they became helium atoms, releasing energy in the process. However, the star ran out of hydrogen about 200,000 years ago. It began smashing together helium atoms instead, and ballooned into a gigantic red star, sending out a cloud of gas that spread around it. The star is producing a wind of electrified gases that hurtles out at 1,700 km (1,056 miles) every second. This wind continues to crash into the gas cloud, making it glow into the nebula we see. Eventually, WR 136 will run out of helium and its other fuels, and explode into an enormous fireball called a supernova.

10 Ne Neon



⊖ 10 ⊕ 10 ○ 10

State: Gas
Discovery: 1898

Forms



This sample of neon *is trapped in a glass sphere, and gives off a red-orange glow when electrified.*

Volcanic eruption

Volcanic eruptions *release neon gas into the atmosphere.*

Neon lights may refer to lighting produced using any noble gas.

Uses

A deep red beam *is emitted by this laser.*



Helium-neon laser

Glass tubes filled with neon *are used as brightly lit signs.*

Neon sign

Neon is a rare element: it makes up just 0.001 per cent of our atmosphere. Some of it was locked in Earth's rocks when the planet formed, and this is released into the air by **volcanic eruptions**. **Pure neon**, a transparent gas, is extracted by cooling air to a temperature of −189.34°C (−308.81°F), at which point the neon gas in the air turns to liquid. Neon can be mixed with helium to create research **lasers**. However, it is most commonly used in lighting, such as in **illuminated signs** or as bright warning beacons in the path of aircraft at airports.

18
Ar

Argon



⊖ 18 ⊕ 18 ○ 22

State: **Gas**
Discovery: **1894**

Forms



Pure argon in a glass sphere

This sample of argon *is trapped in a glass sphere, and gives off a pale purple colour when electrified.*

Uses

Argon-filled suit

Some diving suits *are inflated with argon to retain heat in cold water.*



Double-glazed window

The space between the glass panes *is filled with argon to slow the loss of heat.*

Metal welding

Argon in this flame *prevents metals from reacting with oxygen*

Argon-filled display

The Magna Carta*, a historical document, is stored in argon, which forces out oxygen and water vapour that would damage the parchment.*

Argon is the third most abundant gas in the atmosphere, after nitrogen and oxygen. It undergoes no reactions with any other element, and was named after the Greek word *argos*, meaning “idle”. Argon does not conduct heat well so it is put in **double-glazed windows**, and in **diving suits** during cold, deep dives. Its lack of reactivity is useful. Argon is used in **museum displays** to protect delicate exhibits. It also stops metals reacting during hot **welding**. This element can also be useful in the production of titanium.

36
Kr

Krypton



36 36 48

State: Gas
Discovery: 1898

Forms



Pure krypton in a glass sphere

*This sample of **krypton** is trapped in a glass sphere.*

*Krypton is a transparent **gas** but it glows with a blue-white light when electricity flows through it.*

*When this camera's **flash** activates, it's a result of krypton being electrified by the camera's battery.*

Digital camera

*Krypton-based **lasers** illuminate this building.*

Laser lighting

Sir William Ramsey won a **Nobel Prize** in Chemistry for discovering the noble gases.

Uses



Incandescent bulb

This energy-efficient bulb contains krypton.

Plasma ball



This globe contains a mixture of noble gases, including krypton.

The word krypton means the "hidden one" in Greek. This element exists as an inert gas in nature, which means that it does not react with almost any other element. Krypton is not found in any minerals and only tiny amounts of it can be found in the air. **Pure krypton** produces a very bright white light when electrified with a current, which makes it ideal for use in **flash bulbs**. Krypton can react with the element fluorine to form the compound krypton fluoride, which is used to power some kinds of **laser**.

54
Xe

Xenon



● 54 ⊕ 54 ○ 77

State: Gas
Discovery: 1898

Forms



Xenon is a transparent gas *but it glows with a blue light when an electric current flows through it.*

This sample of xenon *is trapped in a glass sphere.*

Anaesthesia machine

The xenon produced by this device *makes a patient unconscious before an operation.*

Xenon is used in powerful **lasers** that can **kill bacteria**.

Uses

Car headlight

Xenon headlights *glow brighter than the more common halogen headlights.*

Xenon glow *disinfects the air in a room.*



High pressure inside this lamp *makes electrified xenon glow very brightly.*

Modern film projector lamp

Dawn space probe

Electrified xenon *blasts from the exhaust, pushing the probe forwards.*

Xenon is so rare that there is only one atom of this gaseous element for every 10 million atoms in the air. Like the other noble gases, xenon is colourless and odourless. It glows brightly when electrified, making it useful in very powerful lamps, such as those used in **film projectors** and **car headlights**. The gas is harmless when breathed in and can be used as an **anaesthetic**. When preparing food, **xenon lamps** can purify the air. To propel spacecraft, xenon is used in some rocket engines that produce streams of fast-moving, electrified atoms.

86
Rn
Radon



⊖ 86 ⊕ 86 ○ 136 State: **Gas**
Discovery: **1900**



This uranium mineral *releases radon gas, as radioactive metals in it break apart.*

These yellow crystals *belong to another uranium mineral called uranophane.*

Uraninite

Radon is the only natural radioactive noble gas. This element is produced by the breakdown of uranium and other radioactive metals. Being a gas, radon escapes from minerals, such as **uraninite**, into the air. Radon is very radioactive and breathing it in can cause illness, such as lung cancer. In most places, the amount of radon in the air is incredibly tiny. However, its levels are high around **volcanic springs** and mud, where it bubbles out with other hot gases. Radon is also present in the water at **geothermal power plants**, which use heat energy from deep, volcanic rocks to make electricity. Radon is also more common in areas rich in granite rock. In these places, people use **test kits** to monitor their homes' radon levels.

It takes only **3.8 days** for half of radon's atoms to split into atoms of other elements.

Glass sphere containing radon and air

As it decays, *a compound called thorium dioxide emits radon.*

The muddy water *from volcanic springs contains radon.*

Hot springs in Lisvori, Greece

These pipes *draw water containing radon from deep under the ground, and this is then used to power the plant.*

Geothermal power plant

This kit *collects radon from the air so the amount of the gas in the area can be measured.*

Radon home test kit

RADO
Glenwo
3 Scien
Glenwo
08807

118 Og Oganesson



State: **Solid**
Discovery: **2006**



Yuri Oganessian

The heaviest element yet made is oganesson. Scientists think it would be solid at room temperature, but it may really be an unreactive, noble gas. However, only a few atoms have been created so far, so its properties are not well understood. Oganesson was first produced by a team of Russian and American scientists who smashed californium and calcium atoms together at the **Joint Institute for Nuclear Research** in Dubna, Russia. The element was named after **Yuri Oganessian**, the leader of the team.

Joint Institute For Nuclear Research, Russia

DICTIONARY OF SELF-AFFIRMING POWERFUL QUOTATIONS

By Christian H. Godefroy
with the help of
Didier Penissard

Published by Christian H. Godefroy (2001 Christian H. Godefroy. All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, recording or otherwise, without the prior written permission of the author.

Manufactured in the United States of America.

Table of contents

Contents

Introduction 3
A 10
B 36
C 47
D 78
E 103
F 125
G 152
H 160
I 181
J 204
K 209
L 211
M 229
N 254
O 261
P 272
Q 306
R 307
S 331
T 387
U 408
V 412
W 418
Y 437

Table of contents

Introduction

What power do words have?

You surely remember fairy tales from your childhood where the wicked queen cast a spell on the hero. The spell usually consisted of some gesture, accompanied by a “Magic Formula” with powerful effects. Sometimes the spell was a curse or malediction (literally: words which convey a wish that harm come to someone).

During your childhood people around you cast all kinds of spells on you. Very often you were not aware of it, but Magic Formulas - transformed into so-called “killer sentences” - had their effect on your mind, and continued harming you in subtle ways.

Let’s look at a few examples. Has anyone ever said something to you like:

- You’re really good for nothing.
- You’ll never make it.
- Blockhead!!!
- You’re just a chip off the old block!
- You’re even worse than your mother.
- You’re not going to start crying again, are you!?!
- Stop trying to be so special...
- It never fails : you’re incapable of being on time.
- What an idiot you are!
- You have absolutely no sense of humor.
- You’re always sick.

Table of contents

- You just don’t have any talent.
- You should never...

Every time someone used the words “be” or “have” or “always” or “never” when referring to you, chances are they were casting a harmful spell on you.

How harmful spells affect your life

Because these kinds of sentences were stored in your subconscious at an age when you were not able to question their validity, they continued to affect you in subtle ways right into adulthood.

Of course they may be more specific:

- Beware of women.
- Beware of men.
- You’ll never understand anything about math.
- Mechanics is a man’s job.
- Never trust a Frenchman.
- Making love is dirty.

These kinds of thoughts may not prevent you from getting married, making love or repairing your car, but the causes for your lack of confidence, for the problems and failures you encounter in life, can very often be traced back to these negative seeds.

You are also casting spells on yourself

Do you sometimes talk to yourself? Of course you do, just like everyone else. And do you sometimes blame yourself for the way

Table of contents

you behave? Are you ever negative about yourself? Of course you are.

- What an idiot I am!
- I'll never make it.
- I'm always so clumsy when I'm with other people.
- I'm just not lucky.
- I'm going to get shafted (taken for a ride) again.
- I'm not good enough.
- I'm so much less talented than...

You've taken up where the others have left off, and are casting spells on yourself! Ideally you would identify these kinds of negative reproaches and replace them with stimulating, positive thoughts which liberate you, make life easier, and affirm your worth instead of inhibiting and prohibiting you.

How to weed out these negative thoughts?

Using the Dictionary of Self-Affirming Powerful Quotations is an excellent way to discover where these seeds of failure, anxiety, health or relationship problems, etc. are hidden. It's as if, by consulting the dictionary, you are trying to defend yourself against them. Whenever a positive thought makes you uncomfortable, or bothers you without your knowing exactly why, or just seems stupid, take it as a sign. Continue working with that thought until it reveals its secret meaning to you.

You can also make a list of the difficulties you have to face, the problems you encounter, and then use a corresponding positive thought as an antidote.

Table of contents

Try to remember what was said to you just before you started feeling “down on yourself” or depressed.

How to neutralize the power of negative spells

Many people before you have had to deal with these kinds of negative thoughts. That’s why therapists, doctors, and specialists in the art of suggestion have developed antidotes in the form of positive affirmations. The Dictionary of Self-Affirming Powerful Quotations offers you a selection of the best of these.

Better still, they’ve all been transcribed into the first person (I) so that you can use them to replace the negative spells you are casting on yourself. Here’s what to do:

1. Using the alphabetical headings and index, find a positive thought that can serve as an antidote. If you like you can copy the structure of existing affirmations to create your own new ones.

2. Read it carefully, out loud if possible. Then repeat it silently to yourself. Copy it on a pad or in a notebook that you carry around with you. Make it a theme of meditation: while driving, or riding on the train or bus, or lying the beach - any time your mind starts wandering - repeat the positive thought.

3. Use altered states of consciousness resulting from relaxation, meditation or self hypnosis to impregnate your subconscious more deeply. You can tape an hypnosis-inducing text on cassette, followed by your positive thought(s), and then a wake-up message.

Table of contents

4. Discuss your situation with a friend or close relative. Exchange points of view with persons who do not have the same problem as you do, in order to understand how their minds work, and eventually to use them as models for your own behavior. Also try to read personal accounts of how others have successfully dealt with the same type of problem.

5. Allow at least 21 days for your inner transformation to take place. If you are trying to make some very drastic changes, persevere for at least 3 months.

A marvelous tool for personal development

The Dictionary of Self-Affirming Powerful Quotations is a constant companion, always ready to inspire you and guide you along the paths of life. It will help you learn to know yourself better, and exploit the formidable power of your subconscious to help you attain your goals.

You can also use it as an instrument of divination: just ask yourself a question, and then open the book at random. You'll be sure to find an answer, or at least its essential elements.

Copy the thoughts you find most inspiring. The simple act of writing out a thought helps make it your own.

If you're living through a difficult period in your life or feel that you're under a lot of stress, immerse yourself in the Dictionary of Self-Affirming Powerful Quotations and let it wash away all the negative influences and emotions you experience during the course of a day.

Table of contents

And if you happen to be a therapist or teach some form of relaxation or meditation, or if you want to use positive suggestions to help your children, the dictionary will provide you with a constant source of counsel and guidance.

A valuable tool in your interpersonal relations

Does your child have a tummy ache? Does he or she have trouble concentrating? Is your sister in the process of rebuilding after a difficult divorce? Is your partner having business problems?

Open the Dictionary of Self-Affirming Powerful Quotations to the appropriate page. Select one or a number of sentences. A single positive thought can change your life. It can be the branch that saves a drowning person, the talisman, the blessing that breaks the evil spell.

Offer these thoughts to others as you would offer a bouquet of flowers. The Dictionary is like a jewel box, the positive thoughts it contains are like precious gems. Offer them as gifts to your friends and loved ones. And like jewels they will reflect the light of love and dispel the shadows of despair.

As you'll soon discover, this dictionary is an amazing collection of positive thoughts with almost magical powers. It's almost like an Aladdin's lamp, ready to grant all your wishes. All you have to do is keep reading it. In no time at all your life will become simpler and easier, free of all the obstacles which have been holding you back in the past.

Life gives you what you expect of it, on condition that you cultivate positive and creative thoughts. And the Dictionary of Self-Af-

Table of contents

firming Powerful Quotations will help you change your way of thinking. You'll see opportunities where others see only obstacles, solutions where others see only problems, lessons to be learned where others see failure, and beauty where others see nothing at all.

Consider this dictionary as a great prayer of enthusiasm and confidence in life and in humanity, full of gratitude.

Christian H. Godefroy, mailto:webmaster@hypnotic-words.com

Table of contents

ABUNDANCE

This great power, the power to choose, gives me the necessary hope and the necessary state of mind and the necessary courage to get everything I really want out of life.

J. Martin Kohe, Your Greatest Power, published by A Different Life Ltd., 1979

I believe in abundance, I desire abundance, I receive abundance.

Shakti Gawain, Reflections In The Light, New World Library, 1978

I allow this infinite abundance to pass freely through me and through all those who listen to me, just as I freely give up the money I possess, allowing it to flow through my hands, giving where it can do the most good.

Robert Collier, Riches At Your Doorstep, S.I.P. 1962

I am grateful, and I rejoice in a life full of abundance.

Dr. Joseph Murphy, The Miraculous Power To Attract Infinite Wealth, Godefroy Publications, 1979.

I lead a rich and abundant life, physically, spiritually, and on other levels.

Shad Helmstetter, The Power Of Inner Motivation, 1987.

The universe is a horn of plenty which everyone can draw from. My very nature is abundance, and I accept it fully. Abundance is what I really am. And I accept it fully and joyfully. The universe is pure abundance!

Shakti Gawain, Techniques Of Creative Visualization, Editions Soleil, 1978.

Table of contents

ACCOMPLISHMENT (Also see Success)

By using my imagination I move towards accomplishment. I remove the debris caused by the wounds I have suffered, which deprive me of the inner security I deserve.

Dr. Maxwell Malts, Psychocybernetics and Self Accomplishment, published by A Different World Ltd. 1970.

I was conceived to accomplish, built for success, and gifted with the seeds of greatness.

Zig Ziglar, Rendezvous At The Summit, published by A Different World Ltd., 1975

I will do things that will make me live longer... live better.

J.V. Cerney, Stay Younger - Live Longer through the Magic of Mental Self-Conditioning,
Parker Publishing Company, Inc. 1968.

ACNE (See Urticaria, Eczema)

ACTION (Also see Opportunity)

From now on I will savor every one of my actions!

Shakti Gawain, Techniques Of Creative Visualization, Editions Soleil, 1978.

I will act immediately.

Og Mandino, The Greatest Secret In The World, published by A Different World, 1979.

I act constructively. I do what my conscience dictates.

W. Clement Stone, Napoleon Hill, Success Through Constructive Thinking, Godefroy Publications, 1978.

I flow with my energy - all the time.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

I act in a positive way.

Subli Power - Subli Control, Edit Inter, 1989.

I act.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I cease all actions which work against me. Then the right actions are revealed to me.

Vernon Howard, Psycho- Pictography, S.I.P., 1965

I don't want to remain passive in the face of life any longer, nor allow myself to be carried along by circumstances. I want to act. I want to attain my goals.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I now know that to overcome fear I have to act without hesitation and my doubts will disappear. I now know that action transforms fear into serenity. I will live this day as if it were my last. Action is the bread and the wine that nourishes my success. Action is the spark that gives life to my dreams, my plans, my goals, and transforms them into reality.

Og Mandino, The Greatest Secret In The World, published by A Different World, 1979.

I am capable of action.

Jean Chartier, How To Acquire A Superior Personality, Published by Dangles, 1971.

I am in the process of changing my life through my actions. This is a choice that belongs to me.

Richard Corriere & Joseph Hart, Staying In Psychological Shape, Les Editions de l'Homme, 1979.

I am completely ready.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I simplify my life. I get rid of disorder and actions which are not fruitful. I continue asking myself questions, at least once a week:

Table of contents

“What is it, above and beyond my daily routine, that constitutes the essence of my life, and what are the real activities to which I should be devoting my time?”

Denis Waitley, Seeds Of Greatness, Editions Pocket Books, 1984.

ADVERSITY

I face up to things courageously. I stay calm.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

I am happy to encounter a certain form of opposition. It offers me an opportunity to test my strength and my ideas.

Raymond Hull, Wanting Is Power, Les Editions de l’Homme, 1969.

Adversity always contains the seed of a new opportunity. I can do it, if I believe I can!

W. Clement Stone & Napoleon Hill, Success Through Constructive Thinking, Godefroy Publications, 1978.

Once I start playing a game I always do my best to hit the ball back and defeat my opponent.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

AEROPHAGY (Flatulence)

Although my stomach is swollen, I know the swelling will gradually disappear. Little by little my stomach will regain the strength and elasticity it lost, and as it regains this strength and elasticity it will return to its normal size, and carry out the functions of digesting food and sending it to the intestines more and more easily, until my stomach and intestines are in perfect form.

Emile CouÈ, Complete Works, Astra Publications, 1976.

Table of contents

ADVICE

God will tell me what I should do.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

My subconscious becomes a more and more important part of myself... I can ask it questions... it answers... it advises me and guides me.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

AFFECTION

I am affectionate.

Dr. Wayne W. Dyer, Your Erogenous Zones, Tchou, 1976.

The positive emotions of love, affection and patience appear when I am in touch with my true self.

Vernon Howard, Psycho-Pictography, S.I.P., 1965

AFFIRMATION

I have the right to be myself. Affirmation is a measure of my success. I affirm myself more and more, in all areas of my existence.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

AGING

I avoid being inactive and doing nothing... I make sure not to let my movements slow down too much... I cultivate vivacity in order to keep myself alert.

Table of contents

I am sure I will stay forever young... my mind will remain lucid... and I will not suffer the pains of aging until very late in life... my life is rich and productive.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I adapt to the ups and downs of life by maintaining my sense of humor. I keep the child alive and awake within me.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I may be aging, but I am also improving with age.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

AGITATION

At the least sign of becoming over-excited I react and remain impassive.

Paul-Clement Jagot, How To Develop Your Personal Magnetism, published by Dangles, 1982.

AGREEMENT

I try to reach explicit agreements in the form of contracts.

Pierre Nicolas, Time Is Money - and Pleasure, Inter Editions, 1981.

AGGRESSION

The spirit in me is my shield. The spirit in me is my saviour. I have nothing to fear - the power of the spirit protects me.

Marcelle Auclair, The Book Of Happiness, Editions de Seuil, 1959.

The spirit in me is my refuge and my fortress.

Marcelle Auclair, The Book Of Happiness, Editions de Seuil, 1959.

Table of contents

AIDS

My immune system is back to full strength again.

Louis Proto, Self Healing, Piatkus Publications, 1990.

ALCOHOLISM (Also see Sobriety)

Drinking is no longer important to me.
Drinking is no longer a necessity for me.
I forgive myself for past mistakes which led me to drink.
I am becoming a more relaxed person.
My self confidence is growing day by day.
I like people, and I feel they like me.
I think of myself as a positive person.
I like to think of myself as a person who doesn't drink.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec/Amerique Publications, 1874.

I like drinking water.

Subli Power, Sublihealth, Edi Inter, 1989.

I free myself of the habit of alcohol. I love myself, and I love life more every day. I am proud of myself.

Karl O. Stoeber, Psycho-training, Godefroy Publications, 1984.

I don't have to have a drink whenever I am upset or frustrated. I can survive life's frustrations without alcohol. And because I have proven to myself over and over again that I have never been able to handle alcohol intelligently, I am going to abstain altogether.

Frank S. Caprio, M.D. and Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc. 1974.

I have no trouble controlling my drinking habit. I now drink alcohol in moderation. I can easily go several days without having a drink. The less I drink the healthier I get. I am mastering my habits,

Table of contents

and my general health is improving day by day. I like my body, and I want to keep it healthy for as long as possible. So I take care of it. I drink very moderately. There are many days I don't drink at all, and I'm perfectly happy.

I am giving up alcohol completely. I have no trouble not drinking at all, and I feel a lot better. My body and mind are completely free of the alcohol habit. I have more and more control over my emotions. I can stop drinking completely, starting right now. From now on I'll be sober and happy.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I couldn't care less about drinking, any place, any time, under any circumstances. Others can drink, but I'm really not interested.

Clement Auger, Transform Your Life Through Auto-suggestion, Heritage Press, 1979.

I feel as if all my problems were fading away.. I've solved them all... nothing can change my mind... I feel absolutely no desire for alcohol any more... drinking doesn't interest me... it turns me off... more and more... even the thought of alcohol turns me off... just looking at alcohol makes it even more repulsive.

From now on I won't drink any alcohol... nothing can make me change my mind... I'm happy to be improving my health, and I feel better every day... I'll never drink alcohol again. I find it more and more repulsive. Even the though of alcohol disgusts me.

If I drink a single glass, I'll get sick. My stomach can't take any alcohol... even a glass will make me very sick... I will try not to succumb to temptation.

I'll never drink alcohol again.

Just the sight of alcohol makes my disgust grow... I'm so happy to be free of it... nothing can make me change my mind. I can't drink any alcohol... and I won't!

Professor Kurt Tepperwein, Secret Techniques of Hypnosis, Godefroy Publications, 1981.

Table of contents

I am capable of resolving my problems, and thus of freeing myself from the burden of alcoholism.

Professor Kurt Tepperwein, Think and Heal, Godefroy Publications, 1984.

I'm going to stop drinking not because others want me to, but because I really want to.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I'm a nice person when I don't drink. I look better when I don't drink. I work better when I don't drink. I lose weight when I don't drink. I'm healthier when I don't drink.

Editorial staff of Practical Health Guides: How To Activate Your Body's Natural Defences,
Godefroy Publications, 1989.

ALLERGIES

I have more and more fun with cats. Cats are gentle, affectionate animals. My body reacts completely normally when I'm with them.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I'm a healthy normal person. My body functions normally, under any conditions. I function perfectly normally in the presence of animals. My body functions normally, whatever the surrounding odors are. I am free of past negative influences which have been causing my allergic reactions. Soon I'll be able to eat any food I like. Each day that goes by strengthens my conviction that I am in the process of resolving all past problems. I perceive of myself as a person who is not allergic to anything.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

ALLERGIES (Food)

I can now eat —— (name the food) easily and find it delicious. I

Table of contents

am free of past negative influences. My body now reacts normally to all the foods I eat.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

ALTRUISM

To me loving means listening unconditionally and without prejudices, to the needs of another person, and fully appreciating his or her worth.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I have the right to be open with other people.

Christian. H. Godefroy & John Clark, How To Have More Time, Godefroy Publications, 1989.

I stop thinking only about myself, and think more about others. Every day I try to do something kind, something that brings a smile to a suffering face.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I always take other people's feelings into consideration. I am aware of their feelings, sensitive to their attitudes and opinions. I know how to listen. I show a sincere interest in the convictions, thoughts and ideas of others. And since my interest is sincere, other people recognize that and start counting on me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

AMBITION
(Also see Vitality, Dynamism, Enthusiasm)

I maintain a victorious attitude towards life. I know there is no task a person cannot accomplish once he or she has made up his mind. I want to accomplish... (name the task). My ambition is completely

Table of contents

legitimate. I want to make progress in my work, as well as in my intellectual and moral development. I will leave nothing to chance. Attaining the success I aspire to depends solely on me.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.¥

I reconstruct myself with a brighter future.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am not content with being less than I can become. I'm as capable as any other human being who has ever lived. I am not afraid of my own greatness.

I always remember that I can become anything I choose to be, and that greatness is there for the taking if I really want it.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I am no longer satisfied with what I can get, but only with what I want to get.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I know I can obtain everything... gain access to the highest circles... I only have to want it... and have faith in my success, and I will succeed.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I am aware, conscious, and ready! I am overflowing with vitality and ambition. I exploit every opportunity with dynamism and enthusiasm.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am a CEO (or a lawyer, or any profession of your choice). Every day brings me closer to my goal. I know I am already there. It's fantastic. I accept my own amazing future.

Charles Baudouin, Psychology And Practice of Auto Suggestion, Idegraph Publications, 1990.

I am full of ambition, and there is nothing wrong with that. I want

Table of contents

to succeed in my work, as well as in my personal development.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

ANAEMIA

My blood is getting richer and richer, more and more red, more and more nourishing. It is getting to be more and more like healthy blood. My anaemia is gradually disappearing, carrying away with it the host of problems that accompany being anaemic.

Emile Coue, Complete Works, Astra Publications, 1976.

My blood is rich, and is replenished daily.

Louis Proto, Self Healing, Piatkus Publications, 1990.

ANAESTHESIA (Also see Pain, Wounds)

With each pinch the anesthesia spreads. At first I pinch lightly, adding pressure each time. The fourth time I pinch, the anesthesia will be complete.

Leslie M. Le Cron, Liberate The Forces In You Through Self Hypnosis, Tchou/Ariston, 1964.

All right, now I'm going to count to three, and on the count of three my arm will become rigid, and the more I try to bend it, the more rigid it will get. During this time my right hand will grow more and more numb, more and more numb... more and more insensitive. Now even my left hand is becoming rigid, so the anesthesia in my right hand is getting stronger.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

Table of contents

ANAESTHESIA - DENTAL

My cheek is numb, I can prick it with a needle, and not feel a thing... My lower gum is numb, I can prick it with a needle, and not feel a thing... My whole mouth including gums and teeth are totally numb, like a block of wood.

Giovanni Sciuto, Real Hypnosis, Dangles Press, 1975.

ANGER (Also see Migraines)

What other people think or say about me doesn't bother me. If my inner Guide is with me, if He (or She) approves of my thoughts and actions, then everything is all right. I am calm and strong!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

It's normal to get angry from time to time.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I take responsibility for my emotions. When I begin to get angry I acknowledge the fact that I own my emotions. I remove myself from any potentially hostile situations. When I talk about my anger or dissatisfaction I say: "I feel angry when I see that happening," instead of saying, "You make me angry when you do that." Only I can make myself angry.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I master my emotions. I never get angry for no reason, nor do I react violently to any situation whatsoever.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

I am very careful not to get angry. I have a good character, I demonstrate patience, and I always think before I act. I avoid complaining.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

When I get angry about not achieving the results I want in a situation, I move quickly from “stewing to doing.’ I ask, “What can I do to turn this situation around? Is there anything I can salvage from this situation? What can I learn from this situation? How can I prevent it from happening again?”

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

When I get angry I remind myself that everyone has the right to be what s/he chooses to be, and demanding that others be different will only result in prolonging my anger. I make sure to let other people make their own choices. After all, don’t I claim that right for myself?

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

When I feel myself getting angry I quickly give myself the suggestion that I can switch my thoughts to something else. If need be I can always walk away from the person who is provoking the anger reaction, or expend my energy in doing something that will divert my mind - finding some other outlet for my pent-up emotions. I am going to remind myself that people can make me angry only if I allow them to do so, and that getting angry is actually flattering the other person.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

ANGINA (Chest)

The attack is passing and my heart is beating normally.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

ANSWERS

My Real Self knows all the answers I need.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

ANXIETY

From now on, whenever I feel anxious I will breathe deeply, relax, and feel a surge of energy rising through me.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I express the anxieties I have about myself, and then let go of them.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am completely calm... completely calm... A marvelous feeling of peace and harmony spreads through my body... I am happy... my circulation is regular and my digestion is perfect.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I feel a hot current flowing through my solar plexus.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

In the past I would look anxiously outside, waiting nervously for something bad to happen. From now on I look inwards, full of confidence. I look to my Inner Guide.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I am learning to interpret my anxiety as a state of excitement instead of nervousness.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

Table of contents

I stop anxiously fighting all the little complications of life. I simplify my affairs.

I have to work towards freeing myself of all forms of fear and anxiety.

I feel less tense and anxious.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am in the process of becoming a much more self confident person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I see my life and everything that happens from the calm, clear perspective of my conscience, and profound understanding.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

My tension can be an ally because if I feel any anxiety, I take it as a sign to call on the means at my disposal to deal with the situation.

I take a deep breath and relax. Everything's all right. I am in control of the situation, and of myself.

It's all over, I've succeeded.

It wasn't as bad as I thought it would be.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

Everything is fine.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

ANXIETY - SOCIAL

It does no good to worry. It's much better thinking about what I can do rather than becoming anxious. I have plenty of time to take a deep breath and relax before dealing with the situation.

I don't have to prove anything to anyone. If others accept me, all the better. If they don't, too bad. I'm not trying to make everyone

Table of contents

love me.

I concentrate on the present moment. What do I have to do now?

I think mostly about the things I have to do, and about the positive results these actions will bring.

If I deal with the situation step by step, I won't have any trouble.

I can't expect people to always think as I do, and do what I want them to.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

APLOMB

In all situations where I used to be too impressionable, I am now protected by a suit of armor through which nothing can penetrate.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

I develop my aplomb and my confidence.

SubliPower, Subli Confidence, Edi Inter, 1989.

I feel an imperturbable calm in the face of anything that happens.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I don't allow anyone to influence me.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

APPEARANCE (PHYSICAL)

I know that my appearance, my weight and my well being depend solely on me. I do everything necessary, every day and every instant, to create the "me" I really want to be.

I am in control of myself. Only I decide what my physical appearance is like, how much I weigh, and how I feel.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

APPETITE (Also see Digestion, Stool)

I'm hungry at mealtimes... I am attracted by natural, healthy foods.

Sublipower, Subli Health, Edi Inter, 1989.

APPREHENSION

I am calm, courageous and free! My inner Guide fills me with confidence, self assurance, love and harmony. I feel free, joyous and strong. I am free, and secure under Your wing. I am free!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Negative suggestions, phobias, apprehensions, dark or sad thoughts all gradually disappear of their own accord, without my having to fight them. Even dark thoughts and feelings which are based on reality are gradually receding.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

APPROVAL

I feel good because I want to, and my feeling good has nothing to do with you.

No one is unhappier than people who need (the approval of) other people. But those who want to love others become happy themselves.

I thank people who tell me things that can help me, even if what they say is difficult to accept. My feeling of gratitude replaces my need for approval.

I stop looking to my spouse, or to anyone else, for approval of what I say, by cutting out things like, "Isn't that true, dear?" or... "Don't you agree?" or... "Ask so and so, she'll tell you."

Table of contents

I reprimand myself out loud every time I find myself seeking other people's approval. By doing so I become aware of this kind of behavior, so that I can stop it.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

It is completely normal that people forget to express or even feel gratitude; therefore, if I expect other people to reward me through a show of gratitude, I am only exposing myself to a flood of bitter disappointments.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I'm sure the sales manager will notice my effort and my results.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

ARCHERY

I am perfectly relaxed when I practice archery.

My reflexes are getting faster and more efficient. I can hit the target more and more easily, shot after shot. I am improving all aspects of my archery. My vision and reflexes are working marvelously well. Archery is easy for me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

ARTHRITIS

I relax the muscles around my joints. I feel a cascade of clear water flowing over my joints, washing them, purifying them, making them strong. The water carries away the pain. I see the cool clear water flowing over my fingers, my knees, my shoulders. It calms me, washing away the inflammation. I can already feel the water sooth-

Table of contents

ing my joints, relaxing them, so that I can move with no pain at all.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

My joints are supple again, and feel smooth and comfortable.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My energy circulates more and more freely through my whole body, which is becoming light and luminous. My pains completely disappear because the amazing power of my subconscious mind is healing me completely.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

ARRHYTHMIA

My heart beats slowly and calmly.
I am my heart.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

ASKING

I have the courage to ASK.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

ASSIDUITY (Also see Perseverance)

I'm interested in material things, and I do my work conscientiously.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Table of contents

Work that you're interested in is never difficult, and sure to succeed.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

ASSIMILATION

I'm getting stronger day by day. I assimilate information more and more rapidly and precisely, and my willpower is getting stronger.

Paul Clement Jagot, The Power Of The will, Dangles Press, 1950.

ASSISTANCE

The universe is always there to help me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

ASSISTANCE - SPIRITUAL

I send you strength and courage. United with the forces of your inner Guide, I consciously direct our plenitude towards you, so that we can offer you assistance and stimulate the right conditions which will help your development.

I love you and send you energy, faith and courage. May a clear vision awaken in you of the right path to follow. Everything good you wish to accomplish will succeed.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Right now divine love is doing its perfect work for the benefit of all.

From now on may divine love and light work through me.

Table of contents

Divine love goes before me and prepares the way.
From now on God will show me the way.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

ASSOCIATES

My time and energy are precious. I choose to surround myself with positive associates who are focused on possibilities, learning, improving and taking responsibility for results. I guard my mental life against negative influences.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

ASSURANCE (Also see Self Confidence)

Every day I feel more and more sure of myself, and it's great. A beautiful, exciting life is awaiting me; it's wonderful to feel this sense of assurance growing in me, this confidence in myself that I feel getting stronger and stronger.

Charles Baudouin, Psychology And Practice of Auto Suggestion, Idegraph Publications, 1990.

I'm ready for action, I look more assured, more vibrant, more convincing. I speak with conviction and tread firmly.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I feel strong and calm no matter what happens.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I always feel calm and self assured.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I can be whoever I want to be with total support. I can go fast or slow - it's my choice. I am protected.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

Table of contents

I am calm and confident. I possess the tranquil assurance that my life will be a success.

Shad Helmsletter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am happy, self assured and strong.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am confident.

Matthew McKay & Patrick Fanning, Self Esteem, New Harbinger Publications, 1990.

ASTHMA

Every day I feel more and more free and relaxed. I react normally to all situations. I fill my lungs fully when I breathe. And I can easily overcome any tension or anxiety I feel. I am in perfect control of my body in all situations.

My bronchial tubes and lungs are strong and relaxed. I breathe calmly and deeply in all situations. I always stay calm, and control my body's reactions. I feel more and more confident and relaxed all the time.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I send energy from my brain into my nostrils, which will remain open, sending air to my longs, for as long as I want.

My lungs are relaxing, air is entering, the attack is subsiding.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

I am completely relaxed, breathing deeply and freely.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am convinced that my asthma problem is getting better every day.

I free myself of the causes of my asthma attacks.

Table of contents

I am convinced that I don’t have to have these attacks.

I’m becoming a relaxed person.

I feel stronger and healthier every day.

I see myself as a healthy, normal person.

I always breathe easily and normally.

I don’t have to use an asthma attack to get other people’s attention.

I can now share my feelings with others more easily.

I have strong willpower, and I can easily control my physical reactions.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

My breathing is relaxed and effortless.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My breathing is slow and regular; with each breath the muscles in my bronchial tubes and lungs relax more and more deeply; air enters my rib cage more and more freely, and my breathing becomes easier and easier.

After each session I see myself gradually improving. I breathe much more easily, the wheezing in my chest is disappearing, I am becoming much calmer, much more relaxed, and much less nervous.

As soon as I place my left hand on my chest, the muscles in my lungs and bronchial tubes relax; I feel them relaxing, I feel the air flowing more and more freely into my lungs, my breathing becomes easier and easier; with each breath my chest muscles relax more and more, and my breathing becomes calm, regular, calm, regular and easy.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

My breathing is completely normal, deep, regular and calm.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Table of contents

ASTHMA ATTACK

It's stopping, I'm already breathing easier.
I can feel myself breathing more easily. One more breath and it'll be over.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

AUDACITY (Also see Courage)

I will go where failures fear to tread.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I dare to do what I want. I act! I'm no longer afraid, and I will succeed.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I dare take the first step towards my rightful castle.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I can't always be reasonable and please everybody if I want to feel good about myself; I have to take risks, risks which develop a feeling of direction in me.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I Can, I Want, I Dare, I Act.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I want to dare.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

To succeed I risk failure, and that is the proof of audacity.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Table of contents

If there's nothing to lose and a lot to gain, I'll go for it.

W. Clement Stone, Passport To Success, Godefroy Publications, 1962.

AUTOSUGGESTION (Also see Hypnosis)

I am going to follow the suggestions which I implant in my subconscious mind.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

AVAILABILITY

I am always available for people whom I consider important, and for things which I consider important.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

AWARENESS (See Self Awareness)

Table of contents

BAD CHARACTER

I am acquiring a pleasant and joyous character.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I believe that my bad temper can be controlled, and I am not going to rationalize by thinking that I cannot help myself.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

BAD HABITS (See Habits - Negative)

BACKACHE

All the muscles in my back are relaxing. The tension in my dorsal region is dissolving completely. My whole back feels better and as this happens my confidence grows. My spine is relaxing. My back is getting stronger every day, and all tension is disappearing.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

BALANCE (Also see Peace, Strength, Wisdom, Health, Harmony)

Table of contents

In the past I used to suffer from fears that almost made me physically sick, but I am gaining strength as I become more and more balanced, and the strong and healthy person I know myself to be.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

I eat and sleep well.

I take care of my physical balance, since it plays such an important role in my ability to work well, and remain emotionally stable.

I know that the best thing is to maintain a constant and balanced relationship with my body, instead of getting preoccupied with it from time to time.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am well structured and balanced.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I am a balanced person.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am perfectly balanced.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

A sign of the presence of God in me is my feeling of peace and balance.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

My body is balanced, in perfect harmony with the universe. I am always deeply relaxed and balanced.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

BALDNESS

Now that I am no longer using my energy to work, I will channel

Table of contents

it to my scalp; the energy flows more normally, replenishing my hair as it did in the past so that it grows quickly.

Like crabs who grow new legs I can regrow my hair.
I want my hair to look like... (add description).
My hair is growing... growing.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

BEAUTY (Also see Health)

Every day my beauty shows a little more clearly. Every day I move closer to this promise of beauty. I feel better and better.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

I give thanks for ever increasing health, beauty and vitality.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

My body is pure and beautiful. I love nature and count my blessings. I see beauty in others, and experience it in myself.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

BEHAVIOR

The totality of my actions and behavior determines how others decide they should treat me.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

BEING

I am a strong, affectionate and creative being.

Table of contents

I am a radiant expression of God. From now on my body and mind will express divine perfection.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

BELIEF

I allow myself to hold something sacred in life.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

BELONGING

I move forward with confidence and chances are I will experience a sense of belonging.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

BENEVOLENCE (Also see Sincerity)

I look at myself with benevolence and I can thus fend off my solitude indefinitely.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am more and more benevolent towards myself and towards others.

Sublipower, Subliconfidence, Edi Inter, 1989.

I am always serene and benevolent.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

Everyone wants the best for me.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

Table of contents

[I treat everyone with kindness. I treat everyone as a precious and passing gift.]

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

BEST

I accept and deserve the best, which is flowing to me now that I have become an open channel.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

BIRTHING

I prepare for giving birth every day, and make sure to practice the techniques I'm learning in my prenatal classes to make the birthing easier. I am a woman who is in full control of myself and my reactions.

Marcel Rouet, Mastering Your Subconscious, published by Dangles, 1982.

I feel very good, and I look forward to the birth impatiently... all this is engraved in my subconscious... As soon as I look at my right hand, I experience a state of deep relaxing sleepiness... pain does not exist... All I have to do is look at the palm of my hand and all the pain disappears... I feel completely fine.

Dr. Kurt Tepperwein, Secret Techniques of Hypnosis, Godefroy Publications, 1981.

BLAME

I don't expect anything from anybody, and I have no one and nothing to blame.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

Table of contents

BLESSING

May God bless all my undertakings.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I accept the good that comes to me, here and now.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I love so that I see only what is good, give only what is good, and receive only what is good.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I count my blessings.

Og Mandino, The Greatest Secret In The World, A Different World Press, 1979.

I thank God for the gift of life.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

From this moment on I am a complete expression of love and gratitude for God. I realize that there is so much good in my life.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am ready to receive all the blessings of this abundant universe.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am grateful for the blessings I receive daily.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am thankful for everything that happens to me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

BLISS

I feel the happiness and bliss of being alive.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

BLUSHING

My blood is descending into my feet. My feet are getting hot. My feet are burning!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

BODY

I have a body, but I am not my body. My body may be tired or rested, healthy or sick, but that has nothing to do with the real me. My body is a precious instrument which I use to experience and act on the outer world. But it is only an instrument. I treat it well, I try to keep it in good health, but it is not me. I have a body, but I am not my body.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

BOREDOM

Every day I try to overcome my boredom by working on achieving worthwhile goals.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I overcome boredom because I concentrate on the details and nuances of each new situation. Because I'm always interested in learning, I stay interested in my work.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Boredom disappears for good when I observe the vastness of life.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

No matter what happens I will not allow boredom or obstacles on my path to deprive me of my peace of mind.

Orison Swett Marden, The Joy Of Living, J.H. Jeheber Publications.

Table of contents

BOWLING

My bowling style is getting better every day. My approach is supple and relaxed. I release the ball with more and more precision. I am able to control the ball and put the effect I want on it. I can hit strikes with ease. My score is getting better every time I play. Bowling is easy for me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

BRAGGING

I learn to control myself when I am about to brag or try to take advantage of someone.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

BRAVERY (Also see Strength, Courage)

I am in the process of becoming a brave person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

BREAKING UP

I chose to love you. That was then, but now I've changed my mind.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

BREASTS

My breasts are developing... growing... at the same time they are

Table of contents

becoming firmer and firmer... my breasts are becoming beautiful.

My breasts are becoming more beautiful every day... more and more beautiful... firmer and firmer... my breasts are becoming fantastic... I feel them swelling... pushing outward... growing... they grow larger every week.

I see myself with beautiful breasts... pushing against my sweater... attracting men's looks.

My chest will develop more and more... and I'll be proud of my breasts... which are becoming more and more beautiful... more and more attractive.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

BREATHING

My breathing is full, regular and deep; I am developing the habit of correct breathing even when I don't think about it, and I know that it is helping to keep my blood healthy.

Charles Baudouin, Psychology And Practise of Autosuggestion, Idegraph Publications, 1990.

My breathing is regular and calm.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

My breathing is completely calm and regular.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am breathing a little more slowly.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Every day I do deep breathing exercises... to maintain the elasticity of my lungs... increase their capacity... to purify my blood... and give my organism even more vitality.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Table of contents

BRIDGE

I defend myself very well at bridge.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

BUDGET

I allow myself a budget for personal expenses.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

BUSINESS (Also see Money)

All my money comes from God. He has sincerely given me enough to meet all the needs of my business, or if He hasn't given it to me yet, it won't be long in coming. If I need more, He will provide more. Therefore, I don't even want to think about easy ways of making money by taking advantage of others. God gives abundantly, and I'm going to manage this business as if He were always here, close to me.

Robert Collier, Riches At Your Doorstep, S.I.P., 1962

I am becoming a better businessman / woman.

Vernon Howard, Psycho-Pictography, S.I.P., 1965

My business affairs are the affairs of God - they are owned, operated and expanded by divine guidance.

R. Charles Barker, The Science Of Success, Dangles Publications, 1983.

Table of contents

BUYING

I get the coat (house, car, etc.) that I want for a great price. Wearing it (or living in the house, or driving the car, etc.) gives me an enormous amount of pleasure.

Raymond Hull , Wanting Is Power, Les Editions de l'Homme, 1969.

Table of contents

CALM (Also see Self Control)

I feel calm and in control of myself under all circumstances.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I use my resolute calm to combat the threatening attitudes of vain, excitable and impulsive people.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I cultivate calm.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am becoming a calmer, more relaxed person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I feel calm, rested and radiant.
I am becoming calm and balanced.
And as I become calm, I feel peaceful.
I am completely calm and reposed.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I stay calm, no matter what happens!

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

I am calm and am comfortable being who I am.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am calm... calm... calm... calm... calm... calm...

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

Table of contents

I am calm, tranquil, imperturbable.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

I am calm, very calm.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

I am calmer and calmer in all situations.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am imperturbable, calm. I am relaxed and peaceful.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I am completely calm.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

My breathing is calm. My heart is beating peacefully. I am as tranquil as the depths of the sea.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I am cool, calm and collected.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I control myself with the confidence of a master psychologist, and I stay cool under the most difficult circumstances.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

I am cool, calm and lucid no matter how important the person I'm speaking to is.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

CANCER

I now imagine my tissues getting rid of this waste, becoming healthy again, clean and normal. My treatment is a success. I'm in

Table of contents

good health. I'm getting stronger and stronger. I feel better and better. I smile a lot. I see myself as a smiling, happy, active, healthy person. Everything's fine. I am healed.

Now I imagine my cancer being defeated. My cancerous cells retreat, they are beaten, they disappear over the horizon, far, very far away, out of sight. My cancer disappears, melts into the distance, very far away, so far no one can ever find it.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

For me, the word 'incurable' simply means that the illness cannot be cured from the outside, but only from the inside ... Dissolving mental patterns dissolves disease.

Anything can be healed. So, I am realistic, and plan for a miracle!

The doctors are amazed at my total remission.

My body is healing itself totally.

Louis Proto, Self Healing, Piatkus Publications, 1990.

CARDIAC TROUBLE

My heart is beating calmly and regularly.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

CARE

The more I take care of myself, the more others take care of me.

Louis Proto, Self Healing, Piatkus Publications, 1990.

CAREER

God leads me forward in a career filled with success.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Table of contents

I know that I can earn a living in different ways, that I don't have to stick to the same job or even the same career just because I already have a lot of time invested in what I'm doing. I give myself permission to be whoever I want, and get into new areas which may have a bearing on my professional decisions.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I find the ideal job that perfectly fulfils all my needs and desires.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I see every job change or career change as an opportunity to attain my objectives. I have a positive opinion of myself, and I feel good about myself. I am clear, calm, confident, and in control.

I never feel committed to work or a career that isn't totally beneficial.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

CHALLENGE

I look at every day as a challenge; and I try to give it the best shot I have. I start the day by making myself receptive to the outside world, and setting objectives which I try to define very clearly. I then decide what I can do to attain those objectives, and get right to work. I develop the habit of exploiting the opportunities that arise every day in order to attain my goals.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Each victory strengthens me for the next challenge.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

At this moment, even as I express these truths about myself, I know that I can succeed and that I will succeed. If I think about the

Table of contents

challenges awaiting me, whatever they are, I know I can win.

Just look what I can accomplish today! I am incredible... and today is the ideal day to prove it!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am eager to face new challenges!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Challenges are stimulating. I meet each challenge with determination and dynamism, and with the absolute certitude that I will get the best possible results.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

CHANGE (Also see Habit)

It is easy for me to reprogram the computer of my mind. All of life is change, and my mind is ever new.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I have the courage and strength to make the changes that need to be made.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I have the power to change myself the way I want.

Sublipower, Sublicontrol, Edi Inter, 1989.

I stop thinking that I have to change my situation before I can change myself. I change myself, and my situation changes naturally.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I start this day in a new and better way.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I will really begin a new life.

Table of contents

The world will start to become better as soon as I choose to make it better. I won't wait for others to improve the world. I won't wait for my neighbor to improve him or herself. I'll be the one to start.

I can change my own small world, and that's what counts. I choose to believe that I can change it.

If I use my power to choose it is amazing how well things work out for me, even beyond my wildest expectations.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

I can change if I make the necessary effort.

I am going to be different.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I want to change this.

I want to change.

I want something different.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

CHARM (Also see Slimness, Health, Sincerity)

I am a radiant being, full of love and light.

From now on my perfect partner will find me divinely irresistible.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am a warm, sincere, caring and affectionate person. And I see these qualities in others as well.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Other people appreciate me because I try to make them feel good. I'm attractive in many ways. I attract other people, their interest, their enthusiasm, their friendship and their confidence. I bring the best

Table of contents

out in everyone, and that makes me attractive.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

My relations with men and women are more and more harmonious. I'm becoming more charming every day. I am capable of loving and of being loved.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

CHILL

I feel fine, I'm not cold, I'm not going to catch cold.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

CHOICE OF PROFESSION

Before making a choice that will determine the course of my entire existence I will spend weeks - months if necessary - gathering as much information and data as I can find concerning my future profession.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I completely abandon myself to You, my inner Guide. Lead me along the right path, and tell me what the right decision is. Enlighten me as to my vocation so that I can choose the profession that is best suited for me.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986

CIRCULATION (Also see Anemia)

My heart is beating normally and regularly; my circulation is regu-

Table of contents

lar; I know how my heart and circulation are affected by emotions, thoughts and suggestions. Thus I can achieve perfect circulation; if an organ has a tendency to become congested and swollen, it will receive less blood and less nourishment from now on, so that it gradually shrinks back to its normal size. If an organ tends to become anemic it will receive more blood. This, plus the fact that the blood it receives will be of a better quality due to my improved digestion, will make it grow stronger.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

My blood circulates freely, my heart beats calmly and strongly.

Sublipower, Sublihealth, Edi Inter, 1989.

CIRCUMSTANCE

I create my own future circumstances. I change myself today, and tomorrow's circumstances will be as I wish them to be.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

CLARITY

By cleaning and tidying up my physical environment, I clean and enlighten my whole life.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

CLIENTS

The people I call need my products and services.

I can't lose what I don't have. Any prospect I gain is one more than I have now.

Table of contents

I'm widening the base of my contacts.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

COLD (Common)

It's getting better now. It's getting better.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am getting rid of my tendency to catch colds.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am breathing more and more easily now. My nose and sinuses are clearing up completely, and I feel myself breathing well. I feel wonderful. All my respiratory passages are opening.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

My sinuses are perfectly healthy. My head is completely clear, and my eyes are dry.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

COLIC (Biliary or Hepatic)

I am relaxing my biliary passages; the channels are dilating; the stone is moving down into my intestine.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

COMFORT (Feeling At Ease)

I feel completely comfortable when I'm with other people.

Shakti Gawain, Techniques of Creative Visualization, Editions Soleil, 1978.

Table of contents

I feel at ease, sure of myself, and others appreciate me.

Claude Arpel, "I Have Confidence In Myself" - A Subliminal Method, Procauvi Publications, 1986

Every day I appreciate other people more, and find them fascinating. I feel more and more comfortable in the presence of strangers.

Paul-Clement Jagot, Education of the Word, Dangles Press, 1975.

COMMITMENT

I learn to say NO as if it means YES, I am already committed. One of the best ways to relieve stress is to schedule my time so that I can, comfortably, keep my commitments.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I don't commit myself halfway, but all the way in order to attain my objectives.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I honor my commitments.

Sublipower, Sublisuccess, Edi Inter, 1989.

Everything I do involves a price to pay.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

COMMUNICATION
(Also see Confidence, Tension)

It's easier and easier for me to see other people's points of view.

Christian H. Godefroy, Human Relations and Communication: The Subliminal Method, Godefroy Publications, 1987.

I have the right to be open with other people.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Table of contents

I communicate with ease and with joy.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I always communicate clearly and effectively.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The first thing I do is show the respect I have for the other person.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I speak with ease, anywhere and to anyone.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I share my emotions.
I enjoy speaking in public.

Christian H. Godefroy, Human Relations and Communication: The Subliminal Method, Godefroy Publications, 1987.

I always think about saying what I feel.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I am the best judge of my actions, thoughts and feelings, and I am the one who is responsible for their consequences.

In order to develop, learn and evolve I communicate with others about my limitations.

In my search for happiness, it is in my best interests to communicate with others about conditions that promote our mutual well being.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I am in charge of what I say and how I say it. Realizing that nothing is learned while I talk, much of my communication is listening, observing and qualifying. When I communicate I am prepared to deliver a message that offers value and leads to mutual understanding on the part of the receiver.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

There's no mystery about communicating. I know how to listen, and I always listen with a clear and receptive mind.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

People feel at ease with me. People feel good in the presence of someone who radiates relaxation.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

COMPANY

My company is there to serve me, and not vice versa.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

COMPASSION

I will not forget that my compassion can make me free.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I can't offer compassion to others unless I am compassionate with myself. I am not unfair with myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I know that others are equally worthy, equally imperfect. I have compassion for them because they are engaged in the same struggle for survival that I am. Since I know that everyone is doing his or her best, it's easy for me to feel sympathy and compassion for other people.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

COMPETENCE (Also see Money, Skill)

I have confidence in my competence.

Table of contents

I am competent.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I'm always learning something new. I'm happy with the skills I already possess, and try to become even more competent in all my activities.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am becoming the best in my field, and money flows to me as if by magic.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I'm competent, hard-working, and really good at what I do.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am open to learn new things every day, and that gives me the optimism, energy and inspiration to create a future full of success.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I am strong and competent.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

I want to develop my skills to their highest level, and acquire superior competence and ability in my fields of expertise.

Paul Clement Jagot, Power Of The Will, Dangles Press, 1950.

My confidence is growing, and as my confidence grows so does my competence.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

COMPETITION

I have confidence in myself and in my subconscious mind. I can

Table of contents

develop all the skills necessary for me to get ahead of the competition.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I never compare myself to others in order to compete with them, because I can never become someone else, and therefore I cannot attain exactly what someone else attains. But what I can do that no one else can do is to be myself, fulfill my life's tasks, and reach the very summit of my own field of endeavour.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

COMPLEX

I embrace life openly... with no complexes... so that I can partake of the quintessential joy and pleasure of really being alive.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

COMPLEX - INFERIORITY

I have no complexes at all towards people I judge superior to myself.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I am no longer preoccupied with what other people think about me, since I know that all they're doing is wondering what I think about them.

I am totally indifferent to the opinions of others.

I thank my enemies for using their sharp eyes and tongues to point out the weaknesses in my life, and myself.

I thank everyone who has deceived me for making me more vigilant, and for having prevented me from becoming dishonest myself.

Table of contents

I know they probably all enjoyed doing this for me, but that is small payment for the service they provided.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

I know that in certain respects I am superior to many people I am acquainted with.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

The best way not to feel inferior of others is to do something about my inferiority complex. Confidence follows accomplishment. Feeling sorry for myself will never cure me of my shyness. Working hard, making myself useful, doing something for someone else will give me the kind of inner satisfaction that brings with it a feeling of self confidence.

I must not use my sense of inferiority as an alibi for being too lazy to improve myself.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

When I am with another person I never consider myself inferior to that person, not even in my thoughts. I always see myself as an equal. Because my personality is unique, just like his or hers, and I am the only one who can do what I must do.

I don't think about another person's professional or financial standing, but only about the person in whom, like myself, there lives an inner Guide whose role it is to harmonize personal good with the general good, so that I have no reason to fear, but rather sufficient reason to love and see in the other person an accomplice to my evolution.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

COMPLEX - SEXUAL

I let Nature do its work; I let myself get carried away in (sensual)

Table of contents

improvisations which arise spontaneously in my partner or myself, because I know that everything is normal and good about the ways men and women use to express their love for one another.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

I am free to express my sexuality as I choose.

Louis Proto, Self Healing, Piatkus Publications, 1990.

COMPLIMENTS

I always say "Thank you" when I am paid any compliment, by any one, for any reason. Neither do I try to play down or play up value that is bestowed. The ability to accept is the universal mark of an individual with solid self esteem.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

COMPOSURE

I cultivate composure... and stay calm under all circumstances.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I want to acquire constant composure, imperturbable self assurance and confidence that is worthy of who I am.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

COMPREHENSION

I make sure I understand the person I'm talking to correctly by reformulating his or her point of view, and asking if I've summed it up well.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

CONCENTRATION (Also see Delegating)

I am learning to concentrate.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I concentrate all my energies on the challenge at hand, and my actions help me forget about everything else.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I'm in control of my thoughts and my imagination.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I believe I can concentrate. I am going to make concentrating a habit. I am going to reduce distractions to a minimum whenever I am reading or studying. I am going to visualize myself as a person having a good mind, the capacity to listen well, to become interested in everything, to concentrate better and achieve success in life.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I develop and improve my powers of concentration.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I master my powers of concentration perfectly. I can direct my attention and control my thoughts. My mental faculties are getting sharper every day, and I'm always looking for opportunities to make them even better, and to develop and improve my concentration. I practice concentrating my attention and my thoughts, so that I am the master of my own mind.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I concentrate on what I desire and prevent myself from thinking about what I don't want.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Table of contents

I can control my thoughts.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I can concentrate.
I can concentrate better and better.
I have a powerful ability to concentrate.
Nothing can distract me when I concentrate.
I do concentration exercises every day, I do them with pleasure, and they don't tire me out at all.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

I know I'm moving in the right direction; I look ahead, never backwards. Since I am able to concentrate on one thing at a time, I concentrate on the work at hand and finish it!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am calm. I feel good. I feel very good. Nothing can disturb my mind.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

My powers of concentration are improving day by day. I can therefore accomplish all my tasks more rapidly and effectively.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

The power of concentration has no limits, and I use it every time I speak or act.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

My mind does not wander.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

My mind can focus effectively on one thing at a time. The best use of my time and energy is to concentrate on the details of the task at hand and take things one step at a time.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Table of contents

Not now, I'm concentrating on something.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

CONFIDENCE

The answer is Yes!

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I trust in the process of life. I am safe.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I have confidence in — (name the person).

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

([I have a right to be here. I am a person too. I am okay.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

There are no weaknesses in my outlook... I always see the future serenely... with tranquil certitude and confidence.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I leave yesterday behind and search for goals that will liberate my creative abilities.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I will not let this insignificant impression (or event) affect me.

Paul Clement Jagot, Power Of The Will, Dangles Press, 1950.

I can do everything I want.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I can handle it.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

I am capable.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I relax and trust the environment to support me. I place my trust in the Universe which helps me whenever I follow the dictates of my heart.

Louis Proto, Self Healing, Piatkus Publications, 1990.

People like me.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

The Real Me is completely confident, in any situation.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

No person and no thing has power over me.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I do nothing I cannot talk about, and I'm ready to talk about everything I do.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

If I confide in others, others will confide in me.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

CONFIDENCE IN THE FUTURE

My future is bright, healthy, loving, prosperous and SAFE. Being healthy, happy, loved and with no problems feels totally SAFE. My life gets better and better with every day that passes. With every day that passes I feel stronger and more alive. I look forward to the future with confidence and trust.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

CONFIDENCE - SELF (See Self Confidence)

I think about my conflict situations. I try to find solutions. But I also now live joyously, as if my problems were already resolved. I live with this confidence, which never leaves me.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

If I'm in conflict with someone, I imagine that I am both myself and that other person.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

If I have to deal with a delicate or a conflict situation I make sure to create a positive atmosphere of respect for the persons opposing me at the moment.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

From this moment on all the difficulties between —— (name) and myself are erased and our relationship is marvelous.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

CONFORMING

I am infinitely more important than all these rules and social norms which are imposed on us for appearance's sake... talking in a certain way, never leaving the beaten path... that kind of repressive nonsense.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

CONGRATULATIONS

Tonight when I go to bed I will review my accomplishments of the day and reinforce my self image. I will think about them calmly and with pleasure; chances are I will have a very good sleep.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I did my job perfectly today. I'm becoming more efficient every day.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I'm pleased with myself. My work was impeccable.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

CONSENSUS

I always look out for an agreement or some kind of consensus, even if certain things cannot be formulated officially.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

CONSIDERATION (Also see Respect)

I show others my consideration by making myself really available when I'm with someone, and through concrete actions that can help, rather than just empty words and wasted time.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I give myself the consideration and respect I deserve.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I treat myself as well as I would like others to treat me.

Sublipower, Sublicontrol, Edi Inter, 1989.

People see me as a good worthwhile person. Those who fail to see my worth have something on their screen that keeps them from seeing what a good person I am. When people really see me, they see me as a good person.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

Table of contents

CONSTIPATION

From this moment on I will feel the need to go to the bathroom every morning after breakfast... every morning without fail I will feel the need to empty my bowels...

I will feel the need to go to the toilet... at night before going to bed, I will go to the toilet... where all my tensions will be released... my stool is normal... evacuation is easy... all my tension disappears... my digestion is perfect... I'm so happy not to have digestion problems any more.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

Using my own nervous energy I can provoke a bowel movement... I am trying.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Every morning when I get up, or more precisely twenty minutes after breakfast, I have a bowel movement without having to take any medication, or depend on any artificial substances whatsoever.

Emile Coue, Complete Works, Astra Publications, 1976.

CONSTRAINT

I am now ready to give up control. I no longer hurt myself. I am strong, wonderful and free.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

CONTACT

Every person is a link in the golden chain of my own, as well as the universal well being.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

I can choose the people I want to associate with.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I touch others more often.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

CONTRACT

I make sure the contract is mutually profitable, i.e. that the sum of the gains for both parties present is as large as possible.

I also make sure the contract is equitable, i.e. that the sacrifices or losses (and not the gains) are equally spread among the parties present.

I then establish a contract with the other parties which precisely defines "who does what, how, and with what means."

And I always include a clause that allows for renegotiation.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

CONVERSATION

Whenever I'm involved in important or delicate discussions I take careful notes and eventually I offer a summary of the conversation to the other party and ask if he or she agrees with my interpretation.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

CONVICTION

I speak with conviction to everyone, and this influences them.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

Table of contents

COOPERATION (Also see Help)

It is easier and easier for me to receive and give aid and cooperation.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I commit myself to cooperate with others on constructive projects.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I meet my ideal business partner.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

COUGH

I don't cough anymore.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

COURAGE (Also see Dynamism, Resistance, Energy, Enthusiasm, Strength, Bravery)

Today is a magnificent day for courage.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Everything important in life deserves fighting for.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I have the courage to aim higher.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I summon my courage.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I feel courageous, full of energy and enthusiasm.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I feel happy, joyous and courageous.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I try to enjoy everything I do. I feel courageous, energetic and enthusiastic; the things I have to do seem easy. Work distracts me, interests me and attracts me.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.

I take hold of my courage with both hands; it's so easy to abandon everything, and so hard to keep your head held high.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am brave, I am strong, I am courageous.

George Barbarin, How To Overcome Fears And Anxiety, Dangles Press, 1974.

When I work I am supple, relaxed and happy.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Work distracts me, interests me and attracts me.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

The things I have to do seem easy.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

COURTESY

I am honest and sincere with everyone. I treat everyone I meet with courtesy and respect.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

COWARDICE (See Lying, Laziness)

CREATION (Also see Money)

From now on I have the firm intention of creating — (specify what) here and now!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

CREATIVITY (Also see Sensitivity, Love)

In my own unique way, I am a genius.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

My aim is to understand an idea with maximum clarity.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I recognize and approach problems creatively. I view all problems as "situations needing improvement" or as "temporary inconveniences" and "opportunities to grow."

I take time to ride my bike, build sand castles, fly a kite, smell a rose, walk in the woods or walk barefoot in the sand. I explore the wonderful creative world of children (and I'm going to do just that this weekend).

I know that ideas are expendable, and there's always a new and better one. I challenge myself to make them work and get them into practical use.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am becoming more and more creative every day. I realize that the only limits on my creativity are the ones I imposed on myself in the past. I now choose not to limit my creativity any longer.

Table of contents

I'm not afraid of exploring new ground or looking for the best solutions to problems concerning every aspect of my life.

The more I make use of my creativity, the more creative I become. The more creative I am the more successful I am in my undertakings.

I use my creativity to explore the source (of universal energy) from which all ideas spring forth. I ask myself a question, and the answer appears in my mind. I define the problem, and my creative mind indicates a solution.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I never experience "writer's block" when I write a letter or memo.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I step beyond the limits of conventional ideas.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I will always be a part of the living spirit. The creative power of God is in me and acts through me.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am more and more creative and inspired in all areas of my life. I find plenty of ideas and solutions to my problems because I am able to draw from the inexhaustible wealth of my subconscious mind.

I am more and more creative.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I feel more and more inspired every day. I feel more creative in dealing with life situations, full of new and original ideas.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

From this moment on I am an open channel for creative energy.
I am the architect of my life.
From now on I will create my life exactly as I want.
I am an inexhaustible source of creative energy.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I am the creative power in my world.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I am wise. I am intelligent and creative. I accept that a positive mental attitude is an important part of creating my reality.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

My subconscious provides me with answers for everything. I can always look to my subconscious for solutions to problems that arise. Now I feel creative, I feel inspired to get the best out of life, always.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

If I try to get both hot and cold water out of the same tap at the same time, I only end up with water that is lukewarm. If I try to criticize and create at the same time, I can neither criticize objectively, nor create ideas with enthusiasm. I am therefore going to concentrate on creating new ideas, and leave the criticizing for later.

Virginia Godefroy and Thierry de Foichaings, How I Got Rid Of My Money Problems Once And For All, Godefroy Publications, 1985.

If the problem appears to be a new one requiring new solutions, I rely on the creative approach.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I do what is necessary to make each day a creative day.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

CREDIT

I am going to get my loan.
My bank manager will approve the loan.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

Table of contents

CRISIS

It is entirely possible not to suffer the burdens of one crisis after another.

My Real Me can understand and resolve each crisis.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I never fail to take five minutes alone to get hold of myself (during a time of crisis).

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

CRITICISM

I want to judiciously examine all the ideas that come to me spontaneously, that I read about or hear about, before accepting them as valid.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

I do my best. Then I open my old umbrella and walk tranquilly through the storm of criticism, which no longer gets under my skin.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I laugh at critics... at bad reviews... which cannot disturb my serenity... nor destroy my confidence.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I never forget that unjust criticism is often a compliment in disguise. I tell myself that criticism is often just a form of jealousy.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I never talk badly about anybody. I avoid criticizing, and even teasing people. I am only hard on myself. I try to notice other people's qualities in order to imitate them, and the bright side of situations in order to enjoy life.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

Table of contents

I keep a scrupulous account of all my blunders and write my own criticism of each one. Since no one can hope to be perfect, I try to do what a little soap salesman once told me: “I seek out frank, useful and constructive criticism.”

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

Outside criticism doesn’t bother me as long as I stay calm and don’t react negatively. I have criticized others, it’s human nature, but I want to get rid of the habit. In future I won’t judge anyone on appearances. I’ll let my inner Guide be the judge, which means I can accept everything and everyone with benevolence instead of criticism. And this will immunize me against hostile remarks. I’ll take them with a smile, learn what I can and then continue on my way without being affected. My success is the best proof that the path I have chosen is the right one.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I thank my critics for spurring me on to ever greater achievements by offering criticism, which I may have misconstrued as a desire for vengeance, in the past.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

If I had to read all the criticism that is directed at me, never mind answer it all, I’d be better off closing down shop. I do my best with the capabilities I have, and try to see things through to the end. If it turns out that I’m right, then what was said against me is of no importance. And if I’m wrong, well ten angels could swear I’m right and it wouldn’t make any difference.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

CURIOSITY

I experience the world with excitement and curiosity so that every day is a great day for me.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

D

DANGER

In case of danger I don’t panic... I summon all my energy.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

There is a force in me that always makes me stronger than whatever is threatening me. I dominate the situation and come out a winner.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

DEAFNESS

I hear the truth. I know and love the truth. My ears are in tune with God’s perfect plan. That is why my hearing is good. Divine harmony is revealed to me through the perfection of its instruments.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

DEBT (Also see Money, Projects)

I obtain the sum of money I need to finance my project and repay my debts.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

My business is not encumbered with debts, and my cash flow is good.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Table of contents

DECISIONS

I forget about past mistakes; I stop torturing myself about them. Today is a day that will never return; I have to do everything I can to seize good opportunities when they occur.

I will not run around in circles any longer; I will set a direction for myself that will help me attain objectives which are really worthwhile.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I will always choose the correct course of action and accomplish it, because my Guide influences my thinking, inspires my words and directs my actions. With my Guide's help I can solve any problem and make positive decisions. I know what I want. I will succeed. I am succeeding!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I create a hierarchy of my priorities in order to develop clear criteria upon which to base my decisions.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I will not allow anyone to influence my decisions... to make me do what I don't want to do.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I will never make a hasty decision.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I make judicious decisions.

When I learn to think with an open mind, the decisions I have to make on a daily basis become easy and profitable.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I make my decisions at the most opportune time.

I transform my decisions into actions that result in both profit

Table of contents

and satisfaction.

I never go around in circles.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I will be able to define what would please me the most, and thus make decisions. I will feel that my decisions are the right ones. At the same time I will try to improve my life, by continuing with my studies, for example.

Charles de Liguori, Hypnotism, de Vecchi Publications, 1975.

I am certain that I've based my decisions on a solid foundation, one that would benefit both myself and those close to me.

I have no trouble making decisions.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

My subconscious mind guides me towards making the right decisions in all my undertakings.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

When I have an important decision to make I not only try to optimize the quality / price ratio, but also the quality / time-spent ratio.

I try to involve the people close to me in the decisions I make, and try to explain my way of thinking to them.

If I can't decide between two options, I look for new ways to approach the problem.

Before committing myself to a course of action I evaluate the impact my decision will have on the people concerned (and on my eventual public).

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I approve of myself and my decisions are always perfect for me.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Table of contents

DEFEAT

I never talk about defeat.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

DEFEATISM

There is only goodness, and the manifestations of goodness.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I never accept "no" as a satisfactory answer. I say "yes" to victory, I say "yes" to life!

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I never, never accept defeat.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

DEFENCE

I have the courage and strength to defend myself.

Louis Proto, Self Healing, Piatkus Publications, 1990.

DEFIANCE

I become more self confident, and this confidence gives me the certitude that I am capable not only of doing well, but of doing very well, of accomplishing anything I desire, within reason of course, and also of fulfilling my duty.

Emile Coue, Complete Works, Astra Publications, 1976.

Table of contents

I am regaining confidence in myself.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

DELEGATING

I concentrate on what is essential, on where my efforts are profitable, and delegate the rest.

I only do one thing at a time, with variations in what I do.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am learning to organize, to delegate a portion of my powers, to direct and to survey.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I delegate as much as possible.

I know how to make other people work.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I delegate a portion of my reading to subordinates and then tell them to sum up the text orally, or in a memo.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

DEPENDENCE

I am convinced that my whole life depends on my relation with the Creator... I don't rely on people, or on the conditions around me... I rely on the Infinite... on the Eternal.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

Table of contents

DEPRESSION
(Also see Conditioning, Confidence, Happiness, Health, Abundance, Optimism)

Day by day I feel better and better... I feel more and more happy... more and more joyful... I feel completely comfortable with my life.

My self confidence is growing day by day... I feel more and more happy... more and more joyful... I feel absolutely wonderful.

My mind is clear, free of all dark thoughts. I feel joyful and happy.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I try to consider depression as a passing feeling. I don't consider it a permanent part of myself.

I banish my depression.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I start and end each day with a smile. All day long I make a conscious effort to smile and to feel good about myself.

I only allow myself to get carried away by thoughts that can help me attain my most important goals. My thoughts are always clear, constructive and powerful.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I believe that life with all its complications and hardships is worth living. I am going to stop brooding because I'm depressed. I am going to remind myself that depressed spells quite often vanish - that they are transient and that everyone at times experiences the 'blues' or low moods.

If my depression is chronic or too deep-seated, I will contact my physician, have him check me physically, and will let him decide whether I should consult some specialist.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

I am becoming a stronger person.
I am free of the negative conditioning of the past.
I like myself.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I allow my hidden feelings to surface. I study them and sort through them. I keep those I like and reject the others. It's normal to feel depressed from time to time. But then I free myself of these feelings of melancholy. I don't allow myself to become a prisoner. I am free because I am able to reject feelings that make me sad or depressed.

I feel strong, healthy and full of energy. Everything is working out in my life. I am liked by other people. I like what I do. My life is happy and serene. I know what peace is. I feel good about myself. I have confidence in the future.

I don't know what real depression is.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

Although I feel depressed for the moment, I know it won't last. And soon, when I've practiced more, these kinds of feelings won't affect me at all.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1982.

I will not allow myself to miss out on any more of the good things in life. I have no intention of falling back into a stupid feeling of depression which I know only too well.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am abundance.

I am becoming a stronger and stronger person. I have confidence in life and I'm recovering my sense of joy. May this feeling of joy stay with me. I feel more and more happy. The current of life flows through me, bringing me an abundance of love and happiness.

I congratulate myself for handling the affair so well. And in fu-

Table of contents

ture I will always handle myself just as well. I'm in great shape, and I'm completely positive. I'm in a very good mood. I congratulate myself.

Every day, and in all aspects, I am becoming stronger, more confident, happier and healthier.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am relaxed, calm and happy. Everything is fine. I feel good. I await the future with confidence. Everything is fine, everything is calm.

Even if the weather is bad at the moment I know it won't last, and besides the weather isn't important.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am happy, confident and strong.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I want my perceptions of things to be just as positive, and my feelings just as pleasant as they are negative and demoralizing when I'm depressed.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

Everything is going well, really well.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

DERMATOSIS

My blood is pure. My skin is beautiful.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

DESIRE

Table of contents

I have desires, but I am not my desires. My desires are transitory and sometimes contradictory. Attraction alternates with repulsion. There are desires in me, but they are not me.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

I now have enough time, energy, wisdom and money to realize all my desires.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I know that by applying the principles of autosuggestion, any desire that I choose to go after will soon materialize, first through external signs, and then as the attainment of the goal itself.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

The power of Infinite Understanding is at work in my consciousness and will realize all the desires in my heart.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Now I very much want what I desire. Now I have the strength, energy and courage to be myself.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

If I really desire something I can obtain it.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

DESIRE - SEXUAL (See Sexual Desire)

DESTINY

Thus, day by day I write my own destiny; for inexorably I become what I do.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

I have the power to create the life I wish for.

Sublipower, Sublicontrol, Edi Inter, 1989.

I can create my life with my thoughts.
I am responsible for everything that happens to me.
Change my thoughts, and I change my life.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I can orient my thoughts accordingly and, this done, and by using the greatest power I have - the power of choice - I am indirectly in a position to control circumstances.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

I am the Master of my Destiny, I am the Captain of my Soul.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I am the master of circumstances.

Sublipower, Subliconfidence, Edi Inter, 1989.

Only I can decide what my destiny will be. I must do what I want to do, despite the obstacles.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Above all I want, I want with all my strength, all the power lying dormant within me. I want to build a beautiful destiny.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

DETERMINATION (Also see Energy)

It is only by being relentless that I will succeed. I will therefore not be stingy with my efforts...

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I keep my head high. I look like the winner I am, and I act and think like a winner. Every time a problem starts wearing me down, I act immediately. I straighten up and attack my problems, and I solve them. Frustration and failure only make me stronger, more positive, better organized and more determined than ever!

I can imagine myself attaining my goals. I'm becoming more positive every day, and I'm more committed than ever!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I will never fail if my determination to succeed is strong enough.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I never let myself stray from the path I have chosen, nor allow anything or anyone to influence me in any way.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I can do what I please if I have enough determination and energy.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I have great determination. I know that nothing can stop me except myself. That's why I never stop moving forward.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I know that determination is the ultimate ingredient of all success, and I have a lot of it.

I am resolute, able to make decisions, constant, persevering and committed.

Each day I see how determined I am to attain all the goals I have established for myself, concerning both work and my personal life.

And because I accept and respect myself, I know that I really do deserve to be a winner in life. And that gives me the determination I need to be a winner, every day, in the most positive and beneficial sense of the word.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

I want to do the right thing at the right time, despite any obstacles or warnings which may try to prevent me.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

If I work assiduously enough and for long enough to attain what I believe in, I will make the dream a reality.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I don't act with precipitation, but with determination.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I want to decide my own course of action and adhere inflexibly to the resolutions and decision I have made after proper deliberation.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

DIALOG

I always let other people express themselves freely and completely. I am attentive and reassuring when other people talk to me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

DIET (Also see Hygiene, Negative Habits)

At each meal I eat half as much as usual.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

From now on I will no longer eat between meals.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I like to eat the foods that are part of my diet. They are quite enough for me.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Table of contents

Now I no longer want to eat what I crave at any given moment.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My diet is doing me a world of good. I'm losing a pound and a half every week.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

DIFFERENCE

Please forgive me. I don't ask you to approve of what I did, or agree with me, but I do ask you to forgive me. I want to put our differences in the past, wipe the slate clean, and start fresh.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

DIFFICULT TASKS

This job looks so big that I'm avoiding doing anything. I'm going to break it down into smaller, manageable tasks and then get started on the first step.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

This task was destined for me. I can do it.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

DIFFICULTY (Also see Worry)

This is a tough situation. I'll have to dig deeper. Now is the time to really use my professional skills. I welcome the chance to test myself.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Table of contents

Each difficulty is a challenge which I accept.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

I succeed in dominating all difficulties that arise.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1982.

The Spirit in me knows, the Spirit in me can.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

When a difficulty arises I don't ask, "Who's to blame?" Instead I ask, "What's to be done?"

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Whatever happens I will react as calmly and intelligently as possible.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

DIGESTION (Also see Appetite, Stool)

I have a good appetite, I eat calmly, and I digest my food perfectly normally.

Professor Kurt Tepperwein, The Powers Of The Will, Godefroy Publications, 1989.

I feel no more pain, I have no weakness, my digestion is good, my circulation is very regular, all my bodily functions are normal.

Henry Durville, Course In Hypnosis and Suggestion, Durville Publications, 1938.

I transform the sunlight warming my skin into energy which I send to my lazy stomach to help it digest properly.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

My digestion and metabolism are functioning well. Every day at mealtime I tell myself that I am feeling very hungry; I eat with pleasure, but also with moderation; I get into the habit of chewing my food well so that digesting is easier. I also know how sensitive my stomach and intestines are to emotions and to cerebral activity, and therefore to suggestion. Thus I can make my stomach and intestines function normally through the power of suggestion. If I digest properly I will assimilate my food properly as well. This means my organism will be nourished as it should be. And finally, my bowel movements are completely normal.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

My digestion is fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I digest food freely and easily.

Sublipower, Sublirelax, Edi Inter, 1989.

My stomach is ready to do its work harmoniously. I'm happy to sit down at the table since the meals I eat will be perfectly assimilated by my body.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

My stomach is functioning normally again. It has all the energy it needs to do its work and assimilate all the foods I eat. I am now digesting more and more easily. I assimilate foods with ease. My digestion takes place normally and easily, and I am relaxed and in good spirits.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Since my digestion is good I will also assimilate foods well; my body will benefit from all the foods I give it, using the nourishment to create blood, muscles, strength, energy - in short, life - so that each day I get stronger and more vigorous.

Emile Coue, Complete Works, Astra Publications, 1976.

Since I digest well, my intestinal functions are also normal. Every

Table of contents

morning when I get up I feel the need to have a bowel movement, and without having to use any kind of medication or artificial stimulus whatsoever I perform the function normally and to my complete satisfaction.

Emile Coue, Complete Works, Astra Publications, 1976.

DIGNITY

I stop debasing myself.
I never neglect my human dignity.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I will by worthy of respect, confidence and esteem. I want to set a noble example. I will therefore overcome any faults I have, in order to live up to this esteem.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I am worthy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

DIPLOMA

I will make sure to finish my program of studies since I want to obtain my —— (specify which) diploma.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I am a successful person. There is no way I won't get my doctoral degree (or any other diploma - specify which). I am certain to succeed, because I know my success is already a part of the order of things. A new and fascinating life is opening up for me.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

Table of contents

DIRECTING OTHERS

I know how to be encouraging and understanding. I incite others to do their best and to fulfil themselves. I always seek out and find the best in the people who work for me, and instruct them in a positive way. Since I expect the best from others, I always get it. I assume complete responsibility for my person. And when I exercise my directorial functions, I let others assume their responsibilities as well.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

DISAGREEMENT (Also see Feud)

Tomorrow ——— (add name) will announce that s/he has changed his / her mind.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I don’t feel insulted by people who disagree with me.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

If, by chance, our opinions happen to coincide, all the better. If they don’t, we can’t do anything about it.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

My willpower is strong; I will calmly refrain from arguing.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1982.

DISAPPOINTMENT

I try to laugh at my little failures and disappointments.

I try to see the funny side of things. I tell myself that it’s not the end of the world, and that things will work out better next time. I

Table of contents

overcome my disappointments by not making mountains out of molehills.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

I'm disappointed with the results I'm getting so far. I'd better find out as much as I can about what is going wrong in this situation so I can improve it or at least get feedback to help me perform better in the future.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

DISAPPROVAL

When faced with someone's disapproval I react automatically by using sentences beginning with "you." I let anyone who is trying to make me feel guilty know that I am quite capable of surviving their disapproval.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

DISCIPLINE (Also see Laziness, Disorder)

I am teaching myself to be disciplined, and to listen with deference and goodwill to the people in charge of my education.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.¥

DISCOMFORT

It won't be long before I feel better.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

Table of contents

DISCOURAGEMENT

I will not let the hesitations and errors caused by my inexperience discourage me. I can always learn something very important.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

DISCUSSION

At the end of a discussion I make sure everyone involved has understood each other.

At the end of a discussion I specify the conclusions I have drawn, and ask the other parties to do the same.

I define, along with the other persons, the goals of the discussion and the points to be covered.

I make sure I am completely available for the entire duration of the discussions.

I try to terminate a discussion within the allotted time, even when I am talking to long-winded persons.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

When a difficult moment in a discussion arises I try to concentrate on what I like or appreciate about the other person(s).

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

DISOBEDIENCE

I am becoming more obedient and reasonable.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

DISORDER (Also see Discipline, Laziness)

All areas of my life are becoming more and more orderly. I am becoming a disciplined and orderly person. I am more and more enthusiastic and I enjoy my work. I take pleasure in accomplishing all my day to day activities. I have all the energy I need to do what I have to do. Every morning I wake up overflowing with energy, and I attack the day with determination and discipline.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am learning to organize my mind and my time more effectively, and to relax and free myself of worries about all kinds of things that are out of my control.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

DISSATISFACTION

When I am dissatisfied I ask myself what I would like to be doing at that moment, and then I try to do it.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

DISTRACTION

I am going to keep myself busy and utilize my leisure time to advantage. I will always find something to do that will give me a lift, like seeing a good movie, reading an interesting book, listening to music or anything that will help me relax and make me forget my troubles.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

DISTRESS

My inner Guide always advises me correctly, and shows me the right path to take. My Guide will rescue me from distress. S/He has the answers to all the questions that are tormenting me. S/He dissolves all my doubts. I have complete confidence in my Guide, and I know S/He is advising and assisting me at this very moment.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

DOUBT (Also see Self Confidence)

Here we are, with no doubts whatsoever.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

DREAMS (Also see Fear of the Unknown)

I let myself dream. I tell myself that I can have everything I want. With no taboos or prohibitions. That I have all the money I need to live out my fantasies for a period of fifteen days. I see that almost all my fantasies are realizable, that I don't desire the moon but simply things that I can obtain on condition that I get rid of my fear of the unknown and make the effort to stretch out my hand.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I want to remember one of my dreams, I can remember one of my dreams, and tomorrow morning I will have a clear recollection of that dream.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

Tonight, as on all nights, I am going to live a new adventure, and tomorrow I will remember all of it!

Pierre Fluchaire, The Dream Revolution, Dangles Press, 1985.

Table of contents

My dreams are becoming concrete reality more easily every day.

Sublipower, Sublisuccess, Edi Inter, 1989.

I have peaceful dreams, and my mind is at rest.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I can modify my dreams when I want to.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

I can (I want to) remain conscious when I dream.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

When I have a clear and lucid dream I feel perfectly rested.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

DRIVING

I always stay calm when I'm driving. All my tension and nervousness disappears. I think before I react.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I am a competent driver. I pass my test easily and effortlessly. Driving gives me pleasure. I find it easy and fun.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

DRUG ADDICTION

I feel more and more detached from my real life... I am free of my negative, annoying thoughts... Nothing is important... I abandon myself to this feeling of deliverance.

Everything around me becomes clear, clean and more and more beautiful... Colors and music blend into pleasant images... I abandon

Table of contents

myself to the sounds and colors... nothing can disturb me.

I am indifferent to the noises from outside... I concentrate on myself... I am in a state which is much higher than any drug can take me... I can enter this state whenever I like... and be free of all worries, problems and negative influences.

No drug can do this for me... I don't need —— (specify the drug) which is ruining my health... and my health is improving every day.

I have confidence in my destiny, which I control through my desires... but nothing will make me go back to taking drugs... I don't see the point anymore.

Drugs disgust me... nothing on earth could make me start taking drugs again... if I feel the need to shut out reality, I will do some self hypnosis or meditation... things which regenerate my entire organism.

I do a few minutes of meditation every day... I concentrate on my future... I am overflowing with strength and energy... the solution to my problems becomes clearer every day... and I'm doing more and more to attain my goals.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I'm proud of myself and my success.
People like me when I'm not on drugs.
I'm healthy when I'm not on drugs.
I work much more efficiently when I'm not on drugs.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

DRUGS

I will not forget that tobacco, coffee and alcohol are drugs. i.e. means of stimulating my body. They can be positive, but there is also a risk of becoming dependent.

Table of contents

I avoid using one drug to compensate for the effects of another (for example drinking coffee when I've had too much alcohol).

I change my habits from time to time, especially those concerning drugs, to determine if I'm addicted or not.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

DUTY

I will do today's duty today.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

DYNAMISM (Mental - Also see Ambition, Enthusiasm, Vitality)

When I'm in the alpha state I condition my mind to become more open to the suggestions and directives I give it. I feel better every time I practice my alphagenic exercises.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

From this moment on I will always be ready and alert, strong and conscious of my goals. Nothing can distract me from attaining my objectives. I am untiring, opinionated and persevering. I take more and more pleasure in the joy of creation.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

From this moment on I am positive and I am going to keep moving forward!

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

I am a super dynamic person.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

Table of contents

DYSFUNCTION (Organ)

Generally speaking, if I have one or a number of organs which are defective to a greater or lesser degree, I tell myself that these organs are starting to function better and better, so that they gradually return to normal and I am completely healed.

Emile Coue, Complete Works, Astra Publications, 1976.

My mind is in command. All my organs obey my mind.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I make sure all my organs are functioning well; my heart beats normally and my blood circulates as it should; my lungs are working well; my stomach, intestines, liver, bladder and kidneys all perform their functions normally. If one of these organs happens to be malfunctioning at the moment, the problem will diminish day by day, so that in the very near future it will disappear completely, and the organ will resume its normal function.

Emile Coue, Complete Works, Astra Publications, 1976.

DYSPEPSIA

I send my stomach the order to contract.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

EASE

It’s easier for me to do what is good for me.

Sublipower, Sublicontrol, Edi Inter, 1989.

I master X technique (specify) easily and pleasantly.

Raymond Hull, Wanting Is Power, Les Editions de l’Homme, 1969.

ECONOMIZING

I never spend my money stupidly. I know the value of wise spending. All my financial decisions are based on the principles of economy and moderation.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

ECZEMA (Also see Acne, Urticaria)

From now on I will stop thinking about my eczema, and think about my intestines instead; I have to get rid of the toxins that are being eliminated through my skin through the mucous membrane of my large intestine instead. As soon as I start doing this my eczema will disappear.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

I am a healthy person, pure and perfect; my skin is healthy, and I am healed.

My skin is perfect.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

My skin is becoming normal, my eczema is disappearing and my skin is becoming smooth, beautiful to the touch, and perfectly normal.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

EDUCATION

As a father of six children I know from experience that the greatest gifts a parent can give their children (and that managers can give their employees) are roots and wings. Roots of responsibility and wings of independence.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

It is my responsibility to teach my child, by example, what real love is and how to work out his problems intelligently, instead of emotionally, how he can live with the greatest amount of happiness in this society of ours.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I never resort to exaggerated threats or warnings which are forgotten in any case. I stick to my word.

I tend to give large or small rewards on all kinds of occasions.

For me each day is an opportunity to show, by setting an example, what the best way to live is.

I teach the values I believe in by setting a good example.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

I understand the difference between punishment, discipline and teaching, and I always try to consider these elements from their proper perspective.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

My children are my greatest joy. Their noisy games are a sign of their minds' vitality and vivacity. My spouse brings life into the home, and merits all my love. We smile at each other a lot and understand each other better each day.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

First, I am able to recognize my children's unique abilities and talents - to reinforce them, nurture them and help them recognize what is special about themselves.

Second, I am able to understand their behavior in the context of who they are - I don't misinterpret natural shyness as being unfriendly, or a need for privacy as rejection. Seen in context, even negative behavior is more understandable and predictable.

Third, seeing my children accurately helps me focus on changing only the behavior that is important to change - behavior that's harmful to them, behavior that isolates them socially, or behavior that is disruptive to the family.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

EFFICIENCY

Every day I am improving, I'm improving more and more in all ways.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I give the best of me in everything.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

I am efficient in everything I do.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I use my time well. I do everything I have to do quickly and passionately.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I concentrate my time and energies on the 20% of my activities, contacts and concepts that have proven most productive to me in the past.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I do my best.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I do my work as well as possible, and I am no more incompetent than anyone else.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I always do my best according to my awareness at the moment.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I remind myself to only do one thing at a time.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am an organized and efficient person. I am mastering the art of doing more in less time.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I'm doing my job better. My performance is improving.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Table of contents

EFFORT

Master of my body, master of my thoughts, I want my effort to also be others' salvation.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Every effort also constitutes an investment.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

EGOISM

Attaining an objective implies sharing it with other people, and thus I move from isolation to happiness.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

By developing a love of humanity in myself I eliminate all hate, envy, jealousy, all egoism and all cynicism from my heart, because I know that harboring a negative attitude towards others can only result in disappointment.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

ELIMINATION (Bowel Movement)

I will assure better elimination of my body waste.

J.V. Cerney, Stay Younger, Live Longer Through The Magic Of Mental Self-Conditioning,
Parker Publishing Company Inc., 1968.

ELOCUTION

Every one of my words is spoken deliberately, fluently, and pro-

Table of contents

nounced clearly.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I have all the tools I need for perfect elocution.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I dare speak out.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I pronounce my words strongly, clearly and fluidly.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I am determined to make my words become influential and dominating.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I'm going to think carefully before saying anything - being mindful of the effect my words may have on others. I am going to avoid being sarcastic, learn to become more diplomatic and develop the art of friendly and interesting conversation. I am going to be less argumentative. If I learn to control the impulse to say the wrong thing in haste, I will become a better person, one who will be loved and respected.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I make sure I have the language, with enough vocabulary and sufficiently varied examples, to best adapt what I'm saying to the person or people listening to me.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I'm becoming much more articulate and effective in my use of language.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

My elocution is becoming clear, harmonious and supple.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

EMOTION

Today I will be the master of my emotions.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I have emotions, but I am not my emotions. These emotions are innumerable, changing, often conflicting, yet I always remain myself, through hope and despair, joy and pain, irritation and calm. I can observe, understand and judge my emotions; I can master them and channel them and use them in better and better ways. I have emotions, but I am not my emotions.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

I dominate my emotions.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I am able to control my emotions.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

When a problem arises I avoid becoming emotional. I Stay Calm.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

EMOTION - NEGATIVE
(Also see Fear, Anxiety, Nervousness)

I cease being the victim of negative emotions. I realize that they have absolutely no power over me.

I know I am on the path towards dissolving all my negative emotions when I begin to consider what they really are.

I become my best friend by trying to understand my negative emotions.

The power of self awareness allows me to reject negative emo-

Table of contents

tions whenever they try to influence me.

I destroy unhealthy thoughts and harmful emotions as soon as I start becoming aware of them.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am able to control my emotions perfectly in all situations. I am gaining complete mastery of my reactions. I am more and more positive and fulfilled in all situations.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am going to keep my negative emotions under control.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

EMOTIONAL SCARS

I erase the scars of my negative feelings.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

EMPHYSEMA (Also see Asthma Attacks)

I am calm, I am breathing, my lungs are relaxing, my kidneys are opening.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

ENCOURAGEMENT

I play a role in the lives of all the people I get close to. By treating someone like the person they should be, I offer a powerful encouragement for them to become that person.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

Table of contents

ENDURANCE (Also see Dynamism, Courage)

Since I take good care of myself I have a lot of energy, endurance and vitality.
I now have more energy and endurance than I did before.
I love life, and I'm happy to be alive.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I have more and more endurance... more and more strength... I get stronger every day... I can make progress... and become stronger.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I know that success isn't due to chance. Real and durable success requires a sum of intellectual and moral qualities. The principal physical quality is endurance. I must be healthy. Therefore I want to live in a healthy way.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I possess dynamism, courage and endurance. I have a very positive attitude towards myself and towards everything I do. I am practical and realistic, but I also believe in getting the best possible results from any situation.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I have more and more endurance, more and more strength.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I have more endurance than X (specify).

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

Table of contents

ENERGY (Also see Courage, Determination, Strength, Vitality, Health)

Each day I accumulate new energy in my solar plexus region.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

I have energy.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I inhale and I am inspired. I exhale and energy flows through me.

Christian H. Godefroy, The Seven Eternal Laws of Success, Godefroy Publications, 1980.

I am overflowing with more and more energy and strength.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I will destroy the negative images my enemies have tried to inject into my mind, and replace them with joyful images that encourage me and increase my energy.

Orison Swett Marden, The Joy Of Living, J.H. Jeheber Publications.

I feel very good today! I have more energy than ever.

I can do great things. And every task I accomplish gives me even more energy!

I have a lot of energy, which I nourish with my curiosity and enthusiasm.

I have more and more energy every day. I am full of life, in great shape, and in an exceptionally good mood.

When I do something that requires a surplus of energy I call on my reserves and find that I always have more than I need.

Every day I am becoming more and more aware of my energy and vitality. I create an unlimited reserve of energy in myself.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I do not waste my emotional energy.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

I feel the life force flowing through my body.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I am in excellent health, overflowing with energy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I am bursting with energy.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

Energy flows freely through my body.

Sublipower, Sublirelax, Edi Inter, 1989.

My breathing is getting deeper and energy is circulating freely through my body.

Sublipower, Sublihealth, Edi Inter, 1989.

My most powerful energy for creating my life is present in me at this moment.

My energy is stimulated by my breathing, by love, and by life-giving thoughts and words.

I am bursting with energy and light.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

To be energetic I act energetically!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Every day and from all points of view I am more and more energetic.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I feel great! I'm full of energy! I'm so strong, I'm always going to feel healthy!

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I balance my energy.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I'm in good physical condition.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

I'm in great shape.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

ENERGY - CREATIVE

I am overflowing with divine light and creative energy.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

ENERGY - VITAL

I absorb the energy scattered throughout the atmosphere, and store it in me. I exhale air, but I retain the energy which is carried into my body by the air I breathe, and which I make my own.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1982.

ENJOYMENT

I relish each golden day.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

All the obstacles to my total expression in life and my complete enjoyment of existence are now dissolved.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

ENLIGHTENED MIND

My mind is clear, alert and ready to meet any challenge.

Table of contents

I enthusiastically wait for opportunities to put my mind to the test and improve it. Instead of considering problems as difficulties to avoid, I see them as opportunities to sharpen my mental faculties.

I am awake and fully conscious. My senses are sharp, my mind is clear. I am aware of everything around me, and I am in control of my life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Divine light and divine love are flowing through me.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

ENTERITIS

If I am suffering from enteritis I imagine the enteritis is clearing up; the intestinal inflammation is gradually disappearing, and the phlegm and other secretions are becoming less and less abundant until they disappear and I am completely cured.

Emile Coue, Complete Works, Astra Publications, 1976.

ENTERPRISING SPIRIT

The search for the best in myself is my greatest enterprise. It is a creative adventure, because it leads me towards self acceptance.

With an enterprising spirit I can combat all negative feelings which belittle me and destroy my true identity.

With an enterprising spirit I increase the power of my personality as I find new horizons, and fully accept what I have already discovered.

With an enterprising spirit I progress towards a world of pure dynamic energy.

My enterprising spirit is the creative effort I make to resolve the

Table of contents

enigma which is in me, to try and understand my complexities and problems in order to overcome them.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

ENTHUSIASM (Also see Ambition, Dynamism, Vitality, Energy, Courage)

Today is the first day of the rest of my life.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Thunder and lightning! Life electrifies me!

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am naturally enthusiastic.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am enthusiastic about my goals; I develop this quality which is so essential to my success.

I apply myself with gusto to creative endeavors. I understand that life can be enjoyable and fun.

Every day I see myself in top form.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I have an iron will... nothing can discourage me... on the contrary, problems only give me more energy... the energy I need to overcome them... nothing can stifle my enthusiasm... absolutely nothing.

I cultivate my enthusiasm... my passion for everything I do.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I give myself a chance to become spontaneously enthusiastic about what I'm doing.

I am enthusiastic about everything I choose to undertake.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

Table of contents

I stimulate my enthusiasm by maintaining a high level of interest. The more my activities interest me, the more enthusiastic I am. The more enthusiastic I am, the more energy I have.

I regularly program my mind with positive instructions designed to keep me in shape, full of youthful enthusiasm.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am enthusiastic about life and filled with energy and enthusiasm.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Life interests me.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

My day starts when I wake up in the morning and shake off the numbness of sleep, overcome my negative impulses and promise to make this day exciting.

I will not spend my day doing nothing; I have exciting goals and I'm full of enthusiasm.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am enthusiastic about my life.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

Oh, this is a great day for getting out there and conquering the world!

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

To be enthusiastic I act enthusiastically!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Every day, in all ways, I am becoming more and more enthusiastic.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Table of contents

ENURESIS (Bedwetting)

From now on I will stop wetting my bed, and I won't get angry when I have to go to bed. My bed won't be wet when I wake up in the morning.

I like going to bed at night.

If I have to go to the bathroom at night I get up and use the toilet. As soon as I get back into bed I fall asleep and my bed stays dry.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

From now on I will have a very strong desire to overcome this shameful habit, which is really a feeling of inferiority. A moment will come when my desire to control my bedwetting will be stronger than anything else.

I can now control myself much better than before.

Every night before falling asleep I order myself to wake up as soon as I feel the need to go to the bathroom. If It happens I will wake up.

I can control myself. I will not wet my bed. I am capable of controlling my bladder no matter what. Even if bedwetting has some hidden meaning for me, even if I want to be obstinate, I can still overcome my enuresis.

And even if I have a relapse, it doesn't mean anything. I will look for the cause of the relapse. I no longer suffer from enuresis. I can control it, and I will succeed in controlling it.

Charles de Liguori, Hypnotism, de Vecchi Publications, 1975.

I always call my mummy, and my bed is always clean.

Emile Coue, Complete Works, Astra Publications, 1976.

I always ask my mummy when I have to go to the toilet, and I always stay clean when I sleep. It's easy for me to stay dry and clean the whole night long.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

I can restrain myself all night long and my bed is always clean and dry.

Emile Coue, Complete Works, Astra Publications, 1976.

I am a pretty little girl and people like me a lot. Everyone likes me because I'm so likable, so happy and gay. People like me because I only sleep in a clean, dry bed. I always sleep in a warm, dry bed. If I have to go to the bathroom, I always wake up in time.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

My bed is clean and dry, and I always wake up when I have to.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

If I concentrate on what I feel as I urinate during the day, I will feel the same sensation at night when I'm asleep, and after I've gone to the bathroom I'll get back in bed and fall asleep instantly.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

ENVY

This is so wonderful! I rejoice in that person's prosperity, and wish him/her more and more good fortune.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

EQUILIBRIUM (See Balance)

EQUANIMITY

I maintain my tranquillity and equanimity.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

ERRORS (See Mistakes)

ESTEEM (Also see Self Esteem)

I accord myself this elementary form of respect. I do not deny who I am. I'm worth more than that. I am in no way obliged to lead a monotonous existence.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I esteem myself. I know I am a good person.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

I never belittle myself to myself.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

EVOLUTION

I am a directly linked representative of the ever-evolving, ever-expanding consciousness of the Creator. I am spirit expressing through a physical structure. I am patient with myself.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

EVOLVING

I have the right to develop, to learn and to evolve.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

EXAMS

(Say this to yourself on the night before an exam): I will not waste

Table of contents

a single minute more on this stupid activity, and I really don't care if I pass or not.

Dr. Maxwell Maltz, Psychocybernetics, Godefroy Publications, 1978.

From now on I always concentrate only on what I'm doing, and any noises only serve to reinforce my concentration.

I prepare very carefully for all my exams.

I am calm and relaxed. I can always remember what I learned when I need to, and therefore all my answers are clear and precise.

I channel all my attention towards my goal.

My marks are improving daily.

I am in complete control in all situations, and I attain the goals I set for myself within their prescribed time limits.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

I study hard. I am certain to be ready on exam day.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I will pass my exam.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am going to pass the exam. I am calm and my mind is clear.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I am secure in the knowledge that I have prepared well for my exam. My thorough revision is now paying off. Everything I have revised is ready in my mind to be recalled easily and effortlessly during the exam.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

EXCHANGE

I like to give and I like to receive.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I give and I receive.

Sublipower, Sublisuccess, Edi Inter, 1989.

EXCUSES

Once and for all, and from this moment on, I will get rid of these excuses.

I will not excuse myself all the time, especially when I'm really not sorry for what I said or did.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I can decide not to start acting in such and such a way again, I can realize that I'm wrong to adopt such and such a behavior, but excusing myself all the time is a sickness which makes me feel responsible for the emotions of others.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

EXERCISE (Also see Obesity, Nutrition)

I have to exercise every day so that I won't get sick... and stay in top shape.

By exercising every day... never missing a single day... even if only for a few minutes if I'm pressed for time... I will live at least ten healthy years longer.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

Every time I exercise I have a better opinion of myself. I'm really proud of the extraordinary work I'm accomplishing.

I always get the exercise I need. I don't stop until I have attained my objective, every time I exercise.

I never force myself too much or hurt myself physically or other-

Table of contents

wise. I do exactly the amount of exercise I need.

I couldn't live without exercise. It helps keep my healthy. It makes me alert, makes me feel better, and allows me to give the best of myself!

I set objectives for myself and then I achieve them. I'm on a regular exercise program, I eat healthy food and I get enough sleep. I spend a part of each day staying in shape.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I like doing exercise.
I feel like moving, walking...

Sublipower, Sublihealth, Edi Inter, 1989.

I can't wait to do some exercise today.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I will do a moderate amount of exercise every day, and I'll have fun doing it.

J.V. Cerney, Stay Younger, Live Longer Through The Magic Of Mental Self-Conditioning, Parker Publishing Company Inc., 1968.

I am going to engage in some form of moderate daily exercise.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Any amount of exercise (running, jumping rope, aerobic dancing, bicycle riding, etc.) gets my mind and body working much better. Exercise makes joy!

Exercising brings me joy.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

EXPERIENCE

I have learned from my experiences, even if sometimes they were

Table of contents

painful.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I listen for the secret messages hidden in my experiences. I let these help me develop positive and useful habits.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

To get into a specialty I first have to learn the basics.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

EXPRESSING ONESELF (See Self Expression)

Table of contents

FAILURE

From this moment on I will very calmly devote all my energy to finding ways likely to reduce the impact of the consequences which I have already mentally accepted.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

This is NOT a catastrophe! This is not horrible, humiliating, or the end of the world! It's inconvenient. I'm disappointed. Now I'm going to learn something and start again. So let's get going!

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I am learning that failure, no matter how serious, can be a trampoline to success and not a chopping block.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

At least once a week I review my goals and find out what I truly want now. I am willing to risk giving up all I have been for what I can become.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I'll do better next time.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I transform failure into success.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Next time I will succeed.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Table of contents

FAILURE (In School)

I can, therefore I must. I could have avoided this mistake, I should have been able to avoid it. I could have learned the lesson better and more quickly, so I should have done it. I could have done better, so I should have.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.

FAITH (Also see Fear)

Belief helps me follow the way.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I have faith, faith in my ideas, in my destiny, and faith in God.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I am free of all fear, I am firm in my faith.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Faith is invincible.
I believe, I really believe.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Well directed faith adds amazing power to all of my thoughts.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

FALSE BELIEFS

I never let my convictions trap me into passivity. Becoming attached to a belief based on past experience is like trying to escape reality. Only the present exists, and what is true in the present may

Table of contents

not necessarily be true of the past. I do not base my behavior on what I believe but on what is, what I experience in the present. By opening myself to the present experience instead of clouding reality with my beliefs, I realize that the unknown is a vast and fascinating domain.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I am ready to clear up any beliefs that hold me back from the good I want in life.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

FAMILY LIFE

My professional life and my family life are mutually enriching.

My family life is rich and creative.

I am there for my loved ones, giving them both time and my full attention.

My family understands and appreciates my professional activities.

I don’t feel guilty about being absent from home when I work.

I make sure that my family life plays an important role in my balance as a human being and my personal fulfillment.

I always make a note of any meetings with my spouse or children in my agenda, in the same way that I keep track of meetings with my boss, or clients.

I ask myself if there is anything positive in my family life that can also be applied to my professional life (and vice versa).

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

FASCINATION

Others find me fascinating and terrific.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

FATIGUE

I like my work, but I also make sure to take time out to have fun: in this way I rarely feel tired.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I am not in the least tired.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

I am never lazy... physically or mentally.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I'm in great shape.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

The sensations of fatigue and weakness that I sometimes feel will gradually disappear and be replaced by sensations of strength and vigor which will become stronger every day.

Emile Coue, Complete Works, Astra Publications, 1976.

FAULTS

Every day I am going to improve and eventually I will succeed in eliminating the faults I have discovered in myself.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

I accept the helpful criticism of my friends, and I use self hypnosis to purge myself of whatever personality shortcomings I possess.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I accept my weaknesses and my faults so that I feel all right even when I fail.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I use my faults as inspiration to motivate me to improve and save more time.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

FEAR (Also see Emotional Paralysis, Anxiety, Nervousness, Guilt, Rejection)

I confront my fears with a positive state of mind and positive behavior.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I do what frightens me.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I have nothing to fear, the Spirit in me is watching, I have everything to hope for.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I fear nothing since my faith in the Mystery is great.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I know that the love of goodness fills my soul and dissolves all fears. I now live in the joyous expectation of goodness.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Simply because I am aware of it, and because I abhor it, because I absolutely don't want this to happen - it will not happen!

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

Nothing can harm me since I am united with my inner Guide!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

The Real Me knows no fear.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

No matter what threatens me I will face up to it and meet the challenge!

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

If I find myself in a situation that frightens me, for example, I think about something that will calm me down.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

What cannot defeat me only makes me stronger.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Every day I overcome my fears, worries and any other destructive thoughts.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

[To overcome fear I use my mind.]

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I confront my fears and I accept them.

Sublipower, Sublicontrol, Edi Inter, 1989.

I free myself of my fear of what other people think.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Only I can free myself from my fears. I start by becoming aware of what I fear, and stop myself whenever I find that I'm thinking or talking about it. I become aware of the 'fear-talk' around me, and stop listening to it.

I specify my fears. As long as they remain unclear they continue to have power over me.

I ask myself what the worst that could happen is. Not only is the worst hardly likely to occur, the answers often make me laugh!

I don't suppress fear. I feel it, talk about it objectively.

I am as safe as I allow myself to be. Only good comes to me. I

Table of contents

have nothing to fear.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I allow myself to be, without the need to prove myself to anyone. I live my power without fear of defeat or rejection. I control my dreams, my life.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am not afraid of being afraid.
Knowing myself helps free me from fear.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I reject useless fears.
I understand my fears and I can explain them rationally.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I smile and my fears evaporate. I am strong. I am powerful. I have confidence in myself.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I am calm and relaxed.

Fears may come and go, but it doesn't matter; I can control them as long as I stay relaxed.

When I can control my thoughts, I can control my fears.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I am inviolable, I am invulnerable.

George Barbarin, How To Overcome Fears And Anxiety, Dangles Press, 1974.

The Eternal is my refuge, and I make the Highest of the high my home.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

The Real Me cannot be afraid of anyone.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

FEAR OF ANIMALS

From now on I am no longer afraid of —— (name the animal). I find them tranquil, calm animals. When I see them I identify as much as possible with them.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I love all animals.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

FEAR OF DEATH

I meditate on death every day in order to give my life more meaning.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

FEAR OF ELEVATORS

I have no trouble taking the elevator. I now feel perfectly relaxed whenever I enter an elevator. I am able to control my reactions and emotions completely. I am able to master the situation completely, remaining calm and relaxed.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

FEAR OF EXAMS (Also see Stagefright)

I know I can pass my exam. I know the material perfectly. I'm ready. I have no reason to worry.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

FEAR OF FAILURE (Also see Disapproval)

I'm making a common mistake. I'm thinking of failure as the enemy of success. But it isn't at all. Failure is a teacher - a harsh one perhaps, but the best. I can be discouraged by failure - or I can learn from it.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I remind myself that fear of failure is really often a fear of disapproval or ridicule, and I tell myself that everyone has a right to their own opinion, but that other people's opinions don't concern me.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I do not fear failure. I am responsible for my actions. I acquire the necessary knowledge and skills to succeed, and I move forward.

I am never afraid to try.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

FEAR OF FLYING

I like airplanes, I am fascinated by them, they are a wonderful way to travel, and I am fortunate to be living in an age where this mode of travel is available to me. I am sharing the benefits of modern progress with many thousands of other people.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

FEAR OF REALITY

I remind myself that nothing human is foreign to me. I can be what I choose to be. I engrave this sentence in my mind, and I recall this aphorism every time I fall into the familiar habit of trying to es-

Table of contents

cape reality.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

FEAR OF REJECTION

It’s better to ask for what I wish to obtain and get “no” for an answer than never to ask for anything, and never get anything.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

FEAR OF THE DARK

From now on I am no longer afraid of the dark. Nothing changes when it gets dark. There is no reason to be afraid. On the contrary, I know that darkness is my friend because it helps me rest.

The darkness is my friend, it helps me get a good night’s rest.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body’s Natural Defenses, Godefroy Publications, 1989.

FEAR OF THE FUTURE

Starting today I am no longer afraid of the future. I feel strong. I am in control of my destiny. I have absolutely no reason to be afraid. The future belongs to me. I am happy, loved and respected.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body’s Natural Defences, Godefroy Publications, 1989.

(From now on only beautiful things will happen in my life.

I rejoice at the thought of the beautiful moments I am going to experience.)

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am very happy... I feel good about who I am... I look confidently

Table of contents

into the future... and I know: my destiny is full of wonderful events.

Day by day, in all ways, things are getting better.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

Life is for me.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Guide me, celestial light, guide me on the right path; I don't ask to see what the distant future holds in store for me. Just the next step is enough.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

FEAR OF THE OPPOSITE SEX

I feel better and better in my relations with the opposite sex. I feel more and more comfortable with men / women. My relationships are harmonious. I am completely at ease, and men / women find me attractive. I am more and more confident and sure of myself with men / women.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

FEAR OF THE UNKNOWN

If I really believe in myself, everything is possible. The totality of human experience is at my disposal from the moment I decide to adventure into unknown territory, without asking for guarantees of any kind. Just because it's different, and I'll have fun doing it.

If I see myself shrinking back from the unknown, I ask myself: "What is the most terrible thing that can happen?"

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

FEAR OF VEGETABLES

From now on I am no longer afraid of — (name the vegetable). I know I am stronger. I see them as friends. They are beautiful plants, basking in the same sunshine as we do. We share the planet with them.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

FEAR OF WATER

From now on I am no longer afraid of water. I know there is nothing to fear because water is an element of nature. I am confident, I am happy, I feel good in the water.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses , Godefroy Publications, 1989.

FEELINGS

To attain emotional maturity each of us must learn to develop two critical capacities: the ability to live with uncertainty and the ability to delay immediate gratification in favor of long range goals.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I accept all my feelings as forming a part of myself.

From now on I will try to live all my feelings.

It's good to express my feelings, and from now on I will allow myself to do so.

I like myself when I express my feelings.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have the right to express my feelings.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Table of contents

I am in control of my feelings.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I can assume responsibility for my own feelings.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I can control my feelings.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I know how to communicate my feelings to other people. I understand them and they understand me. I am not afraid of approaching people and telling them what I feel.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

If there's no feeling in it I don't want it any more.

Louis Proto, Self Healing, Piatkus Publications, 1990.

FEELINGS - NEGATIVE

I refuse to allow images of disaster and of a terrible future to take root in my mind and dominate my personality with feelings of failure.

I refuse to allow distorted, rambling thoughts to occupy any space in my mind.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Trying to rise above my negative feelings means that I am making progress.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

FEELINGS - POSITIVE

I am working to continue my past successes and create entirely

Table of contents

new ones. As a constructive observer of the mind, I make sure my feelings of success are constantly growing in my imagination.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

FERMENTATION (Intestinal)

Under my hand my intestine is contracting and pushing the gas upwards.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

FEUDING

I want my problems with —— (name the person) to stop.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

To cut the thread of my negative thoughts towards someone I cut the knot attached to my own mind.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Your inner Guide is allied with my own. Together they can bring us peace. I understand you, and you understand me. Our inner Guide is our only guide.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

FEVER

My temperature is going down.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

FIBROMA

The contractions of my uterine muscles strangle the blood vessels which nourish my fibroma; lacking blood, it atrophies and disappears.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

FIGHTING SPIRIT

I know that I have the fighting spirit to attain my objectives; that means I try, and when I try I succeed. If I fail I try again.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I develop the habit of reacting positively and with a fighting spirit to threats and problems. I do this by adopting a positive, fighting attitude towards all day to day problems, as well as the problems in my mind.

Dr. Maxwell Maltz, Psychocybernetics, Godefroy Publications, 1978.

FILING

I equip myself with the necessary material (office furniture) to set up an efficient filing system.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

FINANCE

I find it easy to organize my finances.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

[I attain my financial objectives.]

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My finances are prospering more every day.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

FIRMNESS

I can achieve goals in this situation with firmness. I don't need to be this angry. I can assert myself and be firm without being so angry or demanding.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I have the right to say no to someone without losing that person's love or respect.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am learning to say no.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I never cave in to pressures or demands imposed by others... except if I have personal reasons for doing so.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I know how to say 'No' without being aggressive or timid.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I want to maintain a firm and dignified attitude, without becoming arrogant or cynical, without violence and without fear.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Other people can say 'No' to me without my being affected.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

Table of contents

FLAB

I am aware of the weight I've put on around the waist and stomach... my waist is going to get a little smaller every day... and my kidneys will purge my body of fat.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

FORCE OF NATURE

No force of nature is bad - it all depends on how it is used.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

FOREIGN LANGUAGES

Studying this language gives me more pleasure every day... I await each class with impatience. I concentrate exclusively on learning this new language... nothing can distract me. Every new word I learn is engraved forever in my subconscious... I don't forget anything that I've learned.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I learn the —— (specify) language easily. My memory absorbs new words more and more easily. I understand the language better and better, and I'm also speaking much more fluently. My memory for this new language is improving day by day. Learning —— is easy for me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

FORGIVENESS (Also see Resentment)

It is over, I can forgive myself.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

Every night I forgive all my enemies for everything.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I forgive my father with a sincere heart. He acted as he thought best. I accept what he did. I wish him peace, joy and harmony. I am sincere. I say what I think.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I forgive all those who have offended me.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I forgive others, they are only human. I forgive myself, I'm human also. If I harbor resentment I may be able to hurt other people, but I am sure to hurt myself with the poison my resentment builds up in me. A person who can't forgive is not really alive.

When I forgive others I take a giant step towards maximum relaxation; and when I forgive myself, I attain it.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I forgive —— (name the persons who offended you). I will radiate love, peace, benevolence and all good things under heaven towards them. They are free and I am free. I know I am free of them because I can think about them without any pain, but rather with a gentle feeling of peace and a blessing that springs from my heart.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I am willing to forgive anyone who ever hurt me, and wish them well.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

I fully and freely forgive you. I loose you and let you go. I do not wish to hurt you. I am free and you are free and all is well again between us. I feel love toward you and I glory in your success, prosperity and complete good.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I now forgive you and liberate you all.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I may not be able to overcome my human weakness and actually love my enemies, but for the sake of my own health and happiness I forgive them and forget about them.

Please open your heart to me. Understand, accept and forgive.

I wish this hadn't happened, but I was trying to meet my needs.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

FORESIGHT

I never undertake something without having a contingency solution, just in case.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I consider what I will do in case of success as well as in case of momentary failure.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

FORTUNE

My happiness? My fortune? They are within me.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

FOUNTAIN OF YOUTH

I feel and think as if I had a magic charm, as if I were much younger than I am. I NEVER consider myself older than twenty-eight to thirty-five years old.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

FRANKNESS (Candor)

I am always frank about everything I do. I never lie out of self interest, negligence or even for amusement. Everything my conscience finds reprehensible I refrain from doing.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.

I force myself to play the game frankly and openly.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

If I realize I've made a mistake I admit it; I try to learn from the experience in order to change my line of action.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

FRATERNITY

My activities and my life, in fact my entire being finds meaning in the spirit of human generosity and fraternity with all people.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

FREEDOM

I am not resistant to new truths. They can free me. I am not bound

Table of contents

to a sad past except by my own mental chains. I break them apart. I can be totally free of negative feelings linked to the past. And this freedom makes everything in the present seem fresh and new.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I plan ahead and free my energy in order to benefit others. I breath in goodness, which liberates me.

I breath the desire to give into my heart, instead of just taking all the time, and I feel free and full of power.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I know that there are infinite forces at work within me. I want to free them, and make them grow constantly.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

(I am limitless. I know no boundaries as I live unconditional love and creativity. I recognize my true identity.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I use my power to choose wisely.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I choose what happens in my life instead of leaving things to chance.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am now at peace with my past. It’s finished, and I am free!

From now on I will forgive everyone whom I come in contact with. We are all happy and free. I don’t have to try and please others. I am worthy of being loved and appreciated, whatever I do!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am free to act as I wish.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

Table of contents

I am free to live in any way I choose.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I want to be free; free of myself as well as of others.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

When my mind is really free I won't be imprisoned by my emotions. A man who is freed from prison doesn't have to think about freedom or imprisonment any longer.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

In harmony with the whole universe I find my individual freedom.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

FREE TIME

I never miss an opportunity to do nothing, and give myself the time to do so regularly.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

FRIENDSHIP

I need friends, I need to be surrounded with people who will help me as I help them.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I like others and I like myself. I find it easy to make new friends.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

I create close links of friendship around me, in which the principle attractions are not problems or needs, but values and goals.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

I cultivate friendships which are important to me. I allow myself to have confidential relationships with certain people.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I keep making new friends.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I make friends easily, and I have a lot of respect for them. My friends can count on me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I only have friends.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I never neglect my friendship with others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am funny and adorable, and I have some very, very good friends.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am surrounded by friends.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Publications, 1982.

I appeal to You, my Inner Guide, to give me the power to radiate love and sympathy all around me, so that I can attract others to me. Help me find those with whom I can forge real and lasting friendships. Let these people cross my path, and help us recognize immediately that we are on the same wavelength, that we belong to each other. I thank You for your help and guidance.

K.O. Schmidt, Success At Your Doorstep, Astra Publications, 1986.

FRIGIDITY

I have gained a better understanding of my problem. I know that

Table of contents

I am not really frigid, that I am a warm person and that the sex act is an expression of love.

I am not frigid and I can achieve an orgasm.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I love my body and I have the right to be sexually satisfied. I find it easier and easier to have an orgasm. I love orgasms, and abandon myself completely, with complete confidence. I am becoming a sexually fulfilled woman, vibrant with sensuality. I find it easy to attain orgasm, and to satisfy my partner. I love my body, and my partner's body, and I am becoming a more and more desirable woman.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I like my body and I like myself. I reach orgasm with ease. I awaken my partner's desire and I know how to satisfy him. I am a sensual woman and I can abandon myself to my desire.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am a normal woman who functions normally.

I can be perfectly relaxed and enjoy a sexual encounter.

I know that having an orgasm is completely normal.

I am a healthy woman; I relax completely and open myself to my partner.

I accept my orgasm without forcing it or wanting it too much.

I am convinced that making love is a beautiful and pleasant experience.

I see myself as a woman who can always have an orgasm.

My body and mind are free of past sexual failures.

I am a woman, a feminine being, and I love to make love with my companion.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Table of contents

FRUGALITY

Whether I'm out or at home I enjoy eating small portions.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I found health by living in moderation and eating frugally, simply in order to assure my survival.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I like leaving the table still feeling a little hungry.

Sublipower, Sublihealth, Edi Inter, 1989.

I will only eat healthy foods, and never to excess.

J.V. Cerney, Stay Younger, Live Longer Through The Magic Of Mental Self-Conditioning, Parker Publishing Company Inc., 1968.

When I sit down to eat I always tell myself: "I live better when I eat less."

I like eating less. Although I am always well nourished, I really like eating small portions and staying a bit hungry.

I never eat more than I should. I know how much food I need, and I'm proud of myself because I eat well, I am reasonable, and I've never looked better!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

FRUSTRATION

I stop brooding about the best way to do things and simply start doing them.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I remind myself that frustration is a waste of time.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I can always reap an advantage of some kind from a negative experience. I no longer react to frustration as I did at one time, for I know that I can profit from whatever happens, good or bad, in one way or another.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

FULFILLMENT

I am burning to discover the best part of myself, that confident, companionable and responsible person I sometimes am. I avidly search for occasions to fulfill myself and refuse to get frustrated and boxed into a dead end.

I never neglect the responsibility I have to myself to open the doors of my real personality and live my life to the fullest.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

[I am excited to be alive. I am glad to be here. I am a bright shiny star that glows every day and night.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

In future everything I say will tend to magnify my life. I want to live a noble and full life, spreading good to those around me, in an atmosphere of clarity and serene joy.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I want to live fully.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I feel fulfilled.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

Table of contents

FUTURE

I try to be as conscious and as positive as possible when making decisions that affect my life and my future.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

This is a great opportunity. I am constructive and positive, and I am starting to work on my future.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

Table of contents

GAMBLING (Games Of Chance)

I am incredibly smart. I know which (card, horse, number, etc.) is going to win.
Win, win, win.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I never play.
NEVER.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

GASTRITIS (Inflammatory)

Blood flows into my stomach and intestines, repairing my mucous membranes, which are red and inflamed; my white blood cells close up the sores, and my mucous membrane is healed.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

GENEROSITY

[I am gentle and generous with the people I like.]

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am a generous and loving person.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

Table of contents

The more I share my possessions the more is given to me in return.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

GIFTS (Talents)

Every day I develop the gifts that have been bestowed upon me. I cultivate them assiduously, and with more and more noticeable success. Once again I let my inner Guide act through and for me. His will is my own.

I am united with my inner Guide. It activates my inner aptitudes, especially my gift for.... (specify). Every day this gift gets stronger.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

GOALS (Aims)

Every time I want to do something or change something about my life I write it down, I develop a plan for attaining my goal, and set myself a deadline. In this way all my goals are transformed into action.

Whenever I want to change something about myself, or get something in life, I set myself a goal, I write it down, I read it over every day, and I take the necessary steps to attain my objectives.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I find my goals and decide now to go after them (intense desire makes things happen!).

I write my goals down. (Writing goals has magic. I have a plan, rather than a wish or daydream. Writing is a commitment).

I read my goals every day (I reinforce my commitment, and in-

Table of contents

spire action).

I visualize myself reaching my goal (just after awakening and just before falling asleep).

I make an affirmation for my goal and affirm myself. (Affirmations are the fuel for motion. I affirm my objective(s) many times each day. I keep building my confidence. I repeat each day's words aloud 10 times, 3 times daily).

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I will not waste my strength on idle pleasure or useless work. All my actions will lead towards my goal.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I don't get all worried about results. I take pleasure in the journey towards my goal. I know exactly what I want.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I always set new and higher goals once the old ones have been attained.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I know what I want.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I know I am capable of attaining the goal I set for myself; therefore I demand continued and indefatigable action from myself, directed towards my goal.

I have a clear written description of the precise goals I set for myself, and I will not stop trying to attain them.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

I am strong. I am courageous. I pursue my choices with focus and confidence.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

Table of contents

Once I set goals for myself, I find it easy to attain them.

Sublipower, Subli Success, Edi Inter, 1989.

My desires lead to positive goals which direct my life.

Sublipower, Subli Success, Edi Inter, 1989.

My prayers are powerful, and I know they will help me attain my goal.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

One of the keys to my success is knowing precisely what I want to do.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

GOLF

My golf swing is improving day by day. I hit the ball with power and precision, no matter what the situation. My swing is becoming elegant and effective. I hit my irons as well as my woods. And I'm doing very well with my putter too. Golf is becoming easy for me. My score is improving all the time.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

GOOD HUMOR

At the center of every human being there lives an inner Guide. May my Guide awaken and transform the sullen side of my personality into a friendly, joyous and harmonious disposition.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I try to maintain my good humor and enthusiasm.
Every morning I try to wake up in a good mood, ready for action!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

GOODNESS

I try to see the good in others, but first I look for what is good in myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I put my best self out there.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am good.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

If I want to find happiness I have to stop thinking about the gratitude or ingratitude of others, and give solely for the joy of giving.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

If man is good, the world is good.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

GRATITUDE

I now give thanks for all the good things I have and all that is still to come.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

If I want my children to be grateful I have to show them how myself, by being grateful to others.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I give thanks for having been allowed to discover the divine aspect of my mind and body, and for the help I received in settling my business affairs and personal relations.

Now I give thanks for this life full of health, wealth, happiness,

Table of contents

and perfect self expression.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

GREED

I have more material wealth than I need, because I am not greedy and desire only what I can use constructively in my life. It took a lot of effort to get where I am, and I have always observed the laws of nature by developing positive habits to which I adhere.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

GRIEF (Also see Forgiveness)

I free myself of my grief, and the incessant flow of negative thoughts.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

GRIEVANCES

I agree to let bygones be bygones, and bury my grievances in the past.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

GROWTH

I'm open to new ideas. The best in me surges forward, never stopping, never ending, filling me with joy and freedom. That is the law of growth working within me, leading me towards what is good.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Table of contents

My world is opening and expanding.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

GROWTH - PHYSICAL

I have a good appetite, I am digesting my food better, my lungs are getting stronger, I'm becoming robust, and developing normally.

Emile Coue, Complete Works, Astra Publications, 1976.

GUILT (Also see Fear, Rejection)

Feeling guilty won't change the past and won't make me a better person.

I tell myself that the past can never be changed, no matter how unpleasant it may be. What's done is done. I can feel as guilty as I like, but that won't change anything.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I have the right not to feel responsible for other people's feelings.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I stop feeling needlessly guilty. I try to find the reason for a mistake, without blaming myself.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I give myself the right to make mistakes.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I pardon and absolve myself of all guilt, here, now and forever!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I forgive all those who tried to make me feel guilty about sex and

Table of contents

my body.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I thank God every day for what life brings me. I an thankful for my luck and for my joys, and also for the obstacles and deceptions. I ask forgiveness for my prejudices against others, and thus free myself of guilt.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Everybody makes mistakes, it's only human.

I accept the consequences of my actions without embarrassing myself by blaming myself for past errors.

However bad a decision I made, it doesn't matter. I accept myself as a person who, like everyone else, is just trying to survive.

I can learn from my mistakes without guilt or worry.

I am not responsible for others.

Everyone's awareness is different, so comparisons are worthless.

Matthew McKay & Patrick Fanning, Self Esteem, New Harbinger Publications, 1990.

I shake off all my erroneous thoughts, as well as those of the people around me. My mind is perfectly clear and free.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

H

HABIT

I reject my negative habits, those which don’t do me any good; I cultivate my positive habits, those which work to help me.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I know that habits can be changed. I have already altered old habits and acquired new ones, whether in sales, bowling, or thinking. I have done it (1) when I became aware of the habit; (2) when I became convinced it was blocking me from reaching my goals; (3) when I worked at substituting a new, more useful habit.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I am completely free of this habit. Harmony and peace of mind reign over me.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

HABITS - NEGATIVE (Also see Diet, Habit, Hygiene)

No negative habit can dominate or influence me. I am in control of myself and my actions. I always do what is best for me and for my future.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I have decided not to have any unhealthy habits.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

I do not identify with undesirable habits. They are only acquired traits, and are not part of my real Self.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am free of this habit, I have peace of mind.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

My bad habits disappear easily and are replaced by positive ones, especially concerning my diet and hygiene. And this naturally contributes to improving my general state of physical health.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

It is easy for me to replace one habit with another.

Sublipower, Sublicontrol, Edi Inter, 1989.

HABITS - POSITIVE

I will develop good habits and become their slave.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I have good working and living habits.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am going to develop habits that are going to make me think better and feel better.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

HAIR

I can improve the condition of my hair... help it grow back... through mental action... I feel my hair revitalizing... getting stronger and more vigorous every day.

I’m not afraid my hair will fall out... losing my hair is no longer a

Table of contents

problem... because I know I can keep my hair.

I think about caring for my hair every day... helping to give it strength and vitality.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

HAIR LOSS

I'm not at all worried about going bald one day... I know I will keep my hair... I don't think about losing it any more... on the contrary I'm certain I have the power to keep my hair... I am free of the fear of losing my hair... I actually feel it getting stronger and thicker.... growing more and more...

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

HALITOSIS

My breath smells fresh.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

HANDICAP

I can be greater than anything that happens to me.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

HAPPINESS
(Also see Love of Self, Confidence, Intimacy)

None of my past sufferings, nothing unpleasant or tragic that

Table of contents

happened to me will enter my mind. I will only allow positive thoughts, thoughts of joy and of the friends with whom I shared happy times, thoughts of peace and success, to enter my mind today.

I will not allow anything to disturb my happiness: I have the right not only to exist today, but to really live.

I don’t want to be unhappy today, whatever happens. I want to live and rejoice to the fullest on this day. I won’t let anything make me angry.

Orison Swett Marden, The Joy Of Living, J.H. Jeheber Publications.

Today is the best day ever.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

God wants me to be happy.

The happier I am, the happier the people around me are.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I assert my permanent good health, my happiness, the perfect creative expression of myself.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I have the right to be happy. I work on getting better at being happy.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I have the right to try to be as happy as possible as long as I respect others.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I always have what I need to be happy here and now.

I am rich, I feel good about myself, I am happy.

I do, however, also accept responsibility for trying to make the world an oasis of happiness and abundance for everyone.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I believe that happiness comes from the ability to enjoy life and an unselfish desire to comfort and help others.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I make an effort to be happy.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I deserve to be happy, healthy and wealthy. My mind's natural state is happiness.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am immersed in happiness.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I think of happiness as a state of inner freedom.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I know how to savor each instant of happiness. I live intensely, in the present moment.

Christian Godefroy, 1987.

I will be happy.

Og Mandino, The Greatest Secret In The World, Different World Press, 1979.

I am happy to be alive and to be building my success.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

The spirit in me is the artisan of my happiness.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

My mind and my soul are a haven of happiness, joy and confidence.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

To be happy I make others happy!
I have found happiness by helping others find it.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Table of contents

For me, true happiness never comes alone...

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

HARMONY

I accept the divine balance between male and female. I experience this male / female relationship with love and understanding. I allow this relationship to expand and strengthen me every day.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am in perfect harmony with the universe.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

HARMONY - CONJUGAL

Each day I shall remind myself to be less sensitive. Love frustrations are often the result of over sensitivity. We all know couples who truly love each other, yet constantly bicker over trivialities, each oversensitive and on the defensive. Their love is like a duet, played on a discordant note.

I must give my wife companionship.

I must not expect my wife to conform to my way of thinking about everything.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I like being married and I take advantage of the numerous benefits it offers.

My marriage is a success because I do my part. I don't take my success for granted, and I make a conscious effort to make my marriage a success, and help it grow.

My marriage is proof of the effectiveness of teamwork. I am never

Table of contents

alone in life, because I am part of a loving, attentive and successful team.

I respect my marriage and my partner, and I always try to resolve our differences in as positive a way as possible.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I begin and end each day with a declaration of love for my spouse, and during the day, if possible, I devote three minutes of telephone time just to chat with him / her and express my love.

I'm a good listener. I care about my spouse's life, about the thousand and one details and little incidents that occur every day. I remind myself that things done out of duty may be done well, but things done out of love are done with grace. I see how something begun as a duty can be transformed into a work of love. It's actually amazing how fascinating the 'little things' in life can be.

I do not force my spouse to compete with the children for my attention. I make sure to spend time alone with my spouse.

When we disagree about something I think that it is possible to have different opinions without arguing. However, we never go to sleep before resolving our differences.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I know and believe that there is a man out there who will love and take care of me. I also know that I can contribute to his happiness and peace. He will accept me the way I am. He won't want to re-educate me, and I don't want to be re-educated. It won't be necessary, because our relationship will be based on love, freedom and mutual respect.

I can picture very clearly the qualities I'd like to see in my husband. I think about these qualities, so that they also become my own.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am you and you are me. We are one, nothing can separate us.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Every day our relationship is becoming more and more harmonious. We are happy to live together, we compliment each other and our love for each other is growing.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

We always solve our differences with understanding and consideration.

I respect the unique character of my spouse. I admire the numerous qualities in her / him which makes this relationship unique.

I am honest and sincere, and I express my thoughts and opinions openly, while taking what my partner has to say into account.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Our relationship is going very well.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

HARMONY - FAMILIAL

(I invest in the well being of my children. And I must make my wife feel like a woman and not a mother substitute.)

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

HARVEST

I ask God to bless each furrow of ploughed earth. Every seed that is put into the seeder is blessed, and I have a clear image in my mind of the abundant harvest that will come later, God willing.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Table of contents

HATE (Also see Love)

Whenever I feel an impulse of hate or anger arising in me I replace it with a loving thought and act as if I feel love instead of aversion.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I celebrate a general amnesty, freeing all those who have hurt me. I wish them all peace, health and happiness, and send them my blessings.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

HEALING

My healing powers are developing and getting stronger.

Sublipower, Sublihealth, Edi Inter, 1989.

What the mind causes the mind can cure.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

My thoughts are becoming more positive every day, healing me, assuring my success and bringing me happiness.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I love my body. I have the power to heal myself.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I believe and know that divine love is in the process of healing me.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I direct all the energy in me towards God and His powers of healing. And the seed of this attitude sprouts and grows in the fertile soil

Table of contents

of my subconscious mind.

I know that the infinite power of healing is healing me right now. It can heal me despite any logical proofs to the contrary. I feel it, I believe it, and I'm ready to attain my objective, which is my complete recovery.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I will recover.

Emile Coue, Complete Works, Astra Publications, 1976.

I rejoice in this new body and give thanks.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am getting better.
I want to get better.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.¥

The love of God saturates my entire being. The peace that comes from God fills my soul, and I give thanks for the marvelous healing that is taking place in me at this very moment.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

The power of my subconscious heals my body and makes it perfectly healthy.
I have the power to heal myself.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

The doctors are amazed at my progress.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My state if health is improving.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

If one of my organs is functioning badly the natural power of healing will work on curing the anomaly day by day.

Table of contents

My healing powers are strong and protect me against all disease.

Sublipower, Sublihealth, Edi Inter, 1989.

The power of suggestion accompanied by effective treatment will assure my recovery.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Every day, and in all ways, I am feeling better and better.

Emile Coue, Complete Works, Astra Publications, 1976.

Everything is fine.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

HEALTH - GENERAL (Also see Beauty, Vitality, Confidence, Happiness, Looking Good, Slimness, Charm, Balance, Harmony, Self Expression, Peace, Success, Prosperity, Love of Life, Energy)

As my essential functions of digestion, circulation, breathing and sleep get better and better, so does my general health.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

From today on I will develop my body and mind. I will remain in good health. I am solid and strong because I have decided to be so.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Calm and relaxed, I regain my strength and health.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Every cell of my body breathes harmony and health. My whole body radiates health. I feel wonderful. I'm in great shape. The way I

Table of contents

look and move expresses health and harmony. I radiate well being.

Every day my positive thoughts keep me healthy. My thoughts create harmony in my body and in my relations with people. These harmonious thoughts give me strength and health.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

Every day I get more beautiful and healthy!

Everything I do promotes my health and beauty.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The prototype of my body in all its perfection can be found in my subconscious mind.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I can feel my body more healthy now. I visualize, think and speak well of my health. I use positive self-talk on a regular basis.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am acquiring good health. I make sure to keep all the parts of my body healthy.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I have an increasingly positive mental attitude in a perfectly healthy body.

I am constantly creating positive images and thoughts which keep me healthy and in top shape.

Christian Godefroy, Mental Dynamics Seminar, 1978.

I listen to my inner voice which always tells me the truth about my physical condition. I always listen to its warnings and advice.

My mind takes good care of me. By giving it clear inner instructions, I consciously condition it to keep my body bursting with health, energy and vitality. My mind always obeys my commands.

I am very healthy, but I don't take my health for granted. I am proud of the efforts I make to stay healthy.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I use the power of my mind to control my thoughts, and keep my body and mind healthy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I will consult my dentist and physician for periodic checkups. I am going to devote a portion of each day to improving my health.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

(I feel good, I look good, I am good.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

I feel very healthy! I feel happy! I am in great shape!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

(I am a friend to my body. I always let my body guide me in perfect equilibrium. I have confidence in my body.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I feel good.
I am in perfect health.

George Barbarin, How To Overcome Fears And Anxiety, Dangles Press, 1974.

I feel fine... I'm healthy... I have confidence in my subconscious... which watches over me and keeps my sympathetic nervous system in balance... my sympathetic nervous system which regulates all my bodily functions... and which keeps me in perfect health...

Nothing can affect me... nothing can harm me... my health can withstand anything... my vital forces are inexhaustible... I am in perfect health... in great shape.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Table of contents

I am now in perfect health.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I am very healthy. God is my health.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I will always live with a positive frame of mind, and that will keep my body healthy.

Day by day my health is improving.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

My body's natural state is exuberant health! I see myself perfectly healthy, radiant and strong. I focus on health.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

The idea of perfect health now fills my mind.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

Every cell, every tissue of my body is regaining its health and harmony.

My health is improving day by day, I am glowing with health. My strength is growing and my health is improving daily.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

The life of God penetrates every fiber of my being. I AM well and whole in every part of my body. I am composed of billions of cells all containing intelligent life, and this intelligence guides me towards health, happiness and prosperity.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

My body is my friend.

The power of life is in me and regenerates me.

Sublipower, Sublihealth, Edi Inter, 1989.

My body is perfect.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

Table of contents

Everything about me is an affirmation of balance and health.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

HEART

I feel each heart beat. My heart is strong. It is doing its work perfectly. I can count on it. It is strong, healthy and vigorous. It is beating regularly, calmly. It is strong.

My heart is vigorous. The blood it circulates is pure.

My cardiovascular system is purified. My arteries are free of all obstructions. My arteries are healthy. I feel good. I feel fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

My heartbeat is slow and regular.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My heart is beating slowly and regularly.

My heart is beating regularly, calmly, and strongly. It is working completely normally.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

My heart is strong again, and functioning normally.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My heart is getting stronger and stronger, more and more calm, more and more rested. It is beating slowly and regularly, easily sending fresh blood full of oxygen to all parts of my body. My heart is getting stronger day by day, becoming more and more calm and powerful.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

My heart feels fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

I'm feeling better and better.
My heart is beating normally and regularly.
My heart is perfectly calm.
My heart is perfectly healthy.
My heart is doing fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

HEART ATTACK (See Tachycardia)

HELP (Also see Cooperation)

God is with me, God helps me, He cannot abandon me.

Marcel Baugin, Hypnotism, Suggestion and Telepsychic Phenomena, Scientific Distribution, 1956.

I accept the help others give me.

Subli Power, Sublicontrol, Edi Inter, 1989.

I have the courage to ask for help.

Shakti Gawain, Reflections In The Light, New world Library, 1978.

I make use of everything that can or could help me.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I am supported by life.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

May God give me the patience to accept what I cannot change, the courage to change what I can, and the wisdom to know the difference.

W. Clement Stone & Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978

Everybody loves me and supports me wherever I go.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

HESITATION

As soon as I decide something... I do it, after having considered all the advantages... I do it right away... enthusiastically... and I resolutely eliminate all doubt and hesitation from my mind.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

HINDRANCES

I now get rid of all the feelings of guilt, fear, resentment, disappointment and hate I may have accumulated. I am free of all hindrances!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I free myself of the hindrances that are no longer useful.

SubliPower, SubliControl, Edi Inter, 1989.

HOMEWORK (Also see Studies)

When I'm at home I concentrate on my homework. I finish all of it carefully. I don't let myself get distracted. I'm not going to be tempted to do anything else until my homework is completed and my courses for tomorrow are prepared.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

HOMOSEXUALITY

I am a man.
A boy's penis smells bad. It's horrible, disgusting.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

HOME

I find my dream home. It's exactly what I've been looking for, and corresponds to all my needs. My subconscious is an infallible guide.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

HONESTY (Also see Frankness, Sincerity)

Honesty demands that I rid myself of the need to evaluate my own worth in terms of exterior values, instead of looking at myself as objectively as possible, with an eye towards an even better life than the one I am living today - in other words, instead of being more or less faithful to 'the way it's always been.'

Being honest with myself requires that I realistically evaluate my strong points and my weak points so that I can identify and separate all the defence mechanisms I've built up around me from my valid inner messages, and eliminate them.

I can decide to continue listening to false inner signals, trying to hide my real self from others, but even if I do, from now on I will be totally honest with myself.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

HONOR

I would be ashamed not to live up to my responsibilities and delude myself; therefore I must live up to my responsibilities to others, and not try to delude them.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Table of contents

HOPE

I build my hope, and never destroy it.
I choose to believe that something good can happen.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

Everything is tranquil around me. I feel good. I am confident. My life unfolds under the sign of hope. I am proud of what I have accomplished up to now. And I will continue being proud. My life is calm, pleasant and full of hope.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

HUMILIATION

No one can humiliate or upset me. I won't allow it.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

Humor

I am going to convince myself that a sense of humor is an antidote to worry. It will help me develop a balanced personality, and is as essential to intelligent living as food is for survival.

I need to laugh for the maintenance of good health, for the relaxation of my mind and body. I am going to remind myself not to take either myself or my troubles too seriously. Laughter will help me make life more bearable. Laughter is a habit. I am capable of cultivating it by simply repeating each day that I will find something to laugh about.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I have a kindly sense of humor about myself.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

HURT

Only the False Me can hurt me.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

No one can hurt me unless I authorize them to do so.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I eliminate the hurt of a negative emotion by refusing to identify with it; this means that I don’t see it as a permanent part of myself, but rather as a feeling that is just passing through me.

I try to put a definitive end to my inner hurt instead of seeking temporary solutions.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

HYGIENE (Also see Negative Habits, Dieting)

I give my body the best.
I love my body and I admire my beauty.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I will keep my body and mind clean because I want to live longer and stay young.

J.V. Cerney, Stay Younger, Live Longer Through The Magic Of Mental Self-Conditioning, Parker Publishing Company Inc., 1968.

I am good to my body and my body is good to me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am going to develop habits that are conducive to making me think and feel better. I am going to cultivate healthy living habits.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

HYPERTENSION

My blood pressure is always normal, and my heart beats regularly.

Christian Godefroy, Mental Dynamics Seminar, Godefroy Publications, 1978.

HYPNOSIS

I am certain I can put anyone under, at any time.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

I am going to use the technique of self hypnosis to develop a will to improve, a desire to study, learn and make progress in every aspect of my life.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

My hypnotic powers are developing day by day.

Pr. Lawrence Powers, The Ten Secrets Of Hypnotic Power, Godefroy Publications, 1982.

I am influencing your mind. I am going to put you to sleep. You cannot resist me.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

My hypnotic power is developing day by day.

Dr. Lawrence Powers, Ten Secrets Of Hypnotic Power, Godefroy Publications, 1982.

Table of contents

I

IDEALS

I intend to become.... (specify).

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I will become great.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I can be one of the cogs in a great cause. I strive to attain my highest ideals, which always include excellent physical and mental health.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

My role is to try to acquire the intellectual and moral qualities of the person I wish to imitate. I therefore observe my ideal model closely. I am aware of the value of each word I speak.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

My ideal is my guide. It is easier and easier for me to attain the goals I set for myself.

Christian H. Godefroy, The Seven Eternal Laws of Success, Godefroy Publications, 1980.

IDEAS

I don't forget the ideas that enter my mind.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

I make a conscious effort to think of new and better ideas, which are the subconscious keys to the vault of my mind.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I try to put an idea to practical use in my business or job, at home, and in my social relations.

I often review the immensely beneficial ideas I have concerning my Real Self and my False Self.

I take all these ideas and store them in my mental filing cabinet.

If an idea is really effective, it will prove itself sooner or later. I want to give my ideas a chance to prove their worth.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The idea that will enable me to succeed is already in my mind. I just have to think to get it out.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am part of the vital flow of divine ideas. I gather them and rejoice in them.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

The exact idea I need today will appear in my mind. Coming from the Divine Intelligence, it also contains all the subsidiary ideas I need. I allow this right idea to govern my thoughts.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

IDEAS - LUCRATIVE

I find the idea I need to double my revenue in one year.

My subconscious comes up with ideas for rapidly earning $50,000 (or the amount you need).

My subconscious comes up with ideas for rapidly earning

Table of contents

$100,000.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

My mind is always creating new and lucrative ideas.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

IDEAS - NEGATIVE

I let go of any mental pattern which is creating negative effects in my life.

Louis Proto, Self Healing, Piatkus Publications, 1990.

IDEAS - PRECONCEIVED

I have a conversation with someone whom I've avoided up to now. I soon notice that my preconceived ideas, when re-evaluated, paralyze me and nourish my indifference.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

IDENTITY

I master the principles of perception. I learn to know myself. I discover my real identity.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I am —— (specify what kind) of person.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I am happy being me right now.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

I am ME.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences the same way as I give , Godefroy Publications, 1989.

IGNORANCE (Also see Sickness)

As I give myself the right to make mistakes, I also give myself the right to be ignorant.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Divine force is manifesting itself in me, I am positive, positive, positive. I have the power to destroy sickness and ignorance.

Richard Ingalese, The Power Of The Mind, Dangles Publications, 1981.

ILLNESS (Also see Pain, Ignorance)

In the final analysis I must love in order not to fall ill.

I have learned the lesson(s) I needed to learn and no longer need to be ill.

I intend to enjoy myself in spite of my illness, rather than brooding over it and bringing myself down with worry.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I have now transcended all preconceived ideas about illness. I am free and healthy!

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I forget about illness.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I feel better.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

Table of contents

I know I can resist all diseases... whatever they are... I cannot be sick... I feel full of vitality... no discomfort whatsoever... no illness can catch my subconscious off guard.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Illness begins in the mind. I will never allow my mind to fall prey to thoughts which are likely to result in disease.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

You couldn't get the better of me, you will never get the better of me again.

Emile Coue, Complete Works, Astra Publications, 1976.

I am in good health, and my body no longer has any trace of disease. I look in the mirror and I feel happy. My skin is clear, my eyes shine with health. I feel good. I have energy. Life interests me. Everything is fine. My body is healthy, perfectly healthy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

ILLUSION

If I accept myself I choose reality and its accompanying roles: happiness, confidence and success. I don't have to live in a world of illusion any longer, because I'm very happy to be who I am.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I get rid of outdated attitudes and acquired convictions. My life will be free of illusions.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

IMAGINATION

I use my imagination in a constructive way.

My imagination is a friend, responsible for my past successes. I construct my present based on these positive images of the past, and make progress towards building a good and pleasant life for myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

The power of my imagination is my greatest strength.

Even if I haven't had a lot of success, what I have accomplished remains in my imagination, where it really counts.

I use my imagination to help establish goals for myself; it provides me with realistic objectives, unclouded by fantasies, which will make me a happier person.

I allow my imagination to work creatively for me and for others, by planning sensible and attainable goals.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

My imagination is a powerful tool for creation.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

My imagination always helps me find new ways to succeed... new and enriching paths to follow.

I have confidence in my imagination, which shows me the best ways to overcome obstacles.

My imagination is becoming more and more fertile. I am constantly discovering things I had no idea about... things that enrich and diversify my mind... so that I have a definite advantage over those whose horizons are limited.

I know I can count on my imagination.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

All the strokes of luck I have benefited from in life already ex-

Table of contents

isted in my imagination.

Imagination is my mind's workshop. It is where I convert my mental energy into action and wealth.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

IMMUNITY

(I am convinced that unconditional love is the most powerful stimulant for the immune system.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

IMPASSE

When faced with an insurmountable obstacle I try to see things on a higher level.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

IMPATIENCE

I will no longer feel impatient or angry; on the contrary I will always be patient, always in control of myself. And from now on the things that used to bother or irritate me won't affect me any more.

Emile Coue, Complete Works, Astra Publications, 1976.

IMPOTENCE (Also see Premature Ejaculation)

Tonight when I am alone with my partner I will feel exactly as I do now. I will be completely confident, sure of myself, I'll feel vigor-

Table of contents

ous and healthy, exactly as I do now.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

It's easy for me to get a strong and long lasting erection. And I have no trouble satisfying my sexual partner. I only ejaculate when I want to - I have perfect control. I like making love more and more, and I'm more and more skillful and loving with my partner. I am becoming more and more virile, and I satisfy my partner completely.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I have perfect control of my erections. I love to make love, and I know how to satisfy my partner. Day by day I am becoming more and more virile and loving.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am a normal man, with normal functions.

I feel confident with the woman I have chosen as my sexual partner.

Just as I am able to stay erect when I masturbate, I can do the same when I am making love.

I am a normal man, with normal sexual habits.

I only think about my successful sexual encounters.

I know that my sexual functions are normal.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

IMPULSE - NEGATIVE

I want to control my physical and emotional impulses and refuse to act on those which run counter to goals, principles and which disturb my vital balance. Next time I'm going to think before I act. I am absolutely determined to control my impulses.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

Table of contents

I am always calm... and I control all my impulses. I never act before deliberating... but once I've made a decision I see it through.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

INCOME

I now have a satisfactory income of $—— per month.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I'm doing what I really like. I therefore excel at what I do and my income is constantly increasing.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

My abilities are improving and helping to increase my income.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

INDECISION

I am no longer undecided, I make no more mistakes or errors of judgment. My conscience is a perfect center of Intelligence of the universal Understanding which is God.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

INDEPENDENCE

As an independent and positive observer of the mind, I do my best to be a complete and independent person. I refuse to let others dominate and control my thoughts.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I don't need to be accompanied by a friend to do what I want to do.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I have the right to live my own life, as long as I don't harm myself or others.

I live my own life. It belongs to me.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I will never allow others to think for me. I must remain the master of my thoughts and actions. I am capable of steering my boat the way I want.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am the sole creator of my universe and day and night I watch over my thoughts and feelings in order to guarantee my independence from others.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

INDEPENDENCE - FINANCIAL

I make a good living! I am heading for even greater success and financial independence.

I appreciate the financial independence which allows me to attain my financial objectives. The more precise and detailed my financial plan is, the more rapidly I will attain my objectives, and the more financially independent I will be.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I aim for financial independence and I make sure I don't owe anyone anything. If I have to beg for money I become its slave. In cases where I can't borrow money I find a creative way to earn it.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

INDIGESTION

My digestive system is calming down.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

INDIVIDUALITY

I am a unique creature.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

INFARCTUS

After each session I feel the pain in my chest diminishing. I will not feel my heart laboring. It now beats regularly and much more strongly.

The fear I feel about my heart is disappearing, and I will stop thinking about it all the time. My heart is now healthy and strong enough, and I am recovering.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

INFERIORITY (See Complex)

INFLUENCE

I have a positive influence on other people.

Sublipower, Subliconfidence, Edi Inter, 1989.

I influence the people around me at will.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

I will tell X that ——— (specify) and my words will have a powerful effect.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I am sure of myself, no one can resist my influence.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

I intimidate you, and you can do nothing to resist me.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

The fact of understanding another person gives me power and influence over that person.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The acts and words of others have no power or authority over me.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

X! During our meeting on — (specify) your opinions will change when I tell you that —— (specify).

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

INFORMATION

I try to promote the exchange of a maximum of information, considering that other people are, in a sense, really strangers, and that I am also a stranger to myself.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I make sure I'm well informed about new developments in my field.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Other people (superiors, subordinates and colleagues) know what

Table of contents

I'm doing, as well as why and how.

I am well informed about everything that has to do with my work and with my business.

I make sure there are no misunderstandings about the information I circulate.

I consider that a part of my work consists of circulating information.

If I'm in doubt about whether or not to divulge a piece of information, I go ahead and do it.

I make sure to always reformulate the information I receive in order to verify that I've understood it correctly.

I do not hesitate to be redundant, i.e. to repeat the same information two or three times in slightly different forms, to make sure that I have been understood correctly.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

INNER DIALOG

I stop focusing my thoughts on the negative. I just let them go! Being realistic doesn't demand focusing on a problem continuously.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I turn all negative 'self-talk' into positive 'self-talk.'

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

INNER GUIDE

I learn to take charge of myself.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I learn to take orders from my inner headquarters - the Real Me.

Table of contents

It is always a sure guide.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I listen to my inner guide for everything that is good, honest and positive.

Sublipower, Sublicontrol, Edi Inter, 1989.

The law of love guides me.

The inner force which guides me shows me how I can best serve humanity. In my dealings with friends and clients I am conscious of the fact that God resides in them, and I work with them for the triumph of happiness, prosperity and peace.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

My true Self guides me in all my actions.
Divine love guides me and always takes care of me.
It is now my inner wisdom that is my guide.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

INNER PEACE

I often practice mental relaxation. When I want to relax completely, even if only for a moment, I use my imagination to project myself to a place where I know I will immediately feel inner peace.

I possess inner peace. I live in a positive and interesting way. I have a reason for being here. I like what I am, and that gives me even greater assurance and inner peace.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

The secret place where I find refuge is found deep in my own mind.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Table of contents

INNER STRENGTH (See Strength - Inner)

INSOMNIA

Every night from the moment I want to go to sleep to the moment I want to wake up the next morning, I will fall into a deep, calm, tranquil sleep during which I will have no nightmares. When I awaken I will be completely refreshed and feel great.

Emile Coue, Complete Works, Astra Publications, 1976.

As soon as I go to bed I fall asleep.

As soon as I go to bed I fall into a deep sleep. I sleep all night long, and wake up refreshed and full of energy.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Being physically and mentally relaxed will enable me to sleep well again... a deep, restorative sleep... This sleep will make me feel completely rested when I wake up.

I will never be nervous again... always relaxed... I know how to relax and fall asleep when I want to.

I will sleep deeply all night long... nothing can bother me. And in the morning when I wake up I'll feel happy, lucid, completely rested... and full of joyous and well channeled energy.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I always get enough sleep; my body makes sure to get all the rest that it needs!

I love sleeping. I get tired, and sleep comes. I am going to have a deep sleep.

My body craves sleep. I will sleep well right through the night, and I'll wake up happy and full of new energy!

Table of contents

I feel the peaceful calm of the night making me drowsy; I am completely relaxed; I am in a state of repose, peace and harmony. I am calm, I feel I am a part of the rhythm of the night... I am weary and relaxed... I feel free and in tune with the natural rhythm of nature, which sleeps at night... my thoughts are getting fuzzy... I'm so tired... I'm falling asleep... sleep.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I sleep deeply and calmly.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I sleep better and better.

Emile Coue, Complete Works, Astra Publications, 1976.

I fall asleep easily, I will sleep deeply all night long and wake up refreshed and full of energy and good humor.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I fall asleep easily. I savor my sleep. Every night when I go to bed I forget my worries, fears and anxieties. I am happy, relaxed, calm, and ready for a great night's sleep.

I don't wake up during the night. Everything is fine. Everything is calm. I sleep deeply right through to the morning. I am calm and I don't think about anything. I sleep deeply.

Everything around me is calm. I do not wake up. I sleep deeply. I am relaxed and happy. Everything is fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I couldn't care less about whether I'm going to sleep or not. Even if I stay up till tomorrow morning it wouldn't bother me.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I am calm... my muscles are loose... my nerves relaxed. I am calm...

Table of contents

and I am falling asleep.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I am a normal person and I can fall asleep naturally.

The noise in my room helps me sleep.

The noise outside my room helps me sleep.

I can sleep the whole night through, without waking up, as I have done many times.

When I go to bed I leave my worries and preoccupations behind.

I am relaxed, free of all the negative influences that troubled my sleep in the past.

I don't have to try to sleep any more - I just let myself fall asleep.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I am going to use self hypnosis and practice relaxing my body and my mind. I am going to sleep soundly and awaken in the morning feeling refreshed and invigorated.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

A wonderful feeling of quiet and harmony spreads through my body... I feel happy... Every night when I go to bed this feeling overcomes me.

I fall asleep immediately... my sleep is healthy and natural... when I wake up I feel rested and refreshed... I can feel the peace and harmony spreading through me... I'll be happy when I wake up... day by day things are getting better and better.

Every night when I go to bed I eliminate all negative or annoying thoughts... I fall asleep right away... and sleep all night long until the next morning... When I awaken this marvelous feeling of peace and harmony is still there... I feel happy... day by day my condition is improving.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

Table of contents

INSOMNIA - CHILDREN

I love to go beddy-by because it feels so good.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

INSPIRATION (Also see Creativity, Optimism)

Every day ideas and creative inspiration come to me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Something good is waiting for me. And God sends me love. God is the light of my life, the source of all my knowledge and inspiration. God, who is at the heart of my being, knows all. He provides the nourishment for my thoughts, ideas which serve me well, and clear divine intelligence.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I am now guided by God. His love fills my soul. God inspires me and enlightens my life. I am full of goodwill and love for all. Every instant of my life I submit to the will of God.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am optimistic and inspired.

Sublipower, Subliconfidence, Edi Inter, 1989.

The inspiration I need will come to me while I sleep. Tomorrow I will resolve all my problems easily.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

My subconscious helps me discover the solution I am looking for. The answer I seek comes to me with ease. What is the best way to —— (specify)?

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

If I am stymied or at a dead end with a problem, I change the scenery and my mood. I try relaxing and reflecting by getting away for a day at the ocean or in the country. I remember that the right brain creative problem solver in my mind is always available for review when my left brain logic slows down.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

INTELLECT

I have an intellect, but I am not my intellect. It is fairly developed and active; it lacks discipline but it can be controlled and channeled; it is an instrument for gaining knowledge, both of the exterior world and the inner world, but it is not me. I have an intellect, but I am not my intellect.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

INTELLIGENCE (Also see Self Confidence)

The self image I choose depends only on me. I can choose to consider myself intelligent by applying my own criteria. For me, the happier I am the more intelligent I am.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I am intelligent.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I am wise. I am intelligent and creative. I accept that a positive mental attitude is an important part of creating my reality.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am an intelligent person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Table of contents

INTIMACY

I have the right to be intimate with someone.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I am capable of being intimate. I like having someone close to me. I am not afraid of intimacy. I'm ready to commit myself to an enriching relationship. I am happy to love someone.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am completely happy. My intimate relations are deeply satisfying and enriching.

I look at my being and my intimacy with enthusiasm and hope. I believe that I deserve the best. I am worthy of the very best, and I obtain it.

I am aware of my most intimate feelings and desires. I possess a fabulous treasure - my magnificent intimacy with another human being.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

INTRANSIGENCE

I will never convince anyone by using force. The feelings this would create are very negative and the results are short lived.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

INTRODUCTIONS

I always greet the people I meet with a smile. When introducing myself in any new association I take the initiative to volunteer my own name first, clearly; I always extend my hand first, looking the

Table of contents

person in the eyes when I speak.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

INTUITION

By listening to my intuition I can hear the voice of God.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

I am intuitive... my intuition is the voice of my inner Guide. S/He leads me and I obey.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

My intuition is getting better and better... and this intuition comes from my subconscious, which protects me... which knows what I should do... to stay healthy... to be loved... to succeed in my affairs... to earn money.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I develop my intuition and heed its advice.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I recognize my own intuitive ability.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I know what I need to know each moment. My consciousness is forever expanding and deepening.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am receptive to the counsel of my inner self.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The Universal Understanding which is in me knows things that I don't. I let this great force of understanding and the power of action do what has to be done. All the wisdom, all the spirit and all the

Table of contents

intelligence of God are now working through me to accomplish my goals.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

The spirit in me knows.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Intuition is not merely a hunch, but is an irresistible light which must be followed.

I never ignore my inner messages.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

My intuition is perfect, my perception of things is also perfect.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

INVESTMENT

I resolve to get my money working instead of me.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

INVOLVEMENT

I insist on my right to be a constructive member of the great human family.

No one can force me to isolate myself.

I live in the present, even in moments of tension, pain or grief.

I voluntarily strive to attain new and inspiring objectives.

I make sure I am open towards people.

I get involved in constructive projects.

Today is another day during which I can become wholeheartedly involved with other people.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

IRRITATION

I am starting to free myself from anger, resentment and irritation as I recognize that the causes of my anger are mostly in my mind, and disappear as soon as I modify my mental attitude.

If I get into a bad mood I sit or lie down, I close my eyes, I rest, breathing deeply a number of times and concentrating on an image of tranquility I repeat, 'I am at peace. I am at peace. I am calm, I am strong."

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I don't get irritated every time a problem arises.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

ISOLATION

I reject whatever can separate me from others.

If I neglect my self esteem I will find myself isolated.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am overcoming my feeling of isolation from others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

JEALOUSY

I have complete confidence in my husband / wife.

I am no longer afraid that s/he will leave me.

I won't try to eavesdrop on his / her telephone conversations any more.

I know s/he loves me as much as I love him / her.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I love him / her as s/he loves me - unselfishly.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I am ready to allow Love to flow through me, working for the benefit of all. I free myself of all hate, all unpleasant thoughts, and all jealousy.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

May my confidence shine through all my actions and attitudes. I show my love for my spouse by doing special little things for him / her, and I do everything I can to fulfil his / her needs and desires. I don't ask for anything s/he is not willing to give voluntarily; I firmly believe in our love, and I see how the magic power of love and mutual confidence changes both of us for the better.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Table of contents

JOBS (Also see Remuneration)

From now on I have a perfectly satisfying and well paying job.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I now have a good job.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I will find the ideal job.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I am keeping my job.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I easily find a well paid and pleasant job such as ——— (specify).

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

The ideal job for me does exist. But I have to start by believing it if I want to find it.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Infinite Spirit, give me the possibility of having a job (or a house, or abundance, or anything else you desire) which pleases me, a job that keeps me busy, a job where I am needed, and which no one else can do as well as I. May I meet the right people so that I find a job where I can offer good service and get well paid for it. Lead me to where I can make the right contacts. I leave it up to You, and I know that all will be well.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I accept the inevitable.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

Table of contents

JOIE DE VIVRE (See Love Of Life)

JOY

I smile a lot. I feel happy inside, and I show it.

I'm a happy person by nature. I try to look at life with warmth and joy, and I believe that life is worth living.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Today is a great day. And I have everything I need. So I choose to live wonderfully, in joy and love!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Each day I prepare myself to be receptive to joy.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Every day my mind is filled with joy, love and peace.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I now choose harmonious thoughts and let the joy flow freely through me.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I let go of the past and now live totally in the present.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I think and act joyously, and so I am joyous.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I smile because I want to share my joy.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I am as joyous as possible.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

(I am excited to be alive.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am always joyous, active and energetic. Eternal joy is my strength. I am always in a good mood, free and full of happiness.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Because my morale is getting stronger and stronger, I feel more and more in control of all situations, however difficult they are. Instead of all those negative and depressing thoughts, I will concentrate my mind on thoughts of health, courage, confidence in life and in myself, certitude and joy.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

JUDGMENT (Also see Action, Memory)

Moderation, common sense, good judgment and balance are all important elements of the way I live.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I channel my thoughts and take the time to exercise judgment concerning all my activities.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I never act contrary to my own better judgment.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

My thoughts are ordered and clear.
My judgment is rapid and sure, my memory is accurate.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

In order to clarify my judgment I try to understand other people's opinions about my behavior, my ideas and my emotions.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

Table of contents

JUSTICE

To be just, I act justly.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

JUSTIFICATION

I refuse to justify everything I do. If someone asks why I do such and such a thing, I reply that I have no reasonable explanation. I do what I do simply because I feel like it.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

KLEPTOMANIA (Also see Honesty)

I no longer feel the need to steal. I am in perfect control of my reactions and my impulses. In stores I always pay for the merchandise I take. I can easily master my impulses. I take pleasure in spending money for objects I desire. I am a perfectly honest person, and happy about it.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

KNOW-HOW

I trust myself to acquire the knowledge and skills I need if this plan or approach does not lead to the results I want.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

KNOWLEDGE

I seek knowledge in order to make wiser choices.

My daily job is to broaden my knowledge.

I can do whatever I want, but what I want is determined by what I know.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I raise my consciousness, my level of understanding.

Table of contents

I raise my level of knowledge.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I make harmonious and confident use of the knowledge I acquire in my life.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

I collect all the information I can.

I replace the effort of thinking with a tranquil understanding of everything that is going on.

I transform my acquired knowledge into personal knowledge. And then I experience the miracle of peace, every day.

The supreme secret for breaking out of the vicious circle of problems is knowledge.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I invest in my own knowledge. I enroll in an extension or seminar class in some aspect of personal or professional development. I make the bookstores and fitness centers my new haunts for 'happy hour.'

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

(Each person's knowledge is different, therefore no comparison is of any value.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

L

LACK

People give to me freely: I do not have to beg or fight.

Louis Proto, Self Healing, Piatkus Publications, 1990.

LAUGHTER

From now on I will cultivate laughter. I will smile, and my digestion will improve; I will rejoice and my burden will grow lighter; I will laugh, and my life will be prolonged, because that is the secret of long life, and it is now mine.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

My scale of values changes as my inner self develops. So now I laugh about things that caused me to suffer in the past.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

LAZINESS (Also see Cowardice, Lying, Disorder, Discipline)

Tomorrow I will wake up at — (specify) o'clock. I will feel rested and eager; I will not waste a minute lying around in bed; I will jump out of bed and joyously greet the day that awaits me. I will maintain my enthusiasm throughout the day, and I will work with joy and

Table of contents

presence of mind, certain that my efforts will lead to the desired results.

Starting today I will not allow myself to waste time on insignificant things, in order to prevent the bacteria of laziness from taking over my mind and my body. I walk straight and stand tall, not bent over like a crescent moon.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I am becoming a good worker, committed, courageous, and more and more frank and sincere.

Emile Coue, Complete Works, Astra Publications, 1976.

I will react against laziness and I will work with courage and regularity (dedication).

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I'm starting to like what I do again.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I can now get up on time every morning, feeling great.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am rested and full of drive. I rejoice in the things I have to do. Today is a lucky day for me. I am calm and serene, and I can handle any situation!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

LEARNING (Also see Knowledge)

Learning is like depositing gold in the bank of your mind. I invest in myself every day. I can learn whatever I want.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

I love to learn. I find the time to learn new things, and constantly develop my mind.

Christian H. Godefroy, The Seven Eternal Laws of Success, Godefroy Publications, 1980.

I am constantly learning!

W. Clement Stone, Passport To Success, Godefroy Publications, 1962.

After you have gained general knowledge in a field or subject, concentrate on learning one aspect of it well. Succeed in specializing, before you diversify. Doing one thing well, until you have mastered it, brings confidence and a reputation for excellence.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I take great joy in learning.

I am completely relaxed, and assimilate the text perfectly.

I can easily remember everything I learn when I wish, and I am satisfied with my progress.

I will stick to the program I set up for myself right to the end, and I will not let myself get distracted.

I am very happy to learn so quickly and easily in this way, and I feel great.

I listen enthusiastically to the information I want to acquire, and assimilate it as if it were the easiest thing in the world to do.

I always concentrate on what I am doing, at the moment I'm doing it.

Learning brings me more joy every day.

I feel free of all obstacles, and learn with enthusiasm.

Each time I make progress I get more pleasure from my work.

Each day brings me a greater and greater understanding of the deeper meaning of what I learn.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

I believe I can learn anything.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

LEARNING WHILE ASLEEP

Soon I will be deeply asleep. And yet I will easily be able to hear what I taped, and memorize it without waking up. I will learn the text on the tape easily, while I am completely calm and relaxed.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

In a few minutes, when I fall asleep, and even if I sleep very deeply, I will be able to hear the tape recorder; it will be easy to learn and memorize everything I hear.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

LEISURE

I engage in inspirational recreation. I get out the kites, grab the Frisbees, dust off the picnic basket, share a project with the children, attend little theatre productions, musicals, and concentrate most of my television and movie viewing on shows that warm my heart.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My leisure time is full.

I am aware that I can take an active part in managing my leisure time, just as I manage my professional life, or anything else I want to do.

I don’t consider leisure time as wasted, or just time to kill. On the contrary it is an opportunity to develop myself and to relax.

Every now and then I review how I make use of my leisure time, and plan various ways to use it better (theatre, vacations, etc.).

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

LESIONS

If there are lesions in one or another of my organs, these will heal up day by day, and will rapidly disappear.

Emile Coue, Complete Works, Astra Publications, 1976.

LEVEL HEADEDNESS

I am always level headed, calm and serene. God's peace permeates my mind and my soul, my entire being. I am full of goodwill, and sincerely wish all people peace and happiness.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

LIFE

Life is an amusing game which I want to play.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I now dedicate my entire mind to the Divine Plan of creative life. I refuse to be a mediocre person achieving mediocre results in my life. God has given me the genius of the Spirit.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Now is the best time to be alive.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

LIKABILITY

I am likable and affectionate, and I have a lot to share with others.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I am likable.

Dr. Wayne W. Dyer, Your Erogenous Zones, Tchou Press, 1976.

I am always relaxed, never irritable, and therefore always smiling and likable.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

LIMITATION

I never allow the obtuse thoughts of others to limit me; instead I open myself to limitless possibilities.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

There is no limit to how good I can feel.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am limitless. I know no boundaries as I live unconditional love and creativity. I recognize my true identity.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am free, nothing frightens me, nothing can limit me. The realm of the mind has no boundaries.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

(I am a limitless being.)

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

All thoughts of limitation and poverty are now erased from my mind.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

No task is impossible if I know and understand my limits.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

My only limit is my mental image.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

LISTENING

I listen to what other people are saying instead of preparing my answers, and I make sure they have finished expressing their point of view before responding.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I listen to everything the people I'm talking to have to say, not only a part of it. To me listening doesn't mean waiting for my turn to speak. When I listen, I really listen.

I am an attentive listener. I don't listen just for the sake of listening, but to understand.

I listen to other people's thoughts, but I also listen to my inner voice, the voice of my best friend and advisor. I listen to the advice I receive.

Every day I become more and more skilled in the art of positive listening. I like to use my listening skills every time I have an opportunity to do so, no matter who it is I'm talking to, what the occasion is, or where I am.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

LOGIC

I am a rational person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

My thoughts are coherent and organized in an orderly way.

Sublipower, Sublimemory, Edi Inter, 1989.

Table of contents

LOOKING GOOD
(Also see Weight, Losing Weight, Health)

I am gradually reaching my ideal weight. Every day I am closer to having the figure I dream about. I'm looking better every day. My body is firm, and I feel light. Life is nourished by life: I feel like eating living nourishing food, rich in vitamins. I love the life-giving taste of fresh raw fruits and vegetables, which enhance my beauty and energy.

Each day I feel my body becoming more beautiful and I rejoice in the life flowing through me.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

When I take an honest look at myself in the mirror I like what I see. I'm proud of the efforts I make to look and feel good!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

(I know I have to look good as good as I can to please my husband / wife.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I vibrate with immense happiness, in a magnificent body sculpted by the immense power of my subconscious.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

LOSING WEIGHT
(Also see Strength, Body Fitness)

I'll soon reach my ideal weight. I feel happy, and my body is looking better and better every day. I don't have to deprive myself of anything. I like my body, I like myself. My subconscious mind is my most

Table of contents

powerful ally. Through the power of my subconscious I can completely master my eating habits. I am free and happy. As I lose weight I feel more fulfilled, I am more active, more considerate of others, and prouder of my image.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Every time I start eating I rapidly lose my hunger. I will not eat any more foods that make me gain weight, and I won't eat between meals. My body will function on a strict minimum of food and, by perspiring, will eliminate all toxic substances.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

I lose a couple of pounds every week, and I feel fine.

Professor Kurt Tepperwein, Secret Techniques of Hypnosis, Godefroy Publications, 1981.

From now on I will be slim, strong and in perfect condition, whatever I do.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I find it pleasant and easy to lose X number of pounds.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I love this new beautiful body my subconscious is sculpting day after day. I'm losing weight. I'm looking better. I feel good. Every breath I take is filled with health and energy. Every time I exhale I get rid of toxins and excess fat.

My fat is melting. I'm looking better and better every day. I have less and less desire for useless foods that do nothing for my health. I am free of all that. I feel light, so light. I'm in great shape. And I feel great.

I feel so much better being myself in a slim body, free of all those false cravings and superficial pleasures.

Charles Baudouin, Psychology And Practice of Auto Suggestion, Idegraph Publications, 1990.

Table of contents

I am gradually reaching my ideal weight, and can maintain it easily. My health is improving. My appearance is also getting better and better, and people like to be with me more. I'm looking better every day. I only eat healthy foods, which help me lose weight without feeling hungry. I am becoming more and more attractive and healthy, thanks to the power of my subconscious mind. I can easily reach my ideal weight, and stick to it with no effort. I like my body, and the new self image my subconscious is helping me create. I am in perfect control of my eating habits. I love my body, and I have the power to lose weight.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I have no trouble maintaining my ideal weight.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am always slim and healthy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Whenever I sit down to eat I never let anyone else influence me, tempt me, or discourage me in a negative way. I am learning to say no to food and yes to success.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Losing weight the self hypnosis way will definitely improve my appearance.

Losing weight the self hypnosis way will change my personality, giving me greater self confidence, a sense of pride, a feeling of accomplishment.

Losing weight the self hypnosis way will make me less tired and sluggish.

Losing weight the self hypnosis way will improve my sex life by making me more attractive.

Losing weight the self hypnosis way will prolong my life.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

LOST OBJECTS

You know all things; therefore You know where my ring is and You will reveal where it is to me.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

LOVE (Also see Success, Happiness)

To love is to look beyond other people's faults and failings. I concentrate on the good in other people.

I love, and I never hesitate to go that extra mile, or spend that extra time to show someone my love.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Every time my partner is affectionate, I forget all my worries, and feel full of love and tenderness.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

My life is an experience of love and warmth.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

Giving and accepting love makes me strong. I always treat love as the most prized gift. The natural state of my heart is love.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I accept appreciation for my loving actions. As I give freely, I also receive freely. I appreciate myself as a male and female.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I greet this day with my heart full of love.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I love to love and be loved.

Table of contents

The more I love, the more love I have to give to others.

From now on I will love and receive love without any reservations.

All the love I seek is already in my heart.

The more I love myself, the more I love ———.

I love ——— and ——— loves me.

I now invoke the quality of love.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I love life, and life loves me in return.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I love.

Jean Chartier, How To Acquire A Superior Personality , Dangles Press, 1971.

I learn to think in terms of love in my mind, and I feel love in my heart.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I give and receive love freely.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I don’t hate anyone, I don’t envy anyone, but I love and respect the whole of humanity.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I could stop loving you, but for the time being I prefer to continue.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I radiate love through my thoughts, words and actions. Love brings harmony and happiness to my life, and to my relations with others.

Dr. Joseph Murphy, Triumph Over Yourself And Others, Le Jour Publications, 1988.

Table of contents

I am always in love with the universe, with life, and with myself.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I am a person worthy of love and affection.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I live in a cosmic universe, and I can hate no person, nation or race.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I live according to the law of love.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I love you.

Marcelle Auclair, The Book Of Happiness, Seuil Publications, 1959.

The emotions of love exists in me when I can be with other people and not want anything from them.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The Spirit in me loves the Spirit in you.

Marcelle Auclair, The Book Of Happiness, Seuil Publications, 1959.

Harmony surrounds me. I listen with love to the pleasant and the good. I am a centre for love.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I fill myself with love and always expect the best.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

LOVE - FILIAL (Also see Creativity, Sensitivity, Optimism, Peace, Joy, Tenderness)

I love and respect my father because he is good for me.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

Table of contents

I love my mother, but I'm not responsible for her happiness.

Louis Proto, Self Healing, Piatkus Publications, 1990.

LOVE LIFE

I respect myself and assume the responsibility of being myself in my love life.

I am loving and caring both towards my partner and myself.

I don't consider marriage an institution where one partner dominates the other. I have faith in love, in the support and opinions of my partner, but I am the only one who is in control of my life.

I like the way my partner looks at me, and I know that this look is a reflection of my approval and appreciation for him / her.

I feel sincere admiration for my partner, and I show it. I often express my admiration and approval, both in public and at home.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

LOVE OF LIFE (Also see Prosperity, Happiness, Self Confidence, Courage, Peace, Love)

I am going to regain my zest for life.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Life is fantastic. That's right, fantastic.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

[I am going to make a positive effort to enjoy life, based on the principle that happiness is an attitude that can be cultivated.]

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I am excited to be alive. I'm glad to be here. I am a bright, shiny

Table of contents

star that glows every day and night.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I rejoice in life, and I am happy to be alive at this point in history. I contemplate the bounty and richness of life all around me.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I profit from life.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I am full of life. I love life and I'm happy to be alive. I am a very special person, living an extraordinary life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Life is fun and pleasurable.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

LOVE OF SELF
(Also see Self Confidence, Self Esteem)

(The more responsibilities I accept, the more energy and self love I have.)

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I love the body I was given. It is a part of me, and I love who I am.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I love and appreciate myself as I am.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I love myself without condition or judgment. I am an energy pattern like no other before or after me. I am comfortable in my individuality.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

Table of contents

I love myself the way I am.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I respect and love myself.

Sublipower, Sublisuccess, Edi Inter, 1989.

I feel warm and loving towards myself.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

LOYALTY

I invest my sincerity and loyalty in others. This brings me closer to people.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

LUCIDITY (Also see Self Control)

By acquiring a lucid and constructive mind I become my own judge; not a judge who condemns with impunity, but a compassionate judge who does everything to plead my cause.

The lucidity of my mind is my laboratory.

My lucidity helps me develop positive habits.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I think clearly and judiciously.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I want to be perfectly lucid under all circumstances, remain in control of myself whatever happens, and feel perfectly at ease with everyone I meet.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

Table of contents

My mind is always clear and lucid, and the results I obtain are the proof.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

LUCK (Also see Money)

I am lucky.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I am getting luckier and luckier.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

I have the right to be lucky and rich.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I go through life smiling.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I am a magnet for everything good.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Love, that divine magnet, attracts everything that is good.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Everything comes to me easily and effortlessly.

From now on everything will contribute to make my life beautiful.

Everything good comes to me easily and effortlessly.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

LUNG DISEASE

My lungs are getting stronger.

Sublipower, Sublihealth, Edi Inter, 1989.

Table of contents

My lungs are clean and strong. I can breathe deeply.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

LYING (Also see Cowardice, Laziness)

I always tell the truth.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

MAGNETISM (Also see Influence)

I am accumulating great magnetic power.

I accumulate all ambient magnetic energy in my solar plexus.

My magnetism is becoming more radiant every day.

The magnetic power I emit makes my suggestions irresistible.

I can easily concentrate the magnetism in me, and project it where and how I want.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

I am projecting my magnetic force. I am saturating this person with the flow of my magnetic energy.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

The people who enter my life are attracted by my own personal level of magnetism.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I have magnetism because I am in control of my mind and body... this gives me great inner strength... this force... each day... I feel it developing in me.

I control and channel my thoughts at will... and this cohesion of my personality has a positive influence on those around me.

Such thoughts attract similar forces... of love and benevolence... which reinforce my personal magnetism.

I feel myself radiating a powerful magnetic force... which helps me succeed in life... which makes me attractive... to both men and

Table of contents

women... I always try to be friendly, hoping to benefit them in some way... with my magnetic force.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I now exert an irresistible attraction on people.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I project my personal magnetism.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

I feel attractive, bursting with all the power in my soul.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I feel more and more attractive, more and more powerful and magnetic. I have a positive influence on everyone around me. More and more people are attracted to me. Yes, day by day I feel my magnetism getting stronger.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

Other people love to have me around.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

My personality is becoming more and more magnetic. I can influence the people around me at will.

People are attracted to me more and more. I'm liked by everyone I meet.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I'm working on my facial expression: I want it to be frank, full of light and strength, ready to spread my power wherever necessary.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

No one can resist the power of my eyes.

Professor Lawrence Powers, The Ten Secrets Of Hypnotic Power, Godefroy Publications, 1982.

Table of contents

Nothing can resist my gaze.

Marcel Rouet, Techniques And Practise Of Hypnotism, Paris Productions N.O.E., 1974.

MAIL

I answer my mail, or throw it away, or delegate it every day, so that it doesn't pile up.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

The mail I send projects a positive image of my service and of myself.

Taking care of my correspondence doesn't take a lot of time.

I use empty blocks of time to take care of my mail.

I write creatively.

I am learning (through practice) to write clean copy on the first draft.

I am learning (through practice) to dictate a clean copy to my secretary on the first draft.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

MANAGEMENT

I build other winners too.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

MANAGEMENT - MONEY

I enjoy managing money carefully and successfully.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

Table of contents

I know how to manage my money. I have a healthy respect for what I earn and what I know, and I put them to the best possible use.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I know where I stand financially.

My spending is in line with my resources, with a sufficient margin for maneuvering.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

MANAGEMENT - TIME

I dedicate about twenty minutes a day to managing my time: ten minutes in the morning going over the list of things I have to do, and one minute per hour throughout the day.

I regularly ask myself what I can do to save time.

I allow myself sufficient time alone to think about how I'm organizing my time.

I know how to say 'no' and avoid time wasting activities.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I make a list of my daily tasks, in order of importance.

I know how important it is to remain in control of my time and my priorities.

Since I establish my own priorities and since I am aware of the importance of each of my actions, I give them exactly the amount of time and degree of attention they merit.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

(I manage my time well.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I take time for sunsets and flowers.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

MARRIAGE

I am wanted by someone. I am happily married to a good and loving man / woman who is interested in things of the mind. I am secure.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

MATURITY

I am becoming more mature every day.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

MEDICAL TREATMENT

This treatment is totally successful and feels very comfortable. My pills are working wonders - and with no side effects.

Louis Proto, Self Healing, Piatkus Publications, 1990.

MEDITATION

I bow before the power that is in me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I remain awake in a passive way.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

MEETING PEOPLE

I like to meet people and I focus on their good qualities. My goal

Table of contents

is to make each person glad they talked with me.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I take great pleasure in meeting other people, and I always see their good side. I am in no way unconsciously fearful of people, I know that the Spirit in all people is one of warmth and loving friendship. I give thanks for all the people I know, and for those I will meet in the future.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I approach people with heartfelt friendship.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I can't select all the people I'd like to work with and be with; but I control whom I spend most of my time with, and I can meet new people. I can change my environment and seek out successful role models to learn from and share with.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Now I meet exactly the type of people I want to know.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The more I meet different people, the more opportunity I have to realize that my fears were all a waste of time. With this in mind the unknown becomes something that I want to explore instead of something I want to shy away from.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

You are you and I am me.
I am not in this world to meet your expectations.
You are not in this world to meet mine.
I am here to do my thing.
You are here to do your thing.
Sometimes we will meet - and that's beautiful.

Table of contents

Sometimes we won't. Too bad.

Louis Proto, Self Healing, Piatkus Publications, 1990.

MEETINGS

I always get to my meetings slightly ahead of time, and I make sure I never miss a plane or train.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Each time I am called upon to make a presentation to my department I prepare carefully and arrive at the meeting feeling completely sure that I know my material and that I will be in control of the meeting.

Each time I meet with our financial advisors I feel very much a part of the family. Being young only emphasizes my capabilities. Sitting with my colleagues I feel calm and serene, one member of a team all collaborating to achieve the same objectives. Because my mind is concerned with the decisions that we will soon have to make, I am oblivious to my body, and I am calm, concentrated and completely without tension.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, The 1978.

I prepare for my meetings.

I make sure that the person chairing the meeting does his or her job properly.

Only the people who are required to make the meeting more effective are allowed to participate.

The meetings I chair always result in explicit decisions being made and understood by all participants.

When I'm not chairing a meeting that I find is going badly I try to exert a positive influence by getting myself appointed secretary, or by suggesting that we take time out to evaluate the proceedings.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

Whenever I am asked a point-blank question in a group meeting I am usually able to respond because I always pay attention to the discussion. I feel calm. I don't worry about coming up with the "right" answer because after all, I am the expert.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

MELANCHOLY

I am never melancholy.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

When I am in one of my melancholy moods I will make sure not to project my disturbed feelings of gloomy disposition onto others.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

MEMORY
(Also see Concentration, Judgment, Willpower)

Starting today all aspects of my memory are improving. It is getting better and better. I retain everything I need to know more and more easily. I have confidence in my memory. It is more and more accurate. It is becoming more and more effective.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

What I record in my memory is written in indelible ink, and stays there forever.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

Whenever I repeat the word X three times in a row my memory becomes perfectly active. It is ready to assimilate data, and I learn everything I have to with ease. Whenever I read or listen to some-

Table of contents

thing my mind will be more open and will store as much information as possible. My memory is improving, and it is much easier to concentrate on the subject at hand.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

I have a good memory... a faultless memory... I can retain whatever I want.

My memory is powerful... and improving every day... as I organize my thoughts.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I like going to classes more and more as my memory improves.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

My memory is improving daily. My memory is getting better day by day, so that I can remember everything I need for my work.

All aspects of my memory are improving. From now on I can easily remember everything I have to, under any circumstances and in any place. My memory is more and more precise and faithful. I absorb all the information I need in my day to day life more and more easily. My memory is improving daily, and will soon be completely effective. I control my memory under any circumstances.

I congratulate myself. I really have a fantastic memory. I should be proud to have such a good memory. I can easily remember all the dates, events, statistics, thoughts, words, reading and work-related information I need to know. I really have an effective memory. Once again, bravo! I congratulate myself!

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I train my memory in order to make it more powerful, and I use it to advance in my chosen profession.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I imagine my memory as a fruit (any fruit). It is healthy, perfectly

Table of contents

smooth, free of imperfections. It is perfect. That is my memory.

I am relaxed. Everything is going well, everything is calm. My memory is improving day by day. I have a good memory, a faithful memory. I can count on my memory because it is becoming more and more accurate.

My memory is faithful. I can count on it. It is becoming more faithful every day. I am happy about the progress it is making.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I always remember my conversations with others clearly. I can repeat important parts word for word. This helps in my work, and in all other areas of my life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am going to devote a part of each day to improving my memory.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I want to make my memory fast and accurate, my assimilation (of information) clear and correct, and my willpower faultless.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

My mind stores information with ease.

All I have to do is give myself a mental command to retrieve any information I want from my memory.

Every day I work on developing my concentration and memory.

My memory is getting better every day.

I have confidence in my memory, as it becomes more and more accurate.

My memory is getting stronger every day.

My thoughts transform into images, which are engraved on my mind.

I can easily recall any information I need, when I need it.

I have the power to remember everything I see, hear or read.

Table of contents

My memory is my friend, and I can count on it.

If I want to forget an event, a thought, a person or an object, my memory obeys.

The more I use my memory, the more accurate and faithful it becomes.

Sublipower, Sublimemory, Edi Inter, 1989.

I now have complete confidence in my memory. It is now fully effective. I can control it under any circumstances. It absorbs everything I need to know, and provides me with the information I need, when I need it.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

MENOPAUSE

I am not at all worried about my life as a woman... because I can stay young... stay young for a very long time.

I feel good... I am relaxed... I am not worried... I am resolutely optimistic... at this age where women reach their full potential... A great life lies ahead... full of promise... and I feel good, wonderfully good.

I am going to manage my menopause and make it another, even more enriching stage in my life as a woman.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

MENSTRUATION

I know that the menstrual cycle should occur regularly every twenty-eight days, and not every thirty days as many people believe. It will last for four days, no more, no less, and the flow will be neither

Table of contents

too abundant or too sparse, both before and during the period; I should not suffer from kidney or lower back pains, headaches or any other kind of pain, since this natural function should take its course naturally, without my having to suffer in any way at all.

Emile Coue, Complete Works, Astra Publications, 1976.

I am balanced and peaceful in all changes of cycles, and I bless my body with love.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

My uterus is tightening, emptying itself.
My uterus is becoming empty; I want it to be empty.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

MENTAL CONTROL

I take charge of my thoughts. I can do what I will with them.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I am responsible for the thoughts in my head.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

MENTAL FACULTIES (Also see Concentration)

My faculties are developing day by day.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

MENTAL FATIGUE

My thoughts are clear and precise, my mind is fresh and alert.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Table of contents

I do not hesitate to take a break from my work if I'm tired... to relax my muscles... to breathe deeply and restore my energy... or to relax my brain by emptying my mind.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

MENTAL PROJECTION

I develop my faculties of concentration and mental projection. I learn to project my mind and all my senses in the desired direction, to any place and any level in the universe.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

I am learning to develop my five senses, my concentration, and to project my mind to any place and any level in the universe.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

MENTAL RETREAT

In my place of retreat I am free, and I am in control of my subconscious.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

MERIT

I merit the best, and from now on only the best will come to me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I was just talking about luck, but luck had nothing to do with it. I got that good grade because I deserved it.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

I want to imitate the examples of those who succeed, of those who fear no obstacles. I want to merit and obtain success, joy, power and love.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

MIGRAINE (Also see Emotion)

I can relax at any time. My head feels cool... my head feels light... my neck and shoulders are supple and relaxed.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

In a few moments my mind will become clearer. The excess blood congesting my head is flowing back down to other parts of my body. Soon my headache will be gone.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I feel my head getting calm.
I feel my head relaxing, getting lighter.
I feel free of all mental stress.
I feel my head is normal, clear.
I am in control of my emotions.
I feel free of the past events which caused my migraines.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I will feel good today, my head will be clear and lucid.

Leslie M. Le Cron, Liberate The Forces In You Through Self Hypnosis, Tchou/Ariston, 1964.

I am going to free myself of migraines.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

My head is opening, becoming calm and light. Energy is once again circulating normally though my head, eliminating all fatigue and all tension. My blood is irrigating every part of my brain fully,

Table of contents

bathing it in a soft light. My head is completely relaxed.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

My forehead feels pleasantly cool.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

My headache has disappeared.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

Go away! Go away!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

MIND (Also see Memory, Concentration)

I use the vast power of my mind.
I concentrate my mind on one thing at a time.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I want to be mindful of everything because whatever I am aware of can inspire new ideas and opportunities.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

All the functions of my mind, like memory, attention, etc. are improving.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

Like an eagle my mind was created to rise to great heights.
I rely on my aptitude for developing maximum mental power.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I affirm the existence of the Real Me.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I will never use the power of my mind to do harm to others.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

I rejoice in this Life which exists for me. I am an incarnation of the Mind of all life.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I AM everything of substance that is.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

[I am going to think with my mind and not my emotions. I am learning to think love in my mind, so that I will feel love in my heart.]

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

My mind is a divine center of operations.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Everything is the Mind. When the Mind is well, everything is well.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

MIND PROJECTION

I want X (specify who) to be forced to reveal —— (specify what).

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

MIRACLES

The light in me is accomplishing miracles in my life, here and now.

The light in me is accomplishing miracles in my body, in my mind, and in my affairs, here and now.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am the greatest miracle in nature.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Table of contents

Divine love is working in me here and now in order to create something.

The Christ in me is accomplishing miracles in my life, here and now.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My own words create miracles in my life.

I expect a miracle.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

MISOGYNY

I will make an attempt to understand and appreciate feminine psychology so as to better comprehend the underlying motivations for my wife's behavior.

I cannot expect love and respect from my wife if I belittle or abuse her.

I must also remind myself that little courtesies, tender attentions and acts of kindness are as important to her as material gifts.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

MISTAKES

I collect my mistakes with pleasure. I consider them as tools for learning.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I have the right to make a mistake.

To err is human. I am a human being.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Table of contents

I nourish my conviction to rise above my mistakes.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I learn from my mistakes.

Sublipower, Sublisuccess, Edi Inter, 1989.

(My father thought that it is important not to make mistakes. But I have to learn how to do this work. I can only learn by trying. If I worry about mistakes I will stagnate, I won't learn anything.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I know that I am free to make mistakes, it is fine to make mistakes. I do the best I can. I always do the best I can within the limits of my awareness. Within the limits of what I know at any given time I do the best I can. I love myself, mistakes and all. I am a good person. I learn from my mistakes, and I am free to make them.

I am free to make mistakes. I can learn from my mistakes without guilt or worry. The past is over and there is nothing I can do about it.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

When I make a mistake or get ridiculed or rejected, I look at mistakes as learning experiences, and ridicule as ignorance. After a rejection, I take a look at my BAG - Blessings, Accomplishments, Goals. I look at rejection as part of one performance, not as a turndown of the performer.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Here's a mistake I promise myself I'll never make again, with the help of God!

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

MISTRUST

I believe everything —— (name the person) tells me about his / her activities.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

MISUNDERSTANDING

I make sure not to mistake a misunderstanding for a real disagreement.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

MODERATION (Also see Discernment)

I am happy to possess this or that object. I promise to use it wisely and in moderation, so that I get as much pleasure as I can from it.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

When I reprimand someone or express my unhappiness I try to do so after the urge to fight or become upset has subsided. The best way to get my feelings across is when I can speak in a normal voice, without all of the warlike body language. When I am upset I try a substitute physical exercise such as running, tennis, racquetball, or handball, in which there is impact involved to release the built-up adrenaline in my system. I do speak my mind, but I criticize the behavior without attacking the other person.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Everything has its just measure, and I respect it.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

I am going to observe moderation in everything I do.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

MONEY (Also see Business, Luck, Competence, Creation, Projects, Debts, Vocations)

From now on I have more money at my disposal than I need.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I earn more money than I spend.

Christian Godefroy Collection, Magic Formulas For Being Happier And More Successful, Godefroy Publications.

I manage my affairs wisely and confidently. I earn enough money to satisfy my needs.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I don't dislike money... it gives me security... and I know that I can make money if I want to.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I can do anything I want to extremely well, including making money.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

I am receiving plenty of money for doing exactly what I want to do.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I am mentally and spiritually connected to the money I gave ——— (name) and it will come back to me multiplied and magnified in the Divine Scheme.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Table of contents

I bless you so that you can bless others in turn. May you enrich everyone you touch. I thank God on your behalf, but I thank Him even more for the thousands of others like you. I bless this infinite abundance. I thank God for it, and receive it with an ever more open mind.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I find the money I require to buy the car I need.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Money is energy, and I control its flow.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Money makes me, and the people close to me, happy.
Money allows me to help others.
Money comes to me without effort.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

Money comes to me freely.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Life places people on my path who can help me progress financially.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

On the first of —— (month), 19— (five years from now) I will have $50,000, accumulated gradually over a 5 year period. In exchange, I will do my best to provide excellent service as a (describe the service or merchandise) salesman.

I firmly believe that I will have that money. My conviction is so strong that I can already see it in front of me. I can touch it... it's there waiting for me to take it. I instruct my subconscious mind to come up with a plan that will get me that money, and as soon as my subconscious mind forms a plan I will put it into action.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

Table of contents

I become more financially comfortable every day.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

MOODS

From now on I will be in a good mood more and more often. Joy, happiness and serenity will become my normal states of mind.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am going to devote time to studying the reasons for my mood swings.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

MOROSITY

I greet this day with a heart full of love.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I no longer think there is no point to life. I use the principles of truth to discover goals in life.

Life is worth living when I understand the value of the richness of life.

My life becomes richer and fuller when I can free myself from my negative self and the errors that part of me commits.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Oh, what a wonderful day for going out and enjoying what the world has to offer!

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

This is the day God has made; I will rejoice and be happy on this day. I thank God for the abundance of life, I thank God for lasting love. I thank God for joy. I thank God for magnificent health, I thank

Table of contents

God for infinite abundance.

I have awakened to a new day. I feel at one with the birds and with all living creatures, celebrating this new day with a burst of song and thanksgiving. God, I thank You for the abundance that is mine.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

MOTIVATION

I like ——— (specify an activity which you like but which you haven't had the courage to undertake.)

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I feel rich! I feel happy! I feel great!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I enjoy my professional activities.

I am enjoying the new project I'm working on.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I show my self respect through this inner motivation which keeps me on the path of achieving my goals, on the path of success, even if I fail now and then.

I am my goal.

I am success, even before I attain it, since I am already on the path of full realization.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

If I want to achieve permanent, sustaining success, the motivation that will drive me toward that goal must come from within. It must be personal, deep-rooted and a part of my innermost thoughts. All other motivation, the excitement of a crowd, the stimulation of a pep-talk, the exhilaration of a passing circumstance is external and

Table of contents

temporary. It will not last.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

MOTIVATION - SCHOOL

After I finish this lesson I can go and watch the football game.
I'll do three more chapters, and then I can watch the movie on TV.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

MOVING

I'm soon moving to a really nice apartment that will make my life more stimulating.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

MUSCLES

Every muscle in my body is controlled by my Muscle Coordination Center.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

My muscles are relaxed and warm.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My muscles are strong and supple.
My muscles are supple and healthy.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

MUTUAL AID

Every day I find occasions to help my peers and accomplish constructive things.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

MYOPIA (See Nearsightedness)

Table of contents

NAIL BITING

Every time I bring my nails to my mouth to bite them, as soon as I put my nails in my mouth, I will experience an extremely bitter taste, and the taste will get more and more bitter, more and more unbearable to the point where I will feel sick and want to vomit.

Gradually, as I grow up, I will become more and more attractive. So I don't want to harm my appearance by having ugly hands; beautiful hands with well trimmed nails will make me even more attractive, and for this reason I will make a determined effort to stop biting my nails.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I no longer feel any need to bite my nails. I find it easy to break the habit, and my hands are becoming beautiful and elegant.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

NATURAL

I am natural and confident.
I act as naturally as I feel inside.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

NEARSIGHTEDNESS

The lens of my eye, too rounded (too convex) ... is relaxing.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

NEED

I have legitimate needs and wants. I can choose what I need and want without having to justify it to anybody. I make choices, and I take responsibility for them.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

It’s all right to meet my needs as I see fit.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I express my needs honestly, listen to the needs of others, and look for the deepest truth.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I first understand my own needs, and then the needs of others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I can invent new ways to satisfy a need and wisely choose the best option.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am secure enough to grow. I ask for what I need. All my needs will be fulfilled.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

The universe always provides for my needs.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

What I say, I get.
And I always have everything I need.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

NEGOTIATING

I know how to break off negotiations if I have to.

My negotiations always result in clear, explicit and concrete agreements.

Before negotiating I clearly define my objective(s) in order to know exactly what I want and what I don't want to happen.

Before negotiating I clearly define my bottom line (without necessarily telling the other party) in order to use dissuasive strategies without being forced to walk away from the table.

When I negotiate I try to remember that any business relationship is comprised of one part cooperation and one part competition, each of which may predominate according to the time and circumstances.

I am careful not to get boxed into an undesirable choice: friend or enemy, trust or mistrust, cooperation or competition.

I make clear pronouncements of the points of agreement as they occur.

I know how to break down my negotiations, so that the discussion about one clause does not systematically bring into question all the clauses already agreed to.

Breaking down the negotiating agenda allows me to remain firmly opposed to the other party on certain points.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

If I negotiate without having the power of decision, I make sure the scope of my delegated authority is clear in my mind, and in the minds of everyone involved.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

NERVOUS BREAKDOWN (Also see Nervousness)

From now on I will no longer be taken by surprise as I was in the past; every time I feel a nervous attack coming on I will be warned by certain symptoms; but these symptoms will no longer frighten me at all, because at the same time as I feel them I will hear a voice inside me saying, as quick as lightning, "No... no... I will not allow this breakdown to happen. My nervousness is disappearing... it has disappeared."

Emile Coue, Complete Works, Astra Publications, 1976.

NERVOUSNESS (Also see Agitation, Anxiety, Fear, Nervous Breakdown)

I always act calmly... without making needless gestures... and I never swear in moments of impatience.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I don't have to be nervous and tense. I am capable of relaxing. I have learned how to relax my mind and body.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I want to dominate my anxiety, fear, nervousness and any other paralyzing emotions.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

When I find my Real Self, nervousness disappears forever.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

NERVOUS SYSTEM

My nervous system is making amazing progress. I am affecting it in two ways, which makes my influence doubly effective. Firstly I influence it directly through suggestion, since the nervous system is directly related to the brain; secondly I influence it indirectly by improving my general state of health, since the nervous system is also affected by the body's general state. My nervous system is becoming more and more sensitive and vibrant, as it should be, and at the same time it is becoming more and more calm, strong and resistant, as it also should be.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

NEW BEGINNING

I am making a new beginning towards a new and better life, and I will get involved with other people.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

NOISE

Noise doesn't bother me... I know how to adapt to any situation... without becoming nervous.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

NOSTALGIA

I should not be nostalgic about the past. I should think about today.

Table of contents

Today is the day I should be living.
I am doing all I can to love this day.
I will use this day to express my positive qualities freely.
I am ready for a day of confidence and accomplishment.
I combat negative emotions which will destroy my having a good day.
I call on my positive qualities: life is lived in the present.
I nourish my enthusiasm for the present moment.
I will use this day to try and express the best of myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

The good old days are here and now!

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

NOVELTY

I like to invite people with very diverse opinions about things. I seek out novelty instead of limiting myself to conventionality, where the unpredictable is excluded.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

NUMBNESS

I want (specify which part of your body) to become numb. I impose my will.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

My hand feels dead, completely numb... and this numbness will soon move up into my wrist, my forearm, my upper arm, right up to

Table of contents

my shoulder... I can feel it moving upwards... my whole arm is becoming numb... there is no feeling at all... it is becoming more and more numb... my whole arm is dead... numb... completely numb.

Marcel Rouet, Techniques And Practise Of Hypnotism, Paris Productions N.O.E., 1974.

NUTRITION

I only eat foods which are good for me.

I only eat foods which are healthy and which help me maintain my ideal weight.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I put only the best fuel into my body.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

[I am constantly fulfilled in my life. Since I know life, I nourish myself with joy. I construct my body in a balanced way.]

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I am going to eat good wholesome food and not overeat, or overindulge in foods that are not good for my health.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

OBESITY (Also see Nutrition, Physical Exercise)

I respect my body, I care for my body, I need my body to live.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I am gradually reaching my ideal weight.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I maintain my ideal weight. It's easy to do because I exercise and eat in a balanced and healthy way.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I never eat between meals.
I chew my food very slowly.
I don't eat food that contains wheat.
I don't eat food that contains sugar.
I don't eat standing up.
I visualize the body I want.
I eat smaller portions.
I don't need to be encouraged not to overeat.
I like myself and I want to be the best I can be.
I persevere until I attain my goal.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Losing weight through self hypnosis will keep me from developing health complications associated with obesity, such as hardening

Table of contents

of the arteries, coronary disease, diabetes, etc.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I stay at my ideal weight no matter what I eat.

Sublipower, Sublihealth, Edi Inter, 1989.

OBJECTIVES (Also see Goals, Self Control)

Every day I make progress towards attaining my objectives.

Every day I continue moving forward by trying as much as possible to avoid the hazards of life. To do this I summon my inner resources to lead my to my objectives.

I learn to attain my objectives by mastering my fears and rejecting my negative emotions.

I choose realistic objectives and then work on attaining them.

I concentrate on my objectives.

I try to attain my objectives every day. I break out of the prison I have created for myself and strive to reach my objectives.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

It is easier and easier for me to realize all my dreams.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

I have clear objectives which guide me in determining my priorities.

I often review my priorities in life, my professional and personal priorities, in order to discern convergencies or contradictions, and any lack of coherence.

I define my priorities in order to make them concrete, stimulating, and attainable.

I am make sure to explain my objectives to superiors and subor-

Table of contents

dinates.

I work on my objectives.

For each objective I strive for harmony between the objective itself, the results it yields and the methods used to attain it.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I easily attain all the objectives I set for myself.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I make a list of goals that I hope to achieve for the day. I visualize myself accomplishing each goal in the best way. I write a note of thanks that I've reached my goals.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I establish my objectives and then use the resources I possess with devotion and perseverance in order to obtain the desired results.

When I keep my mind fixed on an objective I increase my chances of attaining it immeasurably.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I make sure my objectives are clear to myself.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I set precise objectives and deadlines for myself.

Sublipower, Sublisuccess, Edi Inter, 1989.

I set my objectives, write them down, and review them often.

My objectives are a clear illustration of my future!

I spend a few minutes every day reading over the file of objectives I've written for myself. I read over my objectives every morning after I get up, and every evening before going to sleep.

My objectives are very precise. The more detailed and precise they are the better I can visualize them and make them a concrete part of my life.

Table of contents

I set myself an objective. I don't hesitate, but start striving to attain it. I know the universe is overflowing with opportunity. Look at what I can do! Where I can go! Look at what I can accomplish, simply by saying "Yes!" to myself.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I never lose sight of my long term objectives.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I'm in my car driving towards my destination. I'm in the driver's seat, and I don't let anyone else drive my car. I am the driver. If I get to a dead end I back up, turn around and continue my journey towards my objective.

I remind myself to concentrate on my objective all day long.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I eliminate this objective for such and such reasons. I realize I no longer need it, or no longer want it. My initial idea is now only a memory of a desire. It has no more power or effect on me. It no longer interests me. I am now concentrating all my interest and all my energy on a new and better objective.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

My objectives in this situation are important. If I don't achieve them, I'll be disappointed and it will be inconvenient, but it will not be a catastrophe or a horrible event. By thinking about negative results as a catastrophe, I'm creating tension and fear that actually reduce my chance of success.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

OBJECTIVES - FINANCIAL

Table of contents

In one year I will find the $———— I need to buy a house.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

OBLIGATION

I always respect the obligations I accept. I never accept obligations which I cannot respect.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

OBSESSION

I am now calmly and confidently concentrating my mind on another subject.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

If I cannot meet such and such a deadline, I won't let it become an obsession. I am satisfied knowing I've done my best.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

OBSTACLES

I eliminate the word impossible from my vocabulary!
I possess the means to overcome all obstacles.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I can overcome obstacles by mentally flying over them.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I will take care of all kinds of obstacles as I encounter them. I will go as far as I can, and when I get there I'll be able to see even farther.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

Table of contents

I was born to win, to succeed. I am very prosperous, and through the power of God I overcome all obstacles and all problems. I am happy, joyous and free.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I can overcome anything, and see everything through to the end.

George Barbarin, How To Overcome Fears And Anxiety, Dangles Press, 1974.

Up to now no problem has been able to get the better of me: I'll overcome this one as well.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Now everything will work out.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

The greatest obstacle to my success lies within me. What prevents me from doing what I want to do is my belief that I cannot do it.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

OFFERING

The more I give the more I receive and the happier I feel.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

OPINIONS

I don't have to give up my opinions for those of another person just because that person seems sure of him/herself.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I can refuse to discuss my opinions or try to convince someone of the logic of my position, and simply believe that I am right.

Table of contents

When I buy clothes or other personal objects I have confidence in my taste, and I don’t start by asking advice from someone whose opinions I deem to be more valuable than my own.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Other people can disagree with me without it affecting me.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

OPPORTUNITY

I take action! I seize opportunities!

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I readjust my objectives according to circumstances, in order to exploit opportunities to their fullest.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am always at the right place at the right time, doing the right and successful thing.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I take advantage of every opportunity.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

A favorable opportunity will give me a sign if I am meant to see it; I am on the lookout for opportunities, and I always try to take advantage of them.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

OPTIMIZING

Table of contents

I always try to make the next hour better and more productive than the one that has just past.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

OPTIMISM (Also see Depression, Inspiration, Positive Thinking)

Whenever my attention strays from what is constructive and positive I immediately concentrate on things that are good and beautiful.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I love life... it's wonderful... full of all kinds of surprises and sudden developments... I never get morose... I'm never bored... because I only see the good side of things.

I stay away from pessimistic people... people who criticize and complain all the time... who are never satisfied with anything... instead I seek out spiritual people, people who radiate health, and whose inner life is calm and serene.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I listen to upbeat, inspiring music. When I am getting ready for work or school I turn the radio on to a good FM station. I stay away from the morning TV news. I can brief myself by scanning the news on the front page of the Wall Street Journal. I resist the temptation to waste time reading the sordid details of someone else's tragedies. I listen to music or cassette tapes in my car. If possible I have breakfast and lunch with an optimist. Instead of sitting in front of the TV at night, I spend time listening to and being involved with those I love.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I use positive words. Never negative words. I use the RIGHT WORDS!

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I inject myself with optimism.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I always expect the very best for myself.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I feel good, very good, my life is going wonderfully well. I have no reason to be afraid. I never get depressed. I'm an optimist. I have confidence in the future, the people close to me love me, my colleagues respect me. I do my work well. I have no fears about the future.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

One of the best ways to make other people happy is to spread optimism and good humor. Every one of my words and actions can contribute to that.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

OPULENCE

I am ever thankful for God's riches, present as always, unchanged and abundant.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

ORDER

Order which is the Spirit is, from this moment on, a part of all my affairs, a part of the way I use my time, a part of my body, my thoughts, my mind and the world.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Now I put my life in order as I prepare to accept all the good that awaits me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

ORGANIZATION (Also see Efficiency)

I accomplish my tasks in order of importance.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I am well organized in my work.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I possess an organized and orderly mind, and that shows in the way I live.

I am very organized. Every night I draw up a list of tomorrow's activities. I establish my priorities and I stick to them.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I take time out to think about the problem at hand, and then I act scientifically.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I get the best out of my time.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

ORIENTATION (See Choice of Profession)

ORIGINALITY

I will find the original me when I eliminate all acquired perceptions concerning myself. I am eliminating them.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

OUT OF BODY EXPERIENCE

I know that I can condense my identity and appear in a distant place.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

OVERWORK

I have the right to take my time.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I have the right to live in the present.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I have the time I need to do what I want to do.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I keep my Workaholic firmly under control.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I can stay relaxed and focused on my timetable.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am relaxed and balanced. I have all the time I need to do all the things I have to do.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My days unfold tranquilly, at the pace I like. I am satisfied with my accomplishments, and with my life. I am affectionate with the people close to me, and greatly appreciated by those around me. I react positively.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

PACE

I adapt my pace to the activity I am engaged in. I make sure to work at the right pace.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

PAIN (Also see Hepatic Colic, Illness, Wounds, Anesthesia)

Soon the pain will pass. I will feel fine.

Leslie M. Le Cron, Liberate The Power In You Through Self Hypnosis, Tchou/Ariston, Forces

As soon as I press the nail of my thumb against the inside of my little finger I will block all the nerves conducting the pain.

A wonderful feeling of calm and security will pervade my body... as long as I keep pressing my thumb nail against the inside of my little finger I will feel no pain... I will feel completely fine.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I eliminate the pain.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

I relax my entire body and forget about the pain.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

I concentrate on calming my body down. I am completely relaxed,

Table of contents

and feel this sense of relaxation throughout my whole body. I don't think about the pain at all. Instead I savor this beneficial sensation of total relaxation.

As I count down from five the sensation of pain will diminish. Each number eases the pain even more. When I reach the number one the pain will be completely gone. Now I'm counting down... five... four... three... the pain is disappearing... two... one...

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Energy circulates harmoniously in me. A wonderful wave of heat and well being spreads throughout my body, which is becoming light, very light and pure, full of light and life. My pain dissolves and disappears completely in this wave of light and heat. The power of life flows and spreads through my regenerated body. I am completely healed.

Charles Baudouin, Psychology And Practise of Autosuggestion, Idegraph Publications, 1990.

Pain is sometimes caused by, and always amplified and aggravated by nervous tension and anxiety... Therefore as soon as I relax I start feeling better. And gradually, as I become more relaxed, the pain gets less and less intense. And now I feel so totally and completely relaxed that the pain is gone.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

My pain is disappearing. Soon I won't feel it at all, it will be completely gone. I'm already suffering a lot less, less and less... In an hour (or in a few minutes - set a time limit) I will not be suffering at all.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

PARALYSIS

God has not given me a fearful mind, but a mind full of power,

Table of contents

love and health. My faith is in the curative powers of God, my creator. I am relaxed and peaceful. Each one of my nerves is also one of God's ideas, and I feel revitalized, energized and healed. I give thanks to God.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

PARTNERSHIP

I find the partner I need to help with my work. Our association will be mutually profitable.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

PASSION

The only way to be happy and make a lot of money is to do what I really like to do.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

PATIENCE (Also see Understanding)

It's easy for me to be patient, understanding and just.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

When I have to wait I do so without getting impatient... by using the time to relax.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Nothing can stop me today. If I need some extra determination, I'll find it! If I need extra energy and drive, well I've got it! Whatever task or problem awaits me, I have the power and the patience to over-

Table of contents

come it.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

PEACE (Also see Joy, Love, Wisdom, Prosperity, Health, Success)

God, my Father, all my thoughts are of You. My body, my heart, my intelligence, my soul, my mind, depend on You. In You I find refuge, light and life.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

I inhale the peace of God, and exhale the peace of God for all.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

I am completely relaxed physically and intellectually. I am free. I believe in the wisdom of God and I feel my mind filling with His peace. I feel it right to the bottom of my heart and my being.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am at peace with myself and with others.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Peace is in me... peace reigns in this home.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

The current of God’s peace flows freely through my whole being, and I am immersed in the peaceful river of God at this moment.

I am relaxed and calm. I am at peace. A peace which goes beyond understanding fills my mind. Peace is in my home, in my heart, and in all my affairs.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Joy now flows freely through me, and I am at peace with life.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Table of contents

I raise my soul towards you, Lord.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

PEACE OF MIND

I am at peace with myself.
My mind is at peace.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

PERFECTION

I am whole and complete unto myself.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My life unfolds in total perfection.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am perfect.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I always try to improve myself, eliminate my faults, resist my negative impulses and become a better and more perfect person each day.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

PERFECTIONISM

It doesn't bother me to be imperfect.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I stop trying to attain perfection in myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I stop making it an obligation for me or my children to succeed at everything we undertake.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I always do my best. Each thought and action is the best I am capable of at the time. Because I'm human, I make mistakes. I accept my mistakes without blame or judgment. When I make a mistake I learn from it. I am imperfect, and I forgive myself for my mistakes.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

PERFORMANCE (Also see Self Image)

My concentration always improves when I make an effort... concentrating allows me to unite all my energies into one effort... and thus improve my performance.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I maintain and develop my image of technical performance.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

One of the best, quickest and most effective ways to improve my image and my performance is to be part of an organization which has useful goals.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

PERFORMANCE - SPORTS

In a short time I will regain my superiority.

I'm sleeping more and more deeply... more and more deeply... I take pleasure in competition because I know my performance is improving day by day... day by day my performance is improving... I

Table of contents

feel very good.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

PERSEVERANCE

It is still too soon to abandon everything, and I won't give up.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I keep trying.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I'll go that extra mile.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I tell myself to persevere and attain my objective; I refuse to be swayed by doubt and fear.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I never forget that my life belongs to me. I continue trying. If I can't make it on my own, someone else will probably help. But I keep trying and I persist.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I persevere until I succeed.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I will persevere until I succeed.

As long as there is a breath left in me I will persist. Because I now know one of the most important elements of success - if I persevere long enough I will win.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I persist with my dreams; they'll become real.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

I will stay healthy and generate new strength which will help me want to act with perseverance.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I am strong... I succeed at everything I do because I persevere... I see things through to the end... I am conscious of my power!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I want to play an active role and dedicate all my strength to attaining my goals. I will persevere despite all obstacles because I am certain that properly directed willpower can overcome anything, if the goal is just and honorable.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Once I make a decision I persevere in carrying it out for as long as I believe I am right.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

If I don't succeed on the first attempt I try again and again.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

PERSONAL AFFAIRS

I am very efficient at taking care of my personal and/or family affairs.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Editions, 1981.

PERSONAL DEVELOPMENT

I am changing my life. I experience a deeper connection with my true self. I am excited about my growth.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

Table of contents

PERSONALITY

I am asserting my real personality more and more every day.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I do what I have to do, and you do what you have to do.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I don't try to do better; I try to be different.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I don't imitate others. I try to understand my personality fully, and be myself.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I don't compare myself to others.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am not inferior. I am not superior. I am simply me.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I'm not going to let myself imitate the undesirable personality traits of other people.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I'm not here to live the way you want me to.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I make a firm decision to be myself and not an imitation of somebody else.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am me and you are you.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

Table of contents

I am me.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I am a unique being and I express my self fully, aiming for success and wealth.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I am unique and I like it that way.

Sublipower, Subliconfidence, Edi Inter, 1989.

I am unique, from head to toe. I may resemble other persons, acting and speaking like them, but I am not them, I am me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I want to acquire constant calm, imperturbable self assurance, and justified confidence in myself.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1973.

My personality is who I think I am.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

The more I express myself, the happier I feel.

Louis Proto, Self Healing, Piatkus Publications, 1990.

You are not alive to live the way I want you to live.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

PERSUASION

The most persuasive influence I have over others is my mature personality.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

PESSIMISM

I forgive myself for holding on to negativity, and now let go of it.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I will not allow my personal opinions to distort the facts in a negative and pessimistic way.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

PHOBIAS (Also see Fear, Negative Thoughts)

I am in harmony with God, and I have nothing to fear.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

My phobia is afraid of me because it knows I am much stronger than it is. I am at ease, perfectly relaxed and confident of my strength. I smile because my phobia has no more power over me. It is unimportant.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Little by little I see these fears, these ideas, these phobias appearing less and less frequently in my mind; they are getting weaker and weaker, less and less tenacious; they have less and less influence on me; I am eliminating them right now by repeating the formulation: "It's over, it's all over..."

Emile Coue, Complete Works, Astra Publications, 1976.

PHYSICAL STRENGTH (See Strength - Physical)

PLANNING (Also see Money)

Above all it is essential I obtain such and such results, which will

Table of contents

bring me closer to my ultimate goal, whether materially, or by increasing my worth or my power.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I have finally come up with a working plan, and I intend to stick to it.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Every day I draw up a list of things to do.
I determine the time required for each activity.
I allot some time for pauses, unexpected events, and a margin of error.
I draw up my list of things to do every day.
I make plans.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I study, I think, I take the time to make plans!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I do high priority work first. I set my priorities on a must-do-now, should-do-soon, and would-like-to-do-when-possible basis.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I gave myself orders and I carried them out.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I never waste my time because I plan. And since I always stick to my schedule, I have enough time to accomplish what I choose to do.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am in control of my time. My time is the very essence of my life, and I take control of it.
I create as much free time as I like, and I know how to delegate.

Christian Godefroy, The Creativity Method, Godefroy Publications, 1992.

Table of contents

Planning builds self confidence. I know beforehand what I am going to do each day. This enables me to develop self discipline, which is so essential to success.

Planning gives my life direction. I must know where I am going, the goals I wish to attain, and how not to dissipate my time. As my plans materialize I become inspired by a sense of achievement.

Planning enables me to get more fun out of life. The habit of day to day planning should include time for enjoyment of life whether it is reading an interesting book, listening to soothing music, playing golf or other sports, seeing a good movie or play or anything else that will relax my mind. To be happy I must make plans for happier living.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

When I plan, I don't just plan FOR the future, I plan so that I will HAVE a future.

This task needs to be done but I can't do it right now. I'm going to schedule a time when I know I'll be able to do it and stick to that schedule. If I don't there's a good chance I won't get to it. Now that I've scheduled it I can forget about it and concentrate on the job at hand.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I choose which Concepts, Contacts and Commitments warrant the most attention and effort. I am responsible for which of them become contractual, with priorities and deadlines. I create my own track to run on - slow, medium, or fast - in my commitments.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I finish each task before moving on to the next one.

Sublipower, Sublisuccess, Edi Inter, 1989.

Table of contents

PLANS

I am open to new points of view, perspectives and plans.

God as Understanding knows what I should know, and I am united with this universal Understanding so that I know everything I need to know.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

From now on I live in harmony with the divine plan assigned to my life.

From now on I recognize, accept and conform to the divine plan of my life, as it is revealed to me step by step.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Talking about ideas and plans needs to be balanced by trying them out. Theory and practice converge into wholeness. I field-test my ideas.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Starting today I will become the architect of my life.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

PLAY

(I am free to enjoy myself any way I want.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

I take time to play like a child.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

PLEASING OTHERS

I please everyone I meet. I have confidence in life because I have

Table of contents

confidence in myself. I know I can count on this immense reservoir of energy that is within me, and which attracts others. I radiate the energy that is mine.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I want to please everyone.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

PLEASURE

I begin the day with pleasure!

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

PLEASURE - SEXUAL

I deserve love and sexual pleasure.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

PLEURISY

I call on the forces of nature to help heal me. I absorb the curative forces of nature and unite them with my own. I eliminate the gas and other waste products which are making me ill.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

POSITIVE MENTAL ATTITUDE

I like people and people like me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I am learning to love instead of suffer! I am learning to love what I hated, and transform negative forces into positive energy. I am forging a path towards happiness. I react positively, even if it takes a great effort at first. And I remain positive even if an adversary is not as positive as I am. I notice the changes this is producing in my life and in the way people see me.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

Whatever the situation, I always adopt a positive mental attitude. And I succeed thanks to my positive mental attitude.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Every morning I am going to condition my mind and instill a positive mental attitude for the rest of the day.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I am developing a positive mental attitude.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

POSSESSION

I can have anything I want!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

POSSIBILITY

I always exceed my possibilities.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

POTENTIAL

I awaken the giant within me!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Table of contents

I nourish my real potential.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

POVERTY

I will buy it! I'll get it!

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

My inner Guide is the spirit of plenitude and will preserve me from all misery. I will lack nothing.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

POWER (Also see Self Confidence)

I can do anything.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I can.
I can do it if I believe I can!
I can make it if I believe I can!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I possess a great and marvelous power.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

I could do it.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

When I want to do something within reason, or when I have to do something that is my duty to do, I always imagine that whatever I do is easy. May words like difficult, impossible, I can't, it's too much for me, I can't help myself... and so on, disappear from my vocabu-

Table of contents

lary. They are not English. I don't understand them. What I do understand is: it's easy, and I can do it.

Emile Coue, Complete Works, Astra Publications, 1976.

Each day brings me more strength and power.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Day by day, in all ways, I am becoming more powerful and confident.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I possess vast power which I have not yet realized.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am united through my inner Guide with an inexhaustible source of health, courage, abundance and prosperity. It fills me with strength and spirit. It provides me with everything I need to move forward ceaselessly. I am confident in its power; it is my strength and my wisdom. It makes me strong and independent of things and people. I am persevering, strong and courageous. I am strong!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

My constant contact with God gives me the power of an eagle soaring above the clouds and the humility of a gentle dove.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

POWER - PSYCHIC

I am learning how to use my mind in extraordinary ways, like mastering my psychic powers, and I am becoming a different person.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

Table of contents

POWER - SPIRITUAL

I can touch the sky. I can be big. I can fly if I want to - I can do anything.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

POWER - SUBCONSCIOUS

I have unshakable faith in the power of my subconscious... unshakable faith.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

PRAISE

S/he worked hard to get the promotion s/he wanted. I wish him/her well.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I allow others to love me and praise me.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

PRAYER

God has received my request.

Richard Ingalese, The Power Of The Mind, Dangles Publications, 1981.

May my comings and goings be done in all honesty, and in the full light of day; not in disorder and drunkenness, not in licentiousness, not in anger or envy. I place my faith in our Lord Jesus Christ, I care nothing for the needs of my body, or for my frivolous desires.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

Table of contents

I pray, I really pray.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

PRECAUTIONS

I care for myself enough not to expose myself to physical risks or emotional damage.

Louis Proto, Self Healing, Piatkus Publications, 1990.

PREGNANCY

I await my pregnancy with pleasure.
I will be happy to be pregnant.
I want to get pregnant.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I feel marvelous... I know the birth will be easy.

I'm enthusiastic about the prospect of having a wonderful child.

My thoughts have a positive influence on the health of my child... on his development. If I am assailed by negative thoughts I always remember that they can hurt my child... and I immediately replace them with joyous, optimistic thoughts of a radiant future.

Everything is going fine... I am firmly optimistic... firmly optimistic. My pregnancy is progressing normally... and will continue to do so right up to the birth, which will be easy... very easy.

I know that my child is developing perfectly. I am sure to have a beautiful baby... a superb, magnificent child.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I will not suffer from morning sickness.
I'll get my figure back after giving birth.

Table of contents

I am thrilled at the idea of waiting for my baby.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

PREJUDICE

I am now dissolving all my negative and limiting prejudices. They no longer have any power over me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

PREMATURE EJACULATION (Also see Impotence)

I control my ejaculation.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

PREOCCUPATION

Everything is going very well.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

PRESSURE

I choose not to spend my life trying to live up to other people's expectations. I don't let others pressure me with their beliefs unless I accept them.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

When external pressures become too strong I call on my inner strength to combat them; to do this I mentally review the successes I

Table of contents

have already achieved.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

PRIDE

(I am proud of my accomplishments and goals.)

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

PRIORITIES

I have enough time for my priorities: 80% of the time, every day, I work on two out of three priorities.

I set deadlines and time limits for myself, and I ask others to do the same.

I regularly sit down and review my priorities.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I re-evaluate my priorities.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I am a person who is responsible and I act in timely manner to reach my goals and priorities.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

PROBLEMS

Before attacking a problem I try to formulate it in terms of "How to do what for whom?"

Before attacking a problem I ask myself, "Am I really determined to resolve this problem?"

Table of contents

If the problem consists of choosing between a relatively small number of clearly defined options, I use the “Pros and Cons” method.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

All right, here’s the problem. I look at it calmly and carefully study its elements. I consider its implications. I take time out for careful reflection. And above all... no emotions!

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

This is my problem. I can do anything I want about it. I know the answer to everything. I will find the solution.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

It works!
My subconscious knows the answer to all my problems.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Tonight my subconscious mind will resolve the problem of — (specify). When I wake up tomorrow morning I will remember the solution, either as a dream, or as a flash of inspiration during the day.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

In quietness I find the answer to every problem. Everything I need to know is inside me.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am learning to see problems on a higher level of understanding. They seem to solve themselves under my very eyes. I try to approach a problem as if I had no connection to it whatsoever. This prevents me from clinging to prejudices and ideas which are impossible to realize, and allows me to access a higher level of understanding. In fact a problem can only be solved when it is completely understood.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I seek an end to all problems.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I know that the resolution of my problem depends on me: the answer is in me because God is in me. I now feel calm and relaxed. I am at peace. I know that confusion never comes from God. I am now in harmony with the infinite. I believe and know that infinite wisdom will reveal the correct solution to me.

I know that all problems can be solved when the mind is calm. I confide in God because He knows the answer. I am at peace.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I attack the problems of life without being afraid to make mistakes, and thus I break free of my chains.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I'm not afraid of problems, I solve them. I don't try to ignore them, I confront them. I don't avoid them, I conquer them!

I know that every problem's solution has a key. Therefore the clearer the problem is, the better I can determine its solution.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I can easily resolve — (specify the problem).

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I look at each problem as an opportunity.

Christian H. Godefroy, Self Confidence: The Subliminal Method, Godefroy Publications, 1987.

I overcome any problems easily. My life is enjoyable and positive.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

I know my victory over my problems is certain because I know that my intelligence is a part of God.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Table of contents

I know you have the answer to this question and I know you will give it to me when you are ready. I will wait patiently, in complete confidence.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I see you with the eyes of love. There is a harmonious solution, and I accept it now.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Easy is right.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Only living beings have problems. The more problems I have, the more alive I am. I am happy to have these problems.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I relax and let divine wisdom and the divinely accurate action of my subconscious mind resolve this problem. I disassociate myself from the problem and let things take their course.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

I offer thanks to my Father for His Divine solution.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

PROCRASTINATION

Today I will do my work without wasting time.

I have finally decided to correct my habit of putting things off for later.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Right now is the best time.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Table of contents

This task is important and it's the kind I might procrastinate on or forget to do at all. I'm going to do it now and get it out of the way. It won't be hanging over my head and I'll be mentally free to concentrate on my other work or just relax.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I act immediately.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

It is my duty to finish what I begin.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I stop worrying about what I can't do now, and do what I can do with all my heart and soul.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I always do what I have to do on time.

I immediately transform all indecisiveness into ACTION, and so I stop stalling.

I don't let chance decide for me. Since I can make decisions rapidly, stick to my convictions and act in consequence, I have no time to stall around.

I have learned to recognize all the arguments that tend to drag me down, and I avoid them instead of avoiding the tasks I encounter in the course of doing my work.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I do everything I have to do at the right time.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I do it now!

John Clark, Do It Now, Godefroy Publications.

I'll do it without wasting a minute.

W. Clement Stone, Passport To Success, Godefroy Publications, 1962.

Table of contents

I'll do it right away... I'll do it immediately!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I set to work immediately and passionately.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I will not neglect today's tasks by putting them off for tomorrow, because I know that tomorrow never comes.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I profit from each day: I don't put off what I have to do, and I do it with joy.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

When I'm faced with a problem I solve it right away if I have all the facts. I don't put off making decisions.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

If I want to succeed I have to start this very day.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I do everything I undertake with care, and I complete it before moving on to some other occupation. I never put off for later what I should and can do now.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

PRODUCTION

I am satisfied with the results produced by my working time.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

PRODUCTIVITY

Whenever I make a change in my life, from the current way I am

Table of contents

doing something, I anticipate a temporary drop in productivity and efficiency. I don't worry if a change I made in profession or lifestyle isn't bearing fruit right away. It takes time for a change to be assimilated. As familiarity and confidence rebuild, productivity will increase again. I don't stew, I let it simmer for awhile.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

PROFESSION (Also see Wealth)

I deserve to have a profession that satisfies me 100%, and which gives me the opportunity to develop and enrich myself beyond my expectations.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

There are experts and professionals in my field who will help me learn, improve and excel. They will respond to my sincere, thought-out questions and concerns.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

PROFIT

I profit from the present moment.

Sublipower, Sublisuccess, Edi Inter, 1978.

PROGRESS

I have everything I need to make profitable progress under the present circumstances.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

Table of contents

I move forward with all my strength.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I develop affirmative statements, about five words in length, describing my correct performance, in the present tense. I relax and listen to myself state the affirmation, and visualize the accompanying action or feeling.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am pleased with the progress I am making. I'm going to tell my best friend about it.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I move forward!

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I want to do better.
I want to do more.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

PROJECTS (Also see Debt, Money)

I set a deadline for every project.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

This project does not have to succeed, and if it fails the world won't come to an end. But I want it to succeed, and so I'm going put all my energy and enthusiasm into it. What do I risk by doing that?

John Clark, Do It Now, Godefroy Publications.

Creative wisdom is at work through me to bring all my projects and plans to fruition.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

Table of contents

PROMISES

Every time I promise something I keep my word faithfully and exactly.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

PROMOTION

I am qualified for the promotion to (specify the job you wish to get) because everyone appreciates me and because I always demonstrate goodwill towards my employer and my colleagues.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I have a right to my place under the sun. I carve out this place through my work, through the contacts I make, through the dignity of my life, through friends and the help I give to others.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

PROSPERITY (Also see Happiness, Budget, Love Of Life, Health, Peace, Success)

Every day I am acquiring better health, a greater love of life and more and more prosperity.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

My interests are prospering day and night.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I accept and believe in prosperity for myself.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

Table of contents

I organize my budget well, and my affairs prosper.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I believe with all my heart that health, peace, success and prosperity in my affairs are mine to enjoy. I see myself under the spiritual sign of peace, harmony and inner development, an image which is completely oriented towards success and prosperity.

I impregnate my subconscious mind with ideal images of prosperity and success. I rely on the infinite source from which everything I need flows. I listen to the voice of God in me. His voice guides and directs me in everything I undertake. I feel linked to the wealth and generosity of God. I believe and I know that there are new and better opportunities in store for me. God will reveal them to me.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I deserve prosperity and happiness. From now on I will be prosperous and happy.

I am now ready to accept all the joy and prosperity that life offers me.

I am blessed with financial prosperity. Each day makes me more prosperous.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have divine guidance all day long, and everything I do prospers. Divine justice and the law of divine order govern all my undertakings, and everything I do succeeds.

I know that prosperity means spiritual growth from all points of view. God helps me succeed in mind, body, and in the things I do. God's will is constantly at work in me, bringing me health and wealth, and making me an expression of divine perfection.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

Table of contents

PROTECTION

I remain under the protection of the Most High.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am never afraid because I know that the Divine Presence which is in me is my saviour.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am safe and secure at all times. Love surrounds me and protects me. All is well.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I am guarded, I am protected.

George Barbarin, How To Overcome Fears And Anxiety, Dangles Press, 1974.

The Spirit walks ahead of me, showing me the path... I have absolutely nothing to fear, the Spirit protects me... the wisdom of the Spirit guides me in all my actions.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

PSYCHIC SHIELD

I will completely reject and ignore all negative and pessimistic "facts" which I can do nothing to change.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

PUBLIC SPEAKING

I like talking to people. When I address a group I feel self confident and relaxed.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

As soon as I begin speaking... I feel transported... I speak with conviction and warmth.

I could speak for hours... ideas keep coming to me one after the other.

At a meeting or conference... I am more and more likely to get up and express my ideas.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I have the energy, assurance and complete self control I need to speak in public. I speak easily and eloquently.

I feel relaxed in public. I feel at ease in any situation. I have complete confidence in myself and in what I have to transmit to others. Everything will be fine.

I am the most important thing I have to transmit to others. I am perfectly at ease. I am in perfect control of myself. I know exactly what I have to say. I am perfectly at ease in public.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I have nothing to fear. I'm going to concentrate on the message I wish to pass on to my audience and not on myself - I have confidence in the power of my own mind.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I feel comfortable in public. I feel at ease under any circumstances. I have complete confidence in myself, and in what I have to transmit to others. Everything will be fine.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I am the most important thing I have to transmit to others. I am perfectly at ease. I am in perfect control of myself. I know exactly what I have to say. I am perfectly at ease in public.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

Table of contents

PUBLISHING

Infinite Intelligence paves the way for the acceptance and publication of my writing.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

PULMONARY DISEASE (See Lung Disease)

PUNCTUALITY

I arrive on time for my meetings.
I arrive at the prescribed time.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am always punctual.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I rarely hurry, and I feel good about myself.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

PURIFICATION

Every breath I take cleanses my body totally. With every out breath I rid my body of toxins.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I eliminate gasses and all other waste products from my body.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1973.

I clean my mind with the waters of love and life.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 198

Table of contents

QUALIFICATIONS

I have the necessary qualifications, and everything else I need to succeed.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

QUALITY

It is my —— (specify which quality) that people appreciate in me.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I have the potential to develop all the qualities I admire in others.

Sublipower, Sublicontrol, Edi Inter, 1989.

I cultivate and develop my qualities.

Sublipower, Sublicontrol, Edi Inter, 1989.

I acknowledge my qualities, as well as those of others.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

QUALITY OF LIFE

The quality of my life improves day by day.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

RADIANT

I am a being of light. I am energy. I am whole as a spirit, mind, and body.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

The more radiant I am the more I attract good things.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

REACTION

I am perfectly capable of reacting in a happy and healthy way, no matter what happens to me.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

READING

I look at books as working tools.

Sometimes I read very quickly, sometimes very slowly, depending on what my objective is.

I have an alarm system that goes off every time I find myself getting distracted, reading a sentence over and over without really taking it in because I'm thinking about something else.

When I finish reading something I ask myself what I got out of

Table of contents

the book or article, and how I can put this information to good use.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Realization

All my thoughts tend to materialize in my life.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

What the mind can conceive and believe, it can also realize!

W. Clement Stone, Success Through Constructive Thinking, Godefroy Publications, 1978.

I have the right to realize my desires.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I can do anything I believe I can.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I'll do it!

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I can do anything through the power of my subconscious mind.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I realize what I want to do.

Christian Godefroy, Mental Dynamics Seminar, Godefroy Publications, 1978.

The universe is now paying me to do what I really love.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

Everything I have to do is simple and easy.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

REALIZATION - SELF

Every day I take a small step towards self realization.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

REALISM

I take care to always remain in contact with reality.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I am practical and realistic, and I keep my feet planted firmly on the ground. But I also give myself the freedom to live according to my ideals.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am a realist.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

REBIRTH

Today I start a new life.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Just as the pain of childbirth is forgotten, I experience each aspect of my life as a manifestation of peace and joy. The past is dead. I am free of all suffocating prejudices. I am reborn every instant, I triumph in my rebirth and my new and happy being.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

RECEPTIVITY

I am receptive to healthy ideas and techniques.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

REFLECTION

I determine the time a task will take before starting it.

I sit down from time to time to reflect on things that are important to me.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

I always find a solution if I take the time to reflect.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I give myself the time to reflect on subjects that are important to me.

I write these subjects down in my agenda so I won't forget about them.

I know that reflection takes time, and that this time is not necessarily directly connected to solving my problems: a time of reflection can also be a time of maturing.

Whenever possible I either write down or record the fruit of my reflections.

Whenever possible I allow myself time for reflection before making a decision.

As I reflect I establish "satisfaction criteria" concerning the results I hope to achieve from the decision I make.

I use my time of reflection to gather ideas which I would then note down in my agenda.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

I want to think about things, because every profound idea contains information that is only revealed through reflection.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

REFUSAL

I always say no when it's the right thing to do.

By not giving in to the demands or influence of others I become more aware of my freedom and my self control.

I am able to say no easily. I am self confident, and always in control of my life.

I never feel obliged to do something I honestly haven't chosen to do. I say what I think. I am frank, direct and honest. I know what I want and where I am, and I express my opinions clearly and without hesitation.

I allow no one to sell me anything against my will. I live according to my own decisions, without ever giving in to pressures from salespersons or anyone else.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

REGULARITY - ABDOMINAL

My solar plexus radiates heat.

I feel a source of heat in my abdomen.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

REGULARITY - RESPIRATORY

I am all breathing, there is something breathing inside me, I feel my rib cage rising and falling like a boat on the ocean, my breathing

Table of contents

is calm, I listen to my breathing. I am breathing gently.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

REJECTION

(I confront my fear, rejection and guilt and let go of them. I am going to discover and overcome these feelings which are obscuring my real light.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I allow myself to be, without the need to prove myself to anyone. I live my power without fear of defeat or rejection. I control my dreams, my life.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

REJOICING

It's good for me to have fun and rejoice, and that's what I do!

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The more I enjoy myself, the more alive I feel.

Louis Proto, Self Healing, Piatkus Publications, 1990.

RELATIONS - COMMERCIAL

I can never control another person; I can only influence him. If I expect to be able to control him I'll probably be angry and frustrated. If I accept that I can influence his free choices I'll be calmer, learn more about him, and be much more effective.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Table of contents

RELATIONS - FAMILY

I love my family.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

My relations with my family are improving.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

RELATIONS - HARMONIOUS

I have the right to be happy with my chosen love.

My relationship with X is becoming more and more harmonious, happy and enriching every day. We are evolving together. We always compliment each other perfectly. I give love and receive abundance in return. I live in the abundance of love and life. X is abundance, I am abundance.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am now ready to get involved in a fulfilling and happy relationship.

I am ready to have harmonious relations with everyone.

Divine love is now working through me to establish a perfect relationship with ——.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The spirit in me speaks to the spirit in —— so that there is only harmony, peace, love and understanding between us.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Table of contents

RELATIONS - HUMAN

To improve my human relations I accept people as they really are and not as I would like them to be.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I choose my relations. I deliberately seek out people with high moral values who see the beauty in life.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I am not interested in relating to anybody who does not respect me as much as I respect myself.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My relations with people are becoming happier and more fulfilling every day.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

When I change my inner self, I also change all my external relations.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

From now on my relations with others will be happy, satisfying and full of love.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have confidence in myself and I like being with other people.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

I have fruitful and pleasant relations with the people I see (both professionally and socially).

If I am with someone, I give them all my attention.

I try to discern what other people are feeling.

I may take a calculated risk of breaking off a relation if that is the

Table of contents

only way I can work things out.

I am careful to concern myself with only one pole of the relation at a time: me, the other person, or the situation.

I periodically review my personal relations and evaluate them, dividing the people I spend time with into positive and negative categories. I then determine those with whom I'd like to try and improve my relations, and those with whom I'd like to establish a relation, but haven't done so as yet.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I have very easy-going human relations.

I understand the natural laws governing relationships, and I work in harmony with them.

When I am in touch with my Real self, all my relations are cordial and effective.

Any sincere effort to improve my human relations will be rewarding.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I like people a lot, and I like to be nice to them.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

I like to thank others.

The more I like myself, the easier it is for me to like others.

I am available for other people.

I know how to listen. I encourage people to talk about themselves.

I listen to them, and they confide in me.

I find it easy to meet new people.

I accept people the way they are.

I like to demonstrate my care and thoughtfulness.

I am sincerely interested in other people.

I wish others only positive things.

Christian H. Godefroy, Human Relations and Communication: The Subliminal Method, Godefroy Publications, 1987.

Table of contents

I will try to be a little more friendly towards others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I will do all I can to understand and maintain good relations with —— (specify such and such member of the family, colleague, etc.).

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I imagine myself at my best and I project that image to others in order to improve my relations and become a happier person.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am going to practice the technique of self-relaxation whenever I find myself in a situation that may precipitate an argument.

Whenever I find myself baited into a heated argument I will change the subject or will remind myself to remain calm and realize that the other person may have reasons for feeling as he does.

I am going to give myself the daily suggestion that I will talk more to people, act more friendly and initiate the kind of conversation that will enlist the interest of the other person.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I seek and find the essential quality of each person I meet.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am in harmony with others.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I treat others as I would have them treat me.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I want to maintain the friendly and harmonious relations I have created with the people around me, my family, friends and colleagues.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

The only kind of relation I can have with anyone, no matter who

Table of contents

that person is, is one of love, understanding and peace. I am a free expression of God.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

RELATIONS - PERSONAL

People are important to me. I like the people who are a part of my life, and I know they like me.

I naturally attract honest and sincere people who respect my opinions, as I respect theirs.

My personal relations are warm, meaningful and enriching. I am always honest and sincere with the people I meet, whatever the situation, and whatever kind of relation we have.

I am worthy of confidence, I am responsible, and other people greatly appreciate these qualities in me.

I am always ready to give someone the benefit of the doubt, whatever the situation. When I'm uncertain, I always imagine the best possible scenario.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

RELATIONS - PROFESSIONAL

The basis of all the thoughts, words and actions I use to address my superiors and colleagues is my ever present good will.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

My relations with associates are governed by the law of harmony.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Table of contents

RELAXATION

Every time I take a breath, and every time I exhale, I relax more and more deeply.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Each inhalation and exhalation relaxes me even more.

Each new movement makes me a little more relaxed. I breathe in deeply and hold the air for the time it takes to count to five. I exhale very slowly. My body is feeling more and more rested, making me even more relaxed. And the more I relax, the better I feel. The feeling of being completely relaxed is very pleasant and reassuring.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I feel more and more relaxed.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I know how to relax and let go. I can flow with the current.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I know how to organize spaces of relaxation, even during very intense activity.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am relaxing now. I am at peace.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am going to take time each day for some form of recreational relaxation to balance my day with work and play.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

My body is loose and relaxed.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

Every time I do my alphagenic induction exercises I relax quickly

Table of contents

and deeply.

I do relaxation exercises every day.

I feel completely numb and insensitive to the position of my body. I am cut off from the people around me. I feel secure and in control of the situation.

My body is relaxing more and more. I am becoming numb to all sensation.

I feel relaxed from head to foot. Every part of my body is relaxed, and I stop analyzing my feelings. I am not thinking about anything except relaxing as I watch the indicator continuing to descend. Soon I will be completely impervious to everything around me.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

With each breath I become more relaxed, with each breath my body becomes looser, heavier and more numb.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I am falling asleep. My whole body is resting. I will awaken in half an hour, at exactly —— (specify the time), rested and full of energy. I am so light I feel as if I'm floating!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I relax every night.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I can relax.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I feel good, very relaxed.
A feeling of well being gently spreads through my body.
My scalp is relaxing little by little.
My forehead and face are relaxing.
My tongue is loose in my mouth.
I relax my throat, my tonsils, my vocal chords.

The muscles around my eyes are relaxing.
My neck and back are loosening up.
My tension is dissolving day by day.
My breathing is unobstructed and is getting fuller all the time.
My diaphragm massages my internal organs.
My solar plexus is relaxing.

Sublipower, Sublirelaxation, Edi Inter, 1989.

(I am going to practice relaxation as a way of life. I am going to practice relaxing each part of my body (progressive relaxation) until I have learned to master the technique of relaxing my entire body (complete relaxation). When my body is relaxed my mind will relax. Relaxation is the best antidote for worry. I am going to make good use of my new habit of hypnotic self-induced relaxation.)

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Relaxing is important to me, and I always make sure to get my required dose. I use my time not only to pursue my goals, but also to appreciate the beauty of life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Everything is relaxing... everything is opening... becoming peaceful and relaxed... my head is heavy, my jaws are loose... my body becomes calmer and calmer every minute.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

RELAXATION - DIGESTIVE

My solar plexus radiates warmth.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

RELAXATION - MENTAL (See Inner Peace)

Table of contents

REMUNERATION (Also see Job)

I have a wonderful job and I am very well paid. I offer a valuable service and do my work admirably.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

REPARTEE

I can answer any question at all without hesitating.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

REPRESSION

As I count to ten I start becoming conscious of these emotions. I feel them more and more strongly. I will feel them intensely, in every fiber of my being.

Charles de Liguori, Hypnotism, de Vecchi Publications, 1975.

REPROACH

I remind myself that my relatives, my spouse, my friends, my boss, my children and all kinds of other people I come in contact with will often disagree with my behavior, but their reproaches have absolutely nothing to do with my inner self.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I start accepting certain attitudes which I have chosen to adopt but which others may disapprove of. Therefore, if a relative or my boss or a neighbor or even my spouse reproaches me for such and

Table of contents

such behavior, I find it completely natural that they do so.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

No more blaming!

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

RESENTMENT (Also see Forgiveness)

No feelings of resentment can enter my mind because I have a spiritual understanding of all beings. I contemplate the love of God in people, which blesses me and fills me with goodness.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I give up all my resentment; this done I find I can be honest with myself.

I reject my feelings of resentment; I use my intelligence to find ways to spend my days fruitfully. I forget the day's setbacks and, above all, I stop being obsessed with the numerous injustices I suffered in the past.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I forgive you. I may not approve or agree, but I can forgive. I can let go of the past and wipe the slate clean. I know better than to expect atonement. I let go of revenge and resentment. Our differences are in the past. I am in control of the present and I can forgive you in the present. I can leave my anger behind.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I want to get rid of all my bad memories, eliminate all hate and resentment from my heart and retain nothing which can degrade or belittle me.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Table of contents

RESOURCES

God is the infallible and unlimited source of all my resources.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My mind is strong and its resources allow me to control my body, my emotions and my thoughts.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

RESPECT (Also see Consideration)

I earn the respect of others.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am respectful and listen to people who have experience.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

First I respect myself, then I respect others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I respect myself enough to say ‘yes’ only when I mean it.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I respect myself. I respect my values, my thoughts, my ideas and acts. And I respect myself the most when I stick to the path I have chosen.

I have a healthy attitude towards myself. I really like myself. I cultivate a very positive self image, and a deep respect for who I am.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I respect others and they respect me. Every person I meet is important to me. I can easily create a feeling of respect and confidence between myself and others.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

Above all I respect myself.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

RESPONSIBILITY

(I am completely responsible for my thoughts, feelings and actions.)

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I consider everything that happens to me as being my fault.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

I have to accept my responsibilities with joy in order to relax my Real Self.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I will leave nothing to chance because chance does not exist, and the success I aspire to depends solely on myself.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I assume responsibility for my strength, my happiness, and for my positive and healthy attitude; I am responsible for my past, present and future.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am grabbing hold of my life.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am happy to realize that I am not a victim of life's circumstances.

I am creating the happy life I lead. I am the author of my own life story.

I don't need to make up excuses, and no one is obliged to assume my responsibilities for me. I carry my burden with pride and joy.

Table of contents

Every day I recognize and assume responsibility not only for my actions, but also for my emotions, my thoughts, and even my beliefs.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am in control of myself and my environment. I take charge of myself!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am responsible for what happens to me.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I am responsible for my life.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am responsible for myself because I have chosen to be so.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I am responsible.

Sublipower, Sublicontrol, Edi Inter, 1989.

I want more responsibilities.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

REST (Also see Sleep)

I always allot myself sufficient time for rest and relaxation. I get enough sleep, and my sleep is deep and regenerating.

I give both my mind and body enough rest, but I don't depend solely on rest to recharge my energy.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am resting peacefully.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

As long as I don't move and don't get upset I am in perfect repose.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

REST - MENTAL

When one minute has passed I will count from one to seven. When I reach the number 7 I will emerge from my state of mental rest and feel as if I had slept deeply for two hours.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

RESULTS (Also see Work)

I get more done because I work harder. I like to make that extra effort and obtain better results.

I feel great satisfaction in knowing that I work hard and well. I try to be more efficient and get better results every day.

I improve my results by concentrating my energy and attention on what I am doing. When I have a task to accomplish, it is the only thing I think about.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Infinite Intelligence shows me the best ways to get better results.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

I am getting better results at work every day. I find my work more and more fulfilling.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I let the results come naturally and effortlessly.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

Table of contents

From now on the divine light within me produces perfect results in all aspects of my life.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

RESULTS - SCHOLASTIC

My interest is growing day by day and my scholastic results are improving. I am doing everything in my power to attain my goal.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

RETIREMENT

I am going to make my golden years interesting and meaningful. I'm not going to be a stay-at-home just because I am past 60 or even 70. Growing old graciously means practising being kind, unselfish and understanding.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

REVENUE (See Income)

REWARD

I reward myself with gifts!

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I give myself what I want; I feel I deserve it.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I reward myself when I bring a project in on time.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

Table of contents

(I deserve this reward.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I will spend this Saturday doing something I really want to do. I don't mean next month. I mean this Saturday. I will enjoy being alive and being able to do it. I deserve it. There will never be another me. I will spend at least one day a week on ME!

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

When this project is finished I'll buy myself the new suit I've been wanting.

John Clark, Do It Now, Godefroy Publications.

When this job is finished I'll relax and have something to eat.

John Clark, Do It Now, Godefroy Publications.

When I complete this assignment I'm going to reward myself with my favorite —— (specify which food, item of clothing, TV show, movie, sports or leisure activity).

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

If I finish all this today I'll go to a movie tonight.

John Clark, Do It Now, Godefroy Publications.

RICHES (See Wealth)

RISK

I accept responsibility for some of the risks involved in the decisions I make, because taking calculated risks is the only way to acquire experience. Therefore I always ask myself this question: 'If this fails, am I ready to assume responsibility for the consequences?'

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

I risk nothing if I fear nothing.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I take risks that may complicate my life, but which could prove to be extremely profitable.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

My path is a luminous one of sunshine and promise. I follow it with joyous anticipation. When I take a necessary risk, I look ahead, anticipating the best, and never turn back.

I reduce the risk of running risks by informing myself as much as possible in advance. Then, once my decision is made, I accomplish each stage with the determination to succeed.

I take positive risks which always bring the desired reward, and contribute to my health and well being.

I only take risks which provide me with even more positive energy, and which contribute to my well being, as well as to the well being of those close to me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

RIVALRY

I no longer feel any rivalry with my neighbors.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

ROUTINE

I take risks to break the routine. For example, I take unplanned vacations, with no reservations, no maps, telling myself that whatever happens I am capable of dealing with any situation. I apply for a new job, or talk to someone I've avoided in the past because I was

Table of contents

afraid of what might happen. I take a different route to get to work, or I eat at midnight instead of at six. Why? Because it's different, and because I feel like it.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

SADNESS

If I sometimes got sad or bored, moody or overcome by dark thoughts, I know that this will no longer happen, and instead of being sad, instead of feeling melancholic and dark I will be joyful, joyful for no reason perhaps, but joyful all the same, just like I got sad for no reason in the past. And what's more, even if I have reason to be sad, real reasons that cause me to feel dark and melancholic, I will not do so.

Emile Coue, Complete Works, Astra Publications, 1976.

I will fill this day with my laughter; I will fill this night with song. I will never have to work to be happy; instead I'll keep myself too busy to be sad. Today's happiness must be enjoyed today.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

SALARY (Also see Work, Value)

My salary is in accordance with my integrity and honesty. I exploit my talents to their fullest. I am appreciated and sought after, and I am indispensable. It's wonderful!

My salary is in line with my spiritual values. My revenue corresponds to my faith and my expectations. My wealth depends on the Universal Substance, and the degree to which people accept me determines the amount of my salary. I accept all the good that comes

Table of contents

my way, here and now.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

SALES

I am learning about the marketplace. I'm widening my base of contacts. The people I call need my products and services.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Starting today my sales will increase every day.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I will develop my understanding of people, of myself and of the merchandise I am selling in order to multiply my sales.

I will become the top salesman in my department because I am unique.

I will be the greatest salesperson the world has ever known.

I will work harder than ever, pushing my body to its limit, and then I'll do even more. I'll make more contacts than ever, more sales than ever, and I'll make more money than ever.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I'm not just any salesperson. I am an experienced salesperson. I am a champion salesperson.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I am a spiritual magnet, attracting clients who are interested by what I have to offer. The service I give is improving day by day. I am highly successful in everything I undertake. I bless everyone who comes into my store, and treat them well. All these thoughts are now filtering down into the deepest part of my subconscious mind, transforming my life into one of abundance, security and peace of mind.

Table of contents

It’s wonderful.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I am an excellent salesperson. I like to sell and I appreciate the numerous rewards my profession offers me.

I always put in the time required to find new clients. It is natural and easy for me to generate new business.

I always take care of details related to my work. I like everything that has to do with sales, and I always have the time to pay attention to details.

I have a great talent for sales. I am a professional salesperson, and it shows.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am going to start out every morning with the idea that this is going to be a good day for me, that I am going to experience an inner feeling of confidence, a feeling that I can sell almost anything to anyone, that I can make more sales than I ever have before.

I believe in the usefulness and value of what I am selling.

I am going to train myself not to do all the talking, but to listen well, ask questions so that my client is made to feel comfortable and not high-pressured into buying something against his better judgment.

I am going to read and study as many books as I can, pertaining to the psychology of selling and apply whatever knowledge I acquire.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Phone calls lead to appointments; appointments lead to sales; sales lead to referrals.

Each person I contact has the potential of opening up a world of new customers and referrals.

I am taking charge of my inner life by choosing my self-talk. I warm up mentally by focusing on effective self-talk and I prepare

Table of contents

thoroughly for every sales interaction.

I am thankful to have this opportunity to present myself and my product.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

My sales are increasing every day.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

Despite all the people who have come before me, if I constantly try to surpass my own record I will constantly make progress, more sales and lots of money.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

SALES - REAL ESTATE

Infinite intelligence will bring me the right buyer for this house, someone who needs it and will benefit from it. The person will be attracted to me through the creative intelligence of my subconscious mind, which commits no errors.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

SATISFACTION

I always get what I need when I need it.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I tell myself that I did the best thing at the best time.
I am satisfied with myself at the end of the day.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I feel good about myself, and all aspects of my life provide me with great satisfaction.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

SAVINGS

I am fully insured (or protected by my savings).

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Because I know how to manage my money I am always able to save a part of it. I set myself monthly and annual savings goals, and I respect them.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

SCHOOLWORK

From now on I will concentrate totally on what my professors are saying.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

From now on I will concentrate on what my teachers at school are saying... I will not let myself get distracted... I will raise my hand whenever I know the answer to a question... I will participate enthusiastically in all my classes.

I will do my homework conscientiously. I will concentrate on my lessons.

I won't let myself get distracted. I won't do anything else until I've finished my homework, and prepared for the next day's courses.

I'm doing much better in school... I'm happy with my results.

Day by day I am improving my performance at school... I work with joy... and my work is improving day by day... day by day my schoolwork is improving.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

Table of contents

SECURITY

Security is found in myself.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Intimately united with you, my inner Guide, I am stronger and stronger in all situations. I feel secure under your protection and guidance. I am independent of exterior circumstances, things and people. You help me and thanks to you all obstacles become incentives. Your strength is my strength. Your supremacy creates my superiority. You make everything succeed for me, and transform all things to my advantage.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

(I have what I need. I will always have what I need.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am at home. I am comfortable as I move into a deeper connection with my true self. I am flexible and secure in my life.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I try as much as possible to eliminate external explanations from my behavior, and external circumstances from my life, my thoughts or my feelings.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

SEDUCTION

I am responsible for keeping myself physically attractive, clean and desirable for my husband.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I am becoming more seductive every day.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

I am seductive.

Charles Baudouin, Psychology And Practise of Autosuggestion, Idegraph Publications, 1990.

I want to make a favorable impression on ——.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

SELF ACCEPTANCE
(Also see Self Confidence, Self Expression)

I continue searching for the best in myself. I accept myself the way I am, and at the same time I do what is required in order to improve myself and gain ever greater satisfaction.

Dr. Maxwell Maltz, Psychocybernetics and Self Accomplishment, published by A Different World Ltd. 1970.

I accept my situation and I feel perfectly good about it.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I accept all my feeling as part of myself.

I like myself and accept myself the way I am.

I don't have to try and please anyone, I please myself and that's what counts.

I like myself the way I am, and I feel better and better.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have the right to be myself.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I like who I am, and live each day in the freedom of self acceptance and self confidence, and with the joy of expressing myself fully.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I like and accept both my body and my spirit.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

Table of contents

I exercise my right to self acceptance.

I am learning to accept myself.

I accept myself for who I am, and I don't try to imitate anyone else.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I stop concerning myself with social popularity. I am working on accepting myself.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I accept myself and I accept others.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

(I stand tall and shine brightly. I appreciate myself and respect myself.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I'd make a bad somebody else, but I'm the best 'me' there is.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

SELF AFFIRMATION

Here I am. I have as much right to be here as anyone else. I matter.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I have the absolute right to be who I am, to think what I think, to feel what I feel, and to want what I want.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

I have the right to say 'NO' to someone without losing their love or friendship.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

Table of contents

I have the right to affirm myself, and it is to my advantage to communicate. I have the right to ask for what I want. I give others the freedom to say ‘yes’ or ‘no.’ If I don’t express what I want, no one will know and I’ll always be dissatisfied.

I have the right to have needs, and to fulfill them, as long as it doesn’t harm anyone.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

SELF AWARENESS

I know that I never waste time asking myself what other people think about me. If I want to know, I simply ask them! In this way I obtain the information I need, and I also feel I know myself better.

Wayne. W, Dyer, The Sky’s The Limit, Mortagne Publications, 1988.

Self awareness helps me see that unhappiness is not a part of the Real Me, and is therefore not necessary to endure. Relaxation and tranquility are the result of self understanding. I make self understanding my goal each day.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The more I know myself the more I love myself.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am convinced that I am a center of pure self awareness; I am a center of willpower, capable of dominating and influencing, using all my psychological and bodily functions.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

I am MYSELF, a Center of pure consciousness.

Dr. Robert Assagioli, Psychosynthesis, Epi, 1965.

Table of contents

SELF CONFIDENCE (Also see Self Esteem, Self Control, Competence, Depression)

My self confidence grows stronger every day.
I have confidence in myself.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I'm more confident of myself every day. I'm getting stronger. I AM ME. I love who I am. I can handle any situation.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I have more and more confidence in myself every day.
I often tell myself: "It's easy, you can do it."
I speak clearly and articulately.
I decide what I really want, and act accordingly.
I can now depend on myself.

Suplipower, Subliconfidence, Edi Inter, 1989.

I have confidence in my abilities.
I trust in myself and believe in my innate wisdom.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I have confidence in my inner powers.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I have confidence in myself and in the future.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I am confident in myself, in others and in life.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I have confidence in you.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

Table of contents

I have faith in myself.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I have everything I need to be happy, here and now.
Everything I need is already within me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have absolute confidence in myself... and I feel at ease under any circumstances... even in public I feel no apprehension... all my faculties remain intact... because I am sure of myself.

Marcel Rouet, Motivating Your Subconscious, Dangles Press, 1982.

I like who I am.
I feel good about myself.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I will reach the highest summits through the power of this newfound confidence in myself.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

I trust my inner knowing in all situations.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I believe in myself.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I develop my self confidence and have faith in my clear conscience, letting it guide me without fear as my confidence grows.

I avoid negativity. I help myself live more fully in the present moment, by keeping in mind the confidence I felt when I succeeded in the past.

I have confidence in my abilities.

The more I am myself, the more I believe in myself.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I am gradually gaining more and more self confidence.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

I congratulate myself on each new success.

Christian H. Godefroy, Self Confidence: The Subliminal Method, Godefroy Publications, 1987.

I feel calm and sure of myself.
I am confident.
I build up my confidence.
My approach is relaxed, calm, tranquil and confident.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I prefer not to be a chronic worrier. I am going to manifest faith in everything I do - faith in the thought that nothing will happen. My faith in a Higher Power will always come to my rescue and provide me with peace of mind.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I am the greatest miracle in the world!

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I am a positive person and I have confidence in myself. I emit positive vibrations. If you look closely you can even see a halo around my head.

If I have suffered from a lack of self confidence in the past I don't anymore. Today is an ideal day for getting rid of all those false beliefs which have paralyzed me up to now.

It doesn't matter what I demand of myself, I can do it, I know I can.

Today, right now, I am capable of offering myself the gift of solid, unshakable self confidence.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Others appreciate my company. I have self confidence and self

Table of contents

esteem. I like myself, and others find that irresistible.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Now I am very sure of myself. I have complete confidence in myself, and confidence in life. I know my life will be very beautiful, because it is a pleasure to use this newfound confidence to work on myself, and to give to others.

Charles Baudouin, Psychology And Practice of Self Suggestion, Idegraph Publications, 1990.

I trust and follow my 'gut feelings' at all times.

Louis Proto, Self Healing, Piatkus Publications, 1990.

SELF CONTROL (Also see Objectives, Calm, Self Confidence, Willpower)

I'm in control of my body, now.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am in complete control of my thoughts and faculties. I use them to attain my objectives.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I command and then I obey my own command.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Every day I am in better control of my habits.

Sublipower, Sublicontrol, Edi Inter, 1989.

I become a mental magician when I control not only what I want to do, but also what I don't want to do.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

All my thoughts lead to acts.

Table of contents

I control my thoughts, and I control my world.
My thoughts make things happen.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am in perfect control of my mental impressions.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

Every day I expect to gain greater control of my feelings and my thoughts.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

I am in control of my thoughts, ideas and feelings.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

From this moment on I am ready to control the personality which awakens in me each morning. I will control my emotions by acting in a positive way, and it is by controlling my emotions that I can control my destiny.

I become my own master.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I feel in complete control of myself.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

I take full control of my mind and my emotions.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I am the master of my life and my own authority.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am in control of my gestures, my thoughts, my emotions. I am free of the things I inherited, free of my impulses which I have brought to heel. I am free of all restraints. I follow my chosen path calmly and firmly.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Table of contents

SELF CRITICISM

I can calmly review and critique my performance and then make improvements without calling myself names or blaming my performance on someone else.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I try to be myself as much as possible. I don't criticize myself that much. After all, you have to live a little.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

When I make a mistake I don't scold or berate myself with left-brain criticism. I develop an affirmative statement, about 5 words in length, describing my correct performance, in the present tense. I relax, and listen to myself stating the affirmation, and I visualize the accompanying action and feeling.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

SELF ESTEEM
(Also see Self Confidence, Self Love)

Increase my self esteem and I will be better respected by everyone.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I esteem myself and recognize that I am capable of exploiting the potential of every aspect of my being.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

(I have enough self esteem to accept what I think is the best.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

I speak about myself in a positive way.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am capable of handling a position of authority. But to do that I must start by improving my self esteem.

Charles de Liguori, Hypnotism, de Vecchi Publications, 1975.

I am a human being. I am worthwhile just because I exist and try to survive. I take care of myself. I take myself seriously. I correctly take myself into consideration first in all matters. No one is any more or less worthy than I.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I'm a wonderful person just the way I am.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I am really unique. I like who I am and I feel good about myself.

I always wanted to be someone, and now I know that I am.

I prefer being me to any other person in the world.

I like what I feel, I like the way I think and act.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I reject thoughts of "I'm this way..." or "I'm like that..." as much as possible.

I let the people close to me know that I intend to try to get rid of certain labels which are attached to me. I choose the labels I want to eliminate first, and ask them to tell me whenever I continue using them.

I make a decision to act differently than I did in the past. I set myself the task of eliminating one label per day.

I tell someone I can confide in about my decision.

I ask him / her to tell me every time I seem to fall back and start hiding behind a negative image or label.

I try to get rid of all these labels day by day.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

The farther I get away from my old habit of underestimating myself and my abilities, the more excited I become about the prospect of living my life in a really fulfilling way.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

I sometimes fail on purpose. If I lose a tennis match or a game of cards, does that in any way impair my integrity? Or do I remain an estimable individual who is simply participating in an activity for the fun of it?

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

SELF EVALUATION

I cease evaluating myself according to other people's standards. I use my own personal standards.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

SELF EXPRESSION (Also see Self Acceptance, Self Confidence, Health, Happiness)

Every time I express my personal opinion I do it as precisely as possible, speaking in the first person. I explain my expectations clearly, and I encourage others to do the same.

I express my opinions frankly, making sure not to be aggressive towards others, and I do not hesitate to express emotions like satisfaction or disappointment when I feel it is necessary.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I speak with gentleness and love. I exhale only the good.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Table of contents

I know how to express myself in a dynamic way.
I express myself freely, fully and easily.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am capable of expressing everything I feel, even if I don't know ahead of time what these feelings will be.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I am conscious of myself. I believe in my ability to express myself fully on a physical, spiritual or emotional level.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I want to express my feelings.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

When I express myself I pay attention to other people's reactions (verbal or non-verbal) in order to make sure that I am being understood.

If necessary I know how to talk in very simple language, using images, gestures and illustrations to get the point across.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

SELF FORGIVENESS

I am a human being, worthy but imperfect. I am like you. We are both just trying to survive. When I hurt you I was just trying to do what seemed best for me at the time. If I had then the awareness I do now, I would have chosen differently. But at the time, I could only do what I did. I understand that I hurt you, and I want you to know that hurting you was not my goal.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

Table of contents

SELF HEALING

I trust that I have the power to heal myself.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My healing power is getting stronger day by day.

Sublipower, Subli Health, Edi Inter, 1989.

SELF HYPNOSIS

I feel fine, perfectly fine. This session is over, and I'm going to resume my normal activities. I am in full possession of all my faculties.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

Now I am sleeping. So calm, so serene! Everything is tranquil. My mind is free, calm. This feeling of calm encompasses everything. I feel it in my legs right up to my chest, in my arms and in my head.

Charles de Liguori, Hypnotism, de Vecchi Publications, 1975.

My ability to practise self hypnosis is improving from session to session. My eyelids are heavy... they're getting heavier and heavier... They are so heavy that soon I will have to close them, and when I do I will enter a state of self hypnosis.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

SELF IMAGE

As much as possible I am going to think: 'Success is inevitable, and I am already the kind of person I want to be." I am going to feel and act like that new person.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I have a positive self image.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

I encourage myself to choose and stick to the path that gives me a healthy self image.

To improve my self image I learn from the school of successful failures.

Now that I like myself the way I am I consolidate my self image every day.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I allot myself some free time each day to work on a better me.

This decision to improve myself each day gives me the strength to improve the image I have of myself. This is going to be a good day, and my self image will be even more positive.

I concentrate on strengthening my self image.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I know that my dominating thoughts have to go through a number of stages before they become reality; that's why I devote 30 minutes every day to thinking about the man I intend to become, creating a precise image of that person.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

When I visualize myself "in the present" as if I were already accomplishing one of my goals, I make certain my visual image is as I would see it out of my own eyes, not "watching me do it" through the eyes of a spectator.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

All the negative images and attitudes I have about myself are now dissolved. I love and appreciate myself.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

SELF IMPROVEMENT

I believe that I am capable if improving my life by improving my way of thinking.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I dedicate a little time each day to improving myself as a human being.

I make a daily resolution to improve myself.

Progressing towards my goals implies a powerful desire to improve myself. In other words I want to become better, I want to strengthen the image I have of myself. I search for new horizons, I want to give my life a deeper meaning.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I love and approve of myself totally, every moment.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I stand tall and shine brightly. I appreciate myself. I respect others

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I'd rather be me than anyone else in the world.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am a unique and valuable human being. I always do the best I can. I love (like) myself, mistakes and all.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I see what is positive in me and I appreciate it.

Sublipower, Subliconfidence, Edi Inter, 1989.

Table of contents

SELF LOVE (See Love Of Self)

SELF PUNISHMENT

I reward myself, never punish myself.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

SELF REJECTION

I am trying to feel better about myself.
I offer myself my own friendship.
I will never abandon my sense of self.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

SELF RESPECT

I respect myself and appreciate myself.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

SELF SUFFICIENCY

I do not have to try so hard. I have enough. I am enough.

Louis Proto, Self Healing, Piatkus Publications, 1990.

SENSATION

I accept and experience all my feelings. (wrong section!)

Shakti Gawain, Reflections In The Light, New World Library, 1978.

Table of contents

I am in control of my way of sensing things.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

SENSE OF SMELL

My sense of smell is improving fantastically... I am able to perceive odors with amazing accuracy... over unusual distances... I am surprised at the number of different odors I can smell... and their intensity... My sense of smell is developing... I can sense even the most subtle odors... my sense of smell is becoming very developed.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

SENSES

All my senses are sharpened. My vision, sense of smell, hearing, and even my sense of touch are more awake than ever.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

SENSITIVITY

I concentrate my mental energy, my time and emotions on what concerns me.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I am a magnificent, sensitive, likable, creative and valuable being.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Table of contents

SENSUALITY

I express my love and my sensuality in many ways.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

SERENITY

I love the tranquility and peace I create in my mind.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

From now on I will feel deep inner peace and serenity.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am calm, tranquil and serene.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I always remain in a state of serene and peaceful balance because I know that God will always provide the right solution to any problem I encounter.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Nothing can disturb my serenity.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

SERVICE

I try to be useful, pleasant, set a good example and help others on all occasions.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I can get everything I want out of life if I help other people get what they want.

Table of contents

If I do something for someone who can't help me in return, I still get more than I give.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

SETBACKS

I never allow a setback to make me physically ill.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am coming back stronger day by day!

Now life is starting to look like a friend instead of the enemy it appeared to be before. The more I get into the habit of not expecting any help from anyone, except from my inner Guide, the closer I get to realizing my hopes and fulfilling my desires, while my fears of powerful adversaries and those who wish me harm disappear.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

SEXUAL BLOCKS

Women (or men) like and accept me the way I am.

Whether or not my sexual activities always work out is of no importance.

My sexual life is enjoyable, and does not cause me any tension or anxiety.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

SEXUAL DESIRE

I feel more and more sexually aroused. My whole body vibrates with desire and love. I am more and more desirable, and I find my partner —— (name) more and more desirable. I am irresistibly at-

Table of contents

tracted to him / her. I find my partner charming and sensual. My desire grows stronger day by day, and all aspects of my sexual life are improving.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

SEXUALITY

I give my fantasies the freedom to live in my mind and strengthen the joy and beauty of my love life.

I take the time to let my partner know about my needs and thus allow him / her to participate in my sexual fulfillment.

The intimate sexual expression of my being constitutes one of the greatest joys of my life. I give myself the freedom to experience pleasure with my whole being.

I love touching. I have no trouble expressing myself physically with the person of my choice.

I know it is good for me to express my sexuality, which constitutes a positive and important part of my overall well being.

I am a GREAT lover! I know how to relax and satisfy both myself AND MY PARTNER, simply by being myself.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I know that the sexual act is an expression of love on a physical level; I know that it is natural for me to be a warm, sensual woman, and there is absolutely nothing wrong with that.

I know that sexual pleasure is a right given to us by nature; I know that the union of two beings is creative in ALL senses of the word; it is the earthly expression of oneness with the total BEING through union with another.

I am constantly more enthusiastic, both actively and passively, when I make love with my husband; it's easy for me to close my eyes

Table of contents

and savor all the pleasant sensations associated with the act of love; I am relaxed and not in a hurry; I abandon myself to the tide of pleasure without even trying to think about having an orgasm.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

I am comfortable with my sexuality.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I am free to express my sexuality as I choose. I enjoy my sexuality tremendously.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am going to enjoy the sex act; I can and will have complete sexual fulfillment whenever I have sexual relations with my spouse.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

When I take my partner in my arms an irresistible desire overcomes me... I feel ready to move on to the act of love... physical love is completely natural... and when I make love I am relaxed and free of complexes.

I am happy with my partner... just thinking about it awakens my physical desire... I am ready for love.

*Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.^*

My body is alive.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

SHARING

I give to others. Doing so makes me feel good. I practice my ability to share with others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I give and I share.

Sublipower, Sublisuccess, Edi Inter, 1989.

I don't ask favors from anyone, but I have the privilege of sharing the blessings I have received with those who want to partake of them.

I share a part of the good and desirable things I possess with others.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

The more I have the more I want to give.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

The richer I get, the more I have to share with others. The more I receive, the more I have to give.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

As I give to myself, it is fun to give to others.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

SHORTNESS OF BREATH
(Also see Breathing, Smoking)

I am catching my breath.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

My breathing is regular and calm.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

Table of contents

SINCERITY
(Also see Benevolence, Warmth, Honesty)

I will be sincere with myself, and not create any more illusions or overestimate my qualifications or possibilities. I will also be sincere with other people.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I am warm, sincere, honest and authentic. I am all this and much more. All these qualities are a part of me! I love who I am, and I'm happy to be me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

My attitude towards friends is sincere, and my sincerity is real. Since I like, appreciate and accept others, benevolence and sincerity are a part of my personality.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

SKIN

My skin is becoming more and more beautiful and radiant. My face is glowing with health. My skin is improving day by day, becoming as fresh as a rose. My skin looks younger every day as it regains its freshness, elasticity and radiance.

My skin is getting softer and smoother.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

SLANDER

The storm will soon blow over, and in any case slanderous words

Table of contents

cannot hurt me.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I never talk about anyone except to express my esteem. I never slander anyone.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

SLAVERY

I flee from servitude; instead I look for ways to become involved. In this way I move from isolation towards happiness.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

SLEEP (Also see Rest)

Every night brings me deep restorative sleep. I sleep, I sleep (inhale), I am deeply asleep, I am deeply asleep (exhale).
I I fall deeper and deeper into sleep.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Tonight, tomorrow night, and on all nights to come, as soon as I wish to sleep I will fall asleep, and sleep right through the night until the next morning, until the hour I set for myself to wake up. I will sleep deeply, calmly, tranquilly, and when I awaken I will feel completely refreshed, happy and ready to greet the day.

Emile Coue, Complete Works, Astra Publications, 1976.

I sleep perfectly every night, and wake up fully rested.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I slide gently into a tranquil sleep.
Tonight I will feel calm and relaxed.

I will fall asleep with a calm body and mind.
My sleep will be deep and calm.
My sleep is calm and restful.
Every night I will sleep more and more deeply.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I am falling asleep in harmony and plenitude.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I feel good and I am secure when I sleep.
I love sleeping in a natural, normal way.
I never resist sleep, whatever time of day it is.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I will soon fall calmly asleep... my muscles are relaxing... my mind is calm... just one minute more and I'll be asleep... the thought of sleep fills my mind... I am going to sleep.

Henry Durville, Hypnotism and Suggestion, Durville Publications, 1938.

I will get into the habit of going to bed at approximately the same hour each night.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Just before falling asleep I flex and then relax every muscle in my body, starting with my feet and moving progressively upwards. I rid each muscle of tension.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

When I wake up I will feel full of energy. I'll be ready to do a thousand and one things, because I will have slept wonderfully well. I'll be in a good mood, happy, enthusiastic. I'm sleeping better every night. I'm sleeping better and better. Everything is fine. I sleep deeply. All is tranquil.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

Table of contents

Now I will fall deeply asleep until tomorrow morning... I am deeply asleep... deep deep sleep.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

My sleep is calm, deep, restful, restorative. It lasts right through until morning, from the time I want to go to sleep to the time I want to wake up, and I wake up exactly on time. I must do this.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I sleep deeply... As soon as I get into bed I forget about all my problems... I fall asleep right away. My sleep is healthy, natural and restorative... In the morning I feel rested and happy to face the new day.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

When I wake up I shall feel totally refreshed, energized and well.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Every night, from the moment I want to go to sleep to the moment I wake up, I sleep deeply, calmly and tranquilly.

Sublipower, Sublihealth, Edi Inter, 1989.

SLIMNESS (Also see Charm, Looking Good, Health, Weight Loss)

Female goal: I enjoy weighing — (specify your ideal weight) pounds and looking slim in my new bathing suit.

Male goal: I weigh a trim, athletic —— (specify your ideal weight) pounds and enjoy exercising every day.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I know that my weight depends solely on the way I see myself, and what I tell myself. I am learning to see myself as slim, in shape,

Table of contents

healthy and very happy.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am now slim.
I'm getting slimmer every day.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Everything I eat makes me more beautiful, healthy, slim and charming.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

SMILING

I belong to the compliment and smile club. When I smile at someone and the person smiles back I automatically feel better.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I remind myself to laugh a little every day.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I smile at life.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I am going to smile at least three times a day.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

SNACK

I have the willpower and assurance to control myself. I decide what I eat, and when I eat!

I will not eat between meals out of habit any longer, nor replace meals with impulsive snacking. From now on I will eat regular meals

Table of contents

of just enough healthy and nourishing food.

I never eat between meals to soothe my anxiety, my nervousness, my tension or solitude. I solve my problems by facing up to them and working on them. But I never replace a solution with a snack.

I no longer eat just to pass the time, or while I'm reading, working, talking or watching TV.

Every day I manage to eat less and less between meals. I am developing the healthy habit of keeping my weight down. I am a winner, and I am proving it every day!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

SOBRIETY (Also see Alcoholism)

I will not drink today.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am acquiring the habit of sobriety, and I can control myself.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I will never allow drinking to become a problem; I will use discretion as to how many drinks I can have or handle.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I don't drink any more and I feel better both mentally and physically every day.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am sober. I don't drink alcohol. I'm making a success out of my life. I am happy and serene.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses , Godefroy Publications, 1989.

I will surmount life's frustrations without drinking. I am sober and happy.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Table of contents

Sobriety and peace of mind are now mine to enjoy, and I am thankful.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am affirming my sobriety more and more strongly every day. I am becoming completely sober. My Guide is helping me faithfully, removing temptation from my path until I have completely vanquished this harmful habit. I am strong, I am joyous, I am free! I am strong, I am joyous, I am free!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

SOLITUDE

I like myself and I naturally attract loving relationships.

My relations with people are solid and affectionate.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I treat others with benevolence.

The fact of not criticizing myself so much any more means that I am being fair with myself, and that I am overcoming my solitude.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I find a partner who likes me, and who is cultivated, sincere, spiritual, faithful, happy, and at peace with him / herself. We feel an irresistible attraction for each other. In my life only things which are the result of love and truth can occur. I gratefully accept the fact that there is someone out there who is the ideal partner for me.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am a center of creative intelligence, love and good grace. I am no longer alone, because Divine Love is flowing through me, making all people feel affection for me. I attract those who are in the same

Table of contents

state of mind as I am.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I want to be loved.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

If I am always myself I will be sure to meet people who love and respect me.

Dr. Martin Shephard, How To Overcome Your Cares, Marabout Publications, 1973.

SOLUTIONS

I now see this point in a completely new light.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

There is a solution, and I'm going to find it.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I gather as much information as possible concerning my problem. Knowing the problem is the key to finding the right solution.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I dare to be aware of myself! I am completely capable of finding the solution I need.

I stop running around looking for solutions. I simply remain calmly receptive to my Real Self; it always provides a solution to my problem.

Solution, solution, solution...

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I am now being guided towards the perfect solution to this problem.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

At night I ask my subconscious to find a solution for a problem I cannot solve, using the 'blackboard' technique. The next day when I wake up, or sometime during the day, the solution appears in my mind.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Dear God, I know that You have the answer, and so I submit my question. It is in Your hands, and I will patiently await the solution.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

SORROW

Today I start a new life. I will forget everything that has caused me pain, sorrow or shame in the past.

Orison Swett Marden, The Joy Of Living, J.H. Jeheber Publications.

SOULMATE

From now on I won't be afraid to approach a person who attracts me. I am strong. I am ready to love and be loved.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I will attract a man who is honest, sincere, loyal, good, faithful and prosperous. He is peaceful and happy. These qualities are now engraved on my subconscious, and as I assimilate them, they become a part of me. I know that the law of attraction is irresistible, and that I will attract the man who corresponds to my subconscious convictions, and deepest feelings.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

I will meet my ideal partner, someone whom I love deeply, and

Table of contents

who loves me deeply in return.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

My ideal partner is waiting for me, and I will meet him (or her) in the right place, at the right time.

Vera Pfeiffer, Positive Thinking, Element Books, 1989.

SPEECH MAKING

My voice will be strong enough for this speech, and my positive thoughts are now helping me systematically improve my speech.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

When I speak my voice is clear, firm and distinct. I breathe deeply and regularly. My body is perfectly calm. When I look up from my notes I look at my audience, making sure to make eye contact with as many people as possible.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

SPENDING

Every dollar I spend comes back to me multiplied.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I deserve to spend money on things I desire.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I earn more money than I spend.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

I never spend impulsively, nor do I feel obliged to spend simply for the pleasure of spending.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

SPIRITUALITY

God is always good.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

He's got the whole world in his hands - and that includes ME. I surrender to the will of God.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I believe in the existence of a Higher Power, A Force of Love, that is eternal, that puts meaning into our lives.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I am one with my supreme nature and my creative power is infinite.

God is in me and manifests in the world through me.

Divine light and divine love flow through me and radiate from me, lighting up everything around me.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am the king's son.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

SPORT

I weigh a trim, athletic —— pounds, and enjoy exercising every day.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I do a lot of sports.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am capable of taking part in sports.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

Table of contents

Taking take three deep breaths through my mouth gives me the strength to perform great sporting feats.

My performance in sports is improving day by day.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

STAGEFRIGHT (Also see Fear Of Exams)

Starting today I will no longer experience stage fright.

I have overcome it once and for all.

I am confident, I know my strong points.

I feel relaxed, calm and serene, just like when I —— (describe a personal and pleasant event).

From now on whenever I have to write an exam I will feel as comfortable as on the day I —— (insert your personal and pleasant experience).

My stage fright is disappearing gradually.

I have overcome it, and I am a stronger person.

I have confidence in myself. I know I am going to succeed.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I have the ability to concentrate on what I am going to accomplish before the fact... I think of nothing else... and I concentrate my energy... also... I never feel any anxiety... even at the idea of speaking in public... I am never afraid... I am never anxious... I am sure of myself.

So I speak and act with vitality... knowing that my stage fright has disappeared... my mind is perfectly clear.

I am not afraid to speak out.... whether I'm with friends... or in front of a group of people I don't know.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Table of contents

I sing wonderfully well.
I an tranquil, serene, calm and full of confidence.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am calm and relaxed.
I can deal with any situation.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am strong! I will triumph! I will succeed!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

(I'm ready. I have already succeeded in the past.)

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

STAYING IN SHAPE

I'm in great shape.

Charles Baudouin, Psychology And Practise of Autosuggestion, Idegraph Publications, 1990.

I am conscious of my body and its importance vis-a-vis my overall well being. I always to what is necessary to stay in top shape.

I do everything I have to do to stay healthy and in shape, and maintain my well being.

I enjoy the challenge of getting and staying in shape. I accept the challenge, and nothing can prevent me from succeeding.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

STOMACH ACHE

Rays of healing energy flow through my stomach. Everything is fine and my stomach is functioning normally.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Table of contents

STOOL (See Digestion, Appetite)

STRENGTH (Also see Courage)

I decided I was strong.
I dare to be healthy and strong.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I have faith. Strength will come. It lies sleeping in me. I make an effort, I struggle. My hidden strength will surge to the surface. I persevere, knowing that my strength is growing, is transforming me. Weak as I am now, I will become strong and robust. I stop my crying and hold my head high. I reject negative thoughts. I don't believe my strength will abandon me.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I seek out and use my personal strength.

The greatest contribution I can make to others is to be strong within myself. People need my strength.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I feel stronger with every moment that passes.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am strong.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I am very strong. Stronger than I've ever been in my life. Stronger, much much stronger. I am surprised at how strong I am.

Dr. Maxwell Maltz, Psychocybernetics, Godefroy Publications, 1978.

Table of contents

STRENGTH - INNER

I feel a more and more irresistible strength growing within me.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

STRENGTH - PHYSICAL (Also see Losing Weight, Staying In Shape)

Every time I say the word X (choose a word) three times the strength of my muscles will immediately double. My muscles will be perfectly nourished by my blood, giving me perfect muscle tone.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

STRESS

As soon as I lie down I feel completely calm. My problems disappear. My body and nerves relax.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

I approach life in a relaxed way.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Stress slides of me like water off a duck's back. I relax with each breath I take. If a stressful event occurs I take a deep breath and regain my inner calm.

Christian H. Godefroy, The Creativity Method, Godefroy Publications, 1992.

I create pressure in any situation by what I focus on and what I say to myself. I can remove pressure by concentrating on doing the best job I can right now and learning all I can.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

Table of contents

I release any thought that subjects me to any stress whatsoever.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I never allow destructive tension to accumulate in me. I overcome stress by attacking its causes. I make a conscious effort to guard myself against stress and tension by maintaining a long-term perspective, by establishing simple goals for myself, and by taking appropriate measures such as exercise and relaxation.

I feel the peace that comes from relaxation and contentment. Every time I repeat these words to myself I become more confident and more relaxed, and I free myself from all the stress inherent in all areas of my life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am happy because my attitude is making my life more joyous and serene. I am free of stress.

I am a totally individual being, with my joys and heartaches. I am healthy and good. Every time I feel some tension building up inside me I take refuge behind my mental shield. Stress cannot break through my shield. I feel protected, night and day. I see all kinds of tension smashing into my mental shield without being able to break through it.

Tension cannot affect me. I am protected against stress. Other people may become upset, but I do not. I go about my life tranquilly, at my own pace. Everything is fine.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am completely calm... relaxed... I will concentrate on everything I do, and I will remain calm and relaxed inside... I do my work calmly... nothing can upset me... I know I can deal with any situation... and this certitude fills me with strength and energy.

I am sure of myself... It is a marvelous feeling to be able to say: 'I will triumph! I will realize all my projects while remaining calm and

Table of contents

relaxed.'

Day by day my sense of inner calm and self assurance grows stronger.

I am more and more calm... I feel completely comfortable with my situation. My heart beats calmly, regularly... My circulation is regular... any effort only makes me stronger... my health is improving day by day. I feel completely good about my situation... Day by day, and in all ways, things are improving. I feel better and better.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

STUBBORNNESS

I am learning to be mentally supple in all situations.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

The universe is running its course to perfection. I have no need to be stubborn.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

STUDIES

Today I learn things easily. My memory is functioning perfectly. If I have an exam I will remain calm and relaxed, and find the right answers. My marks will improve day by day, and I will take pleasure in learning.

Professor Kurt Tepperwein, How To Learn The Painless Way, Godefroy Publications, 1983.

May God show help me complete my —— (specify which) year of university, in harmony with divine law and order.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Table of contents

I do my homework and learn my course material.
I participate in courses whenever I can.
Learning interests me.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I know I can do this work since I am studious... may I also be wise.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.

When I study I do nothing else! I concentrate my mind and energy on the object of my study.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

When my homework is done I prepare for the next day's courses.

Everything I undertake I do conscientiously. So I also do a good job preparing for tomorrow's courses.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

My thoughts are organized, and my comprehension is growing.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

If I draw a blank on a certain subject, like algebra for example, it's just a natural result of the choices I made up to now. If I decided to make an effort to study these subjects by putting in the necessary time, I would certainly make progress.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

STUTTERING

Every time I say the word —— in my mind I will feel calm and relaxed, the muscles in my windpipe will remain completely relaxed and I will speak very well, with confidence and ease. It will be easy for me to communicate with others.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

Table of contents

I can now express myself correctly... correctly... with no problem whatsoever.... correctly.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

SUBCONSCIOUS MIND

I am united with the infinite wealth of my subconscious mind.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

SUBCONSCIOUS PROGRAMMING

I program my subconscious in order to realize my desires... my projects... my subconscious gives my imagination the means to attain my goals.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

SUBMISSIVENESS

I remind myself that habit is not a reason for doing something. Just because I've always had a submissive attitude doesn't mean I have to continue being submissive.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

SUCCEEDING

I have the right to succeed and get the best out of life.

Sublipower, Sublisuccess, Edi Inter, 1989.

I have everything I need to succeed.

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

Table of contents

I do everything in my power to succeed at such and such an endeavor.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

I am determined to succeed.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

I am succeeding.

I know I will continue to succeed, as I have done up to now. I am more determined than ever to reject anything that can become an obstacle to my success, anything that is unhealthy in my life.

Everything I do succeeds.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I am happy and successful because I have decided to succeed.

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Today I am going to succeed wonderfully well in everything I do.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I want to be happy and succeed.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I want to succeed.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

The greatest secret in the world is that I just have to be a little better than mediocre... that's all I need to succeed.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I succeed at everything I do.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

Table of contents

SUCCESS (Also see Wealth, Happiness, Self Love, Peace, Prosperity, Health)

Stocks may go up or down on the exchange, but in life my abilities are constantly helping me reach new heights of success.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am now willing to be happy and successful.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I have the certitude that I am making the best use of what I have. With this in mind, and armed with the desire and determination to see things through, chances are very good that I will attain success.

I believe I was put on earth to succeed, to be happy and healthy, and to attain useful goals.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I know that my future is one of progress, creative endeavor and financial security. This in no way depends on external factors. It depends on my mind, and I am grateful only to God, in the present as well as in the future.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I make my dreams a reality.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I make sure to take advantage of events.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

I am attaining a higher level of existence as I become more receptive to superior powers.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I turn to you, my inner Guide, with my prayer. I am confident

Table of contents

you will assist me in everything that has to do with my inner progress and my exterior success, both today and all the days to come.

You are helping me attain the goal I so ardently desire. I thank you for your support. You are the power that makes my desires a reality. I am one with my desires and I attain success. With your help I always attain success.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I will succeed by attracting the forces necessary for my success, by always being the first to be of service, and by instilling in my peers a desire to help me.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

I will succeed because I am able to handle any situation.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I am succeeding more and more easily at everything I do.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I succeed very well in certain areas.
I am in the process of becoming a successful person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I am strong, I feel better every day, and I will succeed at what I do.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

Life is beautiful. I am succeeding! I am succeeding!

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

My mind is constantly opening to new ideas. I use all the means at my disposal to achieve success. I am open to new ideas which lead to my success.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

Table of contents

Today is God’s day. I choose to let harmony, success, prosperity, abundance, security, and divine justice guide my actions.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

I accept the responsibility of being alive. I concentrate my thoughts on what I want to do and who I want to be. I know I can obtain all the good things I can imagine. I rid my subconscious of all negative thoughts which can prevent me from achieving what I desire. They do not exist. God’s power over me is now complete, and I progress on the path of right thinking. I await the results of my actions, and I give thanks.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I grant myself success, happiness, love of self and love of others.

Sublipower, Subliconfidence, Edi Inter, 1989.

I look to my past successes.
I invite success and not failure.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I only envisage the possibility of success... and so I succeed.

W. Clement Stone, Passport To Success, Godefroy Publications, 1962.

I persevere until I attain success.

I am more and more successful in everything I do. I am able to attain all my objectives more and more easily. I am becoming a successful person. Life smiles on me. Everything I do succeeds. I move from one success to another, more and more easily.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am the personification of success. I do my work, allowing God to guide me in all my undertakings.

The divine wisdom in me will reveal the solutions and means I need to attain professional success.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

Table of contents

I succeed when I attain my objectives, but I also succeed each day, on the voyage of life. I know that success does not only exist at my final destination, but at every step along the way.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am aware of my worth. I know I merit success in everything I undertake, and that I also merit the rewards my success will bring.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am on the road to success.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

All the powers of my subconscious are working for my success.

Negative thoughts and doubts are erased and replaced by new ideas and positive thoughts of success.

I have all the qualities I need to succeed.

The creative power of the universe is at my disposal to help me succeed.

I like having a goal and persevering until I succeed.

Each day I take a step closer to success.

I have confidence in my intuition, which is guiding me towards success.

Sublipower, Sublisuccess, Edi Inter, 1989.

SUCCESS - FINANCIAL
(Also see Marketing, Happiness)

Financial success comes to me easily and effortlessly.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Table of contents

SUFFERING

It’s going away, it’s going away...

Emile Coue, Complete Works, Astra Publications, 1976.

(I choose to ignore death. I live my life based on what I think and feel.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

When I face up to my suffering and treat it, my present suffering frees me from future suffering. It must be confronted.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

SUGGESTION - POSITIVE

I have a positive attitude towards each one of these suggestions, and I am convinced that they will make me a happier person.

The suggestions I am receiving will help me and I will listen to them. These suggestion will influence me every day of my life.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

SUPERIORITY

The person opposing me is no trouble at all. S/he knows nothing about my expertise or experience on the subject, and so I have every advantage over him / her. I am strong! Much stronger that s/he imagines.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

Table of contents

SUPPLENESS

Every breath I take makes me more supple.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

My bones must always stay healthy, and my joints, especially those in my spine, should move freely and easily.

I make sure that my muscles are healthy, able to respond rapidly, and always ready to function.

Christian Godefroy, Mental Dynamics Seminar, Godefroy Publications, 1978.

SUPPORT

Everyone around me helps me to grow.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

SURGERY

The operation is a total success. Everything is healing as it should.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Nothing is going to disturb my recovery. I'll have no complications, and I will feel good because I know it's all over.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

SURPASSING

Today I will surpass everything I did yesterday.

It isn't important to surpass others; the only important thing is to surpass myself.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Table of contents

SWEETS

I don't eat sweets. I imagine life without sweets. I imagine that I (specify a daily activity) without feeling the need to eat sweets. I don't like sweets. But I do like to be healthy. I am in great shape and full of energy. I don't eat sweets.

I now reject my tendency to eat sweets. I don't like sweets. I reject them because they harm my body. They are bad for my teeth. They make me gain weight. I don't like them. Sweets disgust me.

Because I have always succeeded at what I tried in the past, I will also succeed in getting rid of this harmful habit. I don't eat sweets. They're bad for my health. I want to be healthy, slim and full of energy.

Without sweets my skin looks fresh and pure.

Without sweets I do not gain weight.

Without sweets I don't run the risk of becoming diabetic.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I give up candy, chocolate and sweets.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

Sweets disgust me... and day by day this feeling of disgust grows stronger... From this moment on I won't eat any more sweets. I will lose two pounds every week... I feel a lot better... I have lost this voracious craving... I eat two meals a day... and I don't snack between meals.

My health is improving day by day... my digestive functions are working wonderfully well... Eating doesn't interest me... I feel great.

I don't eat a lot at mealtimes... and I don't snack on sweets between meals... day by day I find sweets more and more disgusting.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I make sure I don't overeat.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

Table of contents

SYMPATHY

I feel more and more sympathetic towards people. People like me and spontaneously seek me out.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

T

TACHYCARDIA

I want my heart to slow down now.
My heartbeat is becoming regular.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

My heart is beating regularly and normally.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

TACT

I am adept at treating people tactfully.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

TALENT (Also see Gift, Salary, Service)

I have talent, I am intelligent and creative.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I have a number of talents which are just waiting to be awakened and used to carry me right to the top.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

(I change everything. I share my creative talents in my daily life. I am a ray of sunshine.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

Table of contents

I possess numerous qualities and numerous talents. I even have aptitudes which I'm still not aware of. I'm always discovering new ones.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I take what I have and use it, and my talent grows, which brings me more profit.

Since I possess the only me there is, I am precious. So I take myself and my talent and I exploit them.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I proclaim my uniqueness.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I find a job which exploits my talents and qualities to the fullest.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

TELEMARKETING

I can improve my phone technique.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

TELEPATHY

I will make ..... (specify who) think about me... s/he won't be able to resist thinking about me.... my image is forcing its way into his / her mind.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1950.

I perceive each of your sensations, all your states of mind, your emotions, everything that enters your mind.

From this moment on our minds are very close, our minds inter-

Table of contents

penetrate and fuse with each other, transforming us into a single mind.

From this moment on I will have no trouble reading your thoughts; all your thoughts will appear to me as clear and precise mental sensations.

I find myself in your body; your body has become my own, your mind is my mind. I see through your eyes, I hear with your ears, I think with your brain.

Your thoughts are present in me; I perceive them very clearly, they are my thoughts.

I am perfectly capable of reading your mind...

Valery Sanfo, Practical Guide To Telepathy, de Vecchi Publications, 1984.

I am going to read your mind... I can read your thoughts... but first I will empty my own mind... I am not thinking about anything... then when I tell myself to... your thoughts will appear in my mind like writing on a blackboard, and they will be easy to read... I will see them clearly... and I will tell you what they are.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

TELEPHONE

In my telephone communications at work or at home I answer the telephone pleasantly, immediately giving my own name to the caller, before I ask who's calling.

Whenever I initiate a call to any residence or place of business where someone new may answer, I always give my own name up front, before I ask for the party I want and before I state my business. By leading with my own name I underscore my value.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

TEMPTATION

I have mastered the blind force which caused me to submit to temptation and I have subjugated it to my will; I will consciously make use of this force for positive ends.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I keep the force that is pushing me to give in to this temptation to myself. ???

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

TENACITY

What others call defeat or failure never stops me. I know that so-called failure is nothing more than a detour. So I get over it and continue on my way.

Whenever I set a precise goal for myself, whatever it is, and develop a specific plan to attain it, I never let it out of my sight, and pursue it tenaciously.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Each step brings me closer to victory. Each obstacle contains the seed of a blessing and of even greater opportunity.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I never stop trying; I will make it through. I will stick with it. Everything will work out in the end.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I persist in a positive and flexible manner until I get things done.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I keep at it and I will succeed.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

One last effort may be all that is keeping me from success. I'm going to do it, right now!

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

TENDERNESS (See Love)

TENNIS

I find it easier and easier to play tennis. And I'm making more and more of my shots. Tennis is becoming easy for me. I'm improving day by day, and I'm winning more and more matches.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

TENSION (Also see Confidence, Communication)

With each exhalation I get rid of my worries and tension.

Sublipower, Sublirelax, Edi Inter, 1989.

As I breathe in deeply I am able to overcome my tension.
It is easy for me to relax.
I avoid situations that create tension.
The image I project is of a relaxed person.
I like being a relaxed person.
I perceive myself as a relaxed person.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I let my benevolent mind support me in moments of tension; it gives me confidence in my ability to overcome any kind of tension.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Table of contents

I feel calm and relaxed.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

A good part of my tension disappears because I feel secure and good about myself, and because I put all the little things that irritate me into their proper perspective.

In short, little things don't annoy me any more.

My bank account of confidence is growing, the communication barriers in my life are falling by the wayside, and my family life is benefiting as well.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

(I will no longer live in a state of constant tension, afraid to relax, not allowing myself to smile and spending too much time reliving unhappy memories from the past. I'm going to make every single day a pleasure.

In order to prevent nervous tension from developing, I try to keep my mind relaxed and free of unpleasant thoughts that tense me up. I nourish myself with pleasant thoughts.

I use the technique of self hypnosis to relax my muscles. Relaxing my body relaxes my mind.)

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

All my tension is disappearing.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

TEST

I am very well prepared for —— (specify the situation).

Raymond Hull, Wanting Is Power, Les Editions de l'Homme, 1969.

Table of contents

THOUGHTS

I choose my thoughts... I can do it... I change my thoughts... I can do it.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

THOUGHTS - NEGATIVE

Every day I create new positive and harmonious thoughts and emotions. They transform my life, bringing me happiness and health.

Christian Godefroy Collection, Magic Formulas For Success And Happiness, Godefroy Publications.

I prohibit myself from thinking negative thoughts. Everything that happens to me has a positive side.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I drop negative thoughts like hot pans!

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I reject and rid my subconscious of all acquired negative thoughts. I am the Spirit, and thus I am in no way affected by disease, death, unhappiness, poverty or frustration. All these things no longer exist in my subconscious mind.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I recognize my wealth and material energy. I get rid of negative thoughts which sap my strength.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

THOUGHTS - POSITIVE

I am going to discover for myself that I have the power within me

Table of contents

to control and influence my mind at will, that I can quickly convert negative thinking into positive thinking.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I have positive thoughts.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

(I avoid other people's negativity. (I am strong. I do not share in the failures that stem from the minds of others.)

I do not get mired down by depression, fear, anger, poverty, disease, lack of energy, struggle, conflicts or bad relationships.)

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I change my mental diet and refuse to ingest negativity.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I concentrate on good thoughts. I retain thoughts which are likely to help me, and reject the others.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

I think positively.

Sublipower, Subliconfidence, Edi Inter, 1989.

I saturate my subconscious with well directed positive thoughts which help get me what I expect out of life.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

I am confident of my power to forge the future through the thoughts of today. That is why I take care to formulate them in accordance with my most sincere wishes.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

My thoughts are positive.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

Table of contents

YES.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

My thoughts are more and more positive.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

TIME

I have all the time in the world for what I want to do.

Louis Proto, Self Healing, Piatkus Publications, 1990.

TIMIDITY
(Also see Inferiority Complex, Self Confidence)

I find it easy to talk to individuals and groups of people.
I am at ease in the company of members of the opposite sex.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Each time I mentally repeat the word X at least three times I will feel perfectly relaxed; I am sure of myself, and talk to people with a strong sense of confidence and serenity.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

I confront the unknown, and triumph over it.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

I take great pleasure in meeting impressive, well-known people.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

I dare to speak out.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

Table of contents

I no longer attach much importance to what other people think about me... and this frees me from my shyness.

I never waste an opportunity to fight my timidity... I often approach people I don't know and engage them in conversation.

I like to get involved in group discussions... in the street I don't hesitate to find some pretext or other to talk to people.

When I talk to people I look them right in the eye... naturally and openly... without trying to avoid eye contact... without being shy... with absolutely no timidity whatsoever.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I must not consider shyness as something to be ashamed of. Shyness is merely a symptom of a lack of self confidence, feelings of insecurity, inferiority and a fear of people.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I will not be shy; I won't be nervous when I talk to people, no matter who they are.

I will be perfectly at ease in all situations.

Paul Clement Jagot, Education Of The Word, Dangles Press, 1975.

If my inner Guide approves of me, which is always the case when I feel His presence, then whatever other people think or say about me doesn't matter. It doesn't affect me. I see my goal, and let my inner Guide lead me to it.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

TOBACCO ADDICTION
(Also see Shortness Of Breath, Cough)

I can easily stop smoking. I completely renounce the smoking habit. At the same time my health and general state will improve. I

Table of contents

can control my reaction to cigarettes. I have absolutely no desire to smoke. I am becoming a new person with absolutely no need to smoke. My subconscious is helping me to stop smoking easily, completely and forever, without gaining weight.

I don't smoke any more. I stopped smoking completely and definitively. My health is great. I'm breathing better and I feel wonderful.

I congratulate myself for having stopped smoking. I really look a lot better. I'm in great shape. This is fantastic. I have stopped smoking.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I feel less and less like smoking, and I have less and less need for cigarettes. I feel good. I feel better every day. I'm smoking less and less. I already feel a lot better.

I'm smoking less. I feel better. I feel full of energy, and I have the courage to continue. I know I'm going to stop smoking once and for all. I already smoke less and less, and I feel great.

I don't smoke any more. I don't need tobacco. I'm breathing better. I fill my lungs with pure air. Each breath fills me with pure oxygen and vitality, recharging my body with energy and doing me a world of good.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I have an image of myself without cigarettes. I imagine myself as a non smoker. I give up tobacco, I reject the habit. My body rejects it, my mind rejects it. I don't smoke and I feel great.

I reject cigarettes because I know they are harming me. I do it for myself, for my health and well being. And since my life is a success, I will continue to succeed as a non smoker. I choose to be a non smoker.

I'm breathing better and better, and I have more and more energy. I feel wonderful. I breathe easily, I have more endurance. The

Table of contents

people around me are happy at my success. I feel marvelous without cigarettes. I am a non smoker!

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I'm learning to do without cigarettes... I don't want to smoke any more... it doesn't interest me... smoking doesn't interest me at all... Even the idea disgusts me... Whenever I smell smoke I feel this disgust.

Now I don't smoke anymore... Nothing can make me change my mind.

I'm happy to be able to improve my health by not smoking.

My health is improving day by day... I don't smoke anymore.

Day by day it's getting easier not to smoke.

I have absolutely no interest in smoking... even the idea of smoking is enough to make me feel disgusted with cigarettes... The smell of cigarette smoke disgusts me more and more.

I'm very happy not to smoke anymore... Nothing can make me change my mind... I'll never smoke again.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

I will smoke less or not at all.

J.V. Cerney, Stay Younger, Live Longer Through The Magic Of Mental Self-Conditioning,
Parker Publishing Company Inc., 1968.

I don't feel like smoking anymore. My health is already better, I'm breathing better, I'm becoming a new person. Not smoking is an expression of my freedom. My subconscious is my most powerful ally, and it is helping me to stop smoking, to build a new self image which is more free and more fulfilled.

Karl O. Stoeber, Psychotraining, Godefroy Publications, 1984.

I don't smoke and I'm proud of myself.

When I see a cigarette or think about smoking, the words 'I Do

Table of contents

Not Smoke' automatically enter my mind and I abstain.

I really like breathing fresh clean air, I like being healthy and in complete control of my mind and body.

My lungs are healthy. I can breathe deeply.

It's easy for me to be a non smoker. After all, I was born that way, so the state is completely natural for me. I am a non smoker! I do not smoke.

I let myself relax, breathe deeply and feel good. I appreciate being healthy and a non smoker no matter what the circumstances.

I do not in any way see cigarettes as a symbol of power, of intelligence or of prestige. I see cigarettes for what they are, and refuse to allow them any place in my life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am breathing deeply... and this purifying breath eliminates my need to smoke... with each purifying breath my need to smoke diminishes... I need to smoke less and less...

I am breathing deeply... and each exhalation gets rid of the toxins which tobacco has deposited in my lungs... I am cleaning my body of these poisons which have been contaminating my blood... weakening my organism... and ruining my health.

Not smoking will give me new vitality... make me more dynamic... more active... I will feel better from all points of view... and I will be victorious in gaining mastery over myself.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I know I am going to get more satisfaction from not smoking than I did from smoking.

I know that I am indifferent to cigarettes, anywhere, anytime, under any circumstances; other people may smoke but as for me, I don't care about cigarettes.

Clement Auger, Transform Your Life Through Autosuggestion, Heritage Publications, 1979.

Table of contents

I have decided to make life as pleasant as possible by becoming a non smoker. I have made a deliberate choice not to smoke, and I feel great. I am a non smoker. I've found the way to get rid of my bad habits.

The next time I need to relax I'll do a few breathing exercises and drink a glass of water or juice instead of lighting up a cigarette.

The next time I go to a restaurant or take a plane I'll sit in the non smoking section.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defenses, Godefroy Publications, 1989.

I'm intelligent, I've got common sense. I need my body to live, and cigarettes are poison.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I am free of the habit of smoking.

Jack Ensign Addington, How To Set Goals And Attain Them, A Different World Publications Ltd., 1977.

I absolutely want to stop smoking.

The taste of tobacco is disgusting.

I don't need to smoke anymore.

I am aware that it is much better not to smoke.

I want my breath to smell good, without the after odor of tobacco.

I respect my body.

I am in good health.

I am gradually freeing myself of my dependence on tobacco.

I substitute the harmful habit of smoking with beneficial habits of nutrition.

As I stop smoking I watch what I eat so I won't gain weight.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

Freedom and peace of mind are now mine. I know that believing and affirming these truths will allow them to penetrate deeply into my subconscious, which will in turn force me to give up cigarettes,

Table of contents

because smoking is harmful and breaks the laws of my subconscious mind.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

My voice is normal again.
I don't cough anymore.
My mouth is fresh tasting and I feel better and better every day.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

If I light up a cigarette I won't get any pleasure out of it. On the contrary the taste will disgust me, to the point where I'll have to put the cigarette out. It will be impossible for me to smoke.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

If I must smoke I will smoke in moderation.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

TOLERANCE

From now on I will think, feel and act justly. I will do what is right, and never deviate from the path of justice. I think, speak and write without taking sides or being prejudiced. From now on I will not react like an ignorant fanatic, but base all my actions on the divine spirit that resides in me. I wish from the bottom of my heart that all men may live in liberty, and rejoice fully in their right to life and happiness. I obey the golden rule and the law of love.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I accept and respect the right of each person to choose.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

(I use self hypnosis techniques to strengthen my potential for tolerance, and I never have any problems.)

Table of contents

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I cease imposing temporary conditions in order to organize and program other people's lives.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I never force others to share my points of view.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am full of tolerance for myself and for others.

Christian H. Godefroy, Self Confidence: The Subliminal Method, Godefroy Publications, 1987.

(I am a warm, open and tolerant person.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I am going to criticize less and be a little more tolerant of others, of their faults, their failures and errors. I will interpret their actions in the best light possible.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

TOOTHACHE (Also see Pain)

I just have to touch my —— (name the part of the body) for it to become numb.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

TORMENT

I calmly try to reduce the impact of extreme circumstances.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

This too will pass.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Table of contents

I am learning to mentally detach myself from external turmoil.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I calmly determine what worst case scenario is that I may have to deal with.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I prepare myself to accept the irremediable if necessary.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

I never abandon myself; I support myself when things go badly or start getting difficult.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

TOXINS

With every out breath I rid my body of toxins.

Louis Proto, Self Healing, Piatkus Publications, 1990.

TRANQUILLITY

My mind and body are tranquil.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I am completely tranquil.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

When I repeat the word X just once, my mind enters a state of rest.

Valery Sanfo, Practical Guide To Self Hypnosis, de Vecchi Publications, 1987.

TRANSACTIONS

Table of contents

God is always present in my transactions, and I never finish a day without accomplishing something valuable.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

Infinite intelligence governs and protects all my financial transactions.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

TRANSFORMATION

Today I am starting a new life.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I find it easy to transform myself.

Sublipower, Sublicontrol, Edi Inter, 1989.

I am transformed.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am a new person every minute.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I want everyone around me to notice my transformation. I have an improved attitude. I am straightening up: my muscles are firmer and stronger. I feel new life flowing through me.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

TRAVEL TIME

Before going somewhere I make sure I am using the means of transportation that is going to save me the most time, not necessarily

Table of contents

the one which is fastest.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I try to organize my traveling time so that my mind is clear, and I can use it to work or think.

I avoid encumbrances, and only move around when I have to.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

TROUBLE

I try not to bother too much about my troubles.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I avoid blaming myself for things I cannot change.

They aren't really important.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

I assign a lot less time for worrying about things.

I give myself ten minutes in the morning and ten minutes in the afternoon to vent my anxiety and reassess all the catastrophes I can think of during those time periods.

Then I use my ability to control my thoughts and stop troubling myself until the next worry period.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Everything is fine the way it is.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I am going to auto condition my mind every morning with a positive attitude toward each new day.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

TRUTH

Table of contents

I have the courage to look truth in the eye.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I seek the truth.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I am full of desire to unlearn false ideas and learn new truths.

I don't need to fall into any traps. Desire without hope dissolves. I have nothing to fear. There is enough of everything to satisfy my real needs. I place Truth above all else, and everything else comes to me. The mental struggle is useless. I just have to relax. I am aware, and I let Truth liberate me.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I have to confront myself and search for truth within myself, with my own means, because I consider it important.

Whether I am aware of it or not my mind is functioning in a unique and natural way, based on the fundamental principle of showing me the truth about any situation I encounter.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

TUBERCULOSIS

Every cell, every nerve and every muscle in my lungs is now being purified, strengthened and perfected. My whole body is healthy and harmonious.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

TUMOUR

Table of contents

I want my little tumor to go away.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

ULCERS (Also see Digestion)

My body is building a protective barrier of tissue around the wound; the wound stops bleeding and heals up.

My wound is no longer painful; all the reflexive reactions disappear; my stomach is calm and digests normally.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

My stomach digests better and better.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

UNCERTAINTY

(When I'm not very sure about what I'm doing I examine the consequences of each possible course of action.)

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

UNDERTAKINGS

I have a clear conscience; it will surely guide me in all my endeavors.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I undertake things which I have always avoided under the pretext that I didn't understand enough about them.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

Table of contents

UNEMPLOYMENT

All right. I haven't got a job. I have to react immediately. I'm going to find work this week. In any case, it's not serious. It'll do me good to see different things, meet different people. Because in fact, I didn't really like the job I had. I was starting to get really bored.

I am competent. I have experience. I'm due for some luck. I am convinced that somewhere out there, right at this very moment, is my ideal job. And I'm going to find it.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

In the universal harmony where all human beings have their place, I have the useful and well paying job I deserve. Thank you!

Marcel Auclair, The Book Of Happiness, Seuil Publications, 1959.

The god in me knows what kind of work suits me best, where it is, and what I must do to carry it out. May this knowledge in me become a living revelation to my conscious mind, so that I may know where my real work lies, and the steps I must take to find it.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

UNEXPECTED EVENTS

I schedule the time I need to deal with unexpected events.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

I never let myself get flustered.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

UNHAPPINESS

I stop trying to be happy. I try to understand the causes of my

Table of contents

unhappiness.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I believe I have the mind-power to survive all life's frustrations, disappointments and misfortunes.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

UNIFORMITY

I remind myself that uniformity and death are the opposite of fulfillment.

Wayne Dyer, Your Erogenous Zones, Tchou Press, 1976.

UNION

I know that an irresistible law of attraction exists and that I will attract a man / woman who is in harmony with my subconscious beliefs. I attract what my subconscious believes to be true.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I know that the intelligence of my subconscious mind has united us in accordance with the divine order of things.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I am in union with Life, Love and Truth, because I live with God. I am united with all beings because the image and reflection of perfect Life resides in everyone.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

Table of contents

URINE RETENTION (Uremia)

In a minute I am going to empty my bladder completely.

Dr. G.R. Rager, Hypnosis, Sophrology and Medicine, Fayard Publications, 1973.

I will urinate tonight, and then more tomorrow.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

URTICARIA (See Eczema, Acne)

USED CARS

I will find the used car I am looking for. At a good price. It is in excellent condition. It corresponds exactly to my needs. My subconscious mind is infallibly guiding me towards this car.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

UTERINE BLEEDING

My uterus is tightening; the blood vessels are closing; the flow of blood is stopping.

I feel my uterus getting tighter as I tighten my fist.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

UTERINE SPASMS

My uterus is relaxing, the pain is going away, and I feel fine.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

VACATION

(This is good, I'll be able to relax, I'll take a vacation.)

Louis Proto, Self Healing, Piatkus Publications, 1990.

I try to take short vacations instead of extended ones which would probably exceed my real need for physical and emotional relaxation.

I remind myself that other people have the same need for relaxation as I do.

I plan my vacations, and discuss them with my spouse and children.

I know that I am not obliged to spend all my vacations with my family (relatives, spouse, children, etc.).

I make sure I get a lot of free time when I'm on vacation.

Pierre Nicolas, Time Is Money... And Pleasure!, Inter Publications, 1981.

VENGEANCE

I never try to do the same to my enemies as they have done to me because by seeking revenge I hurt myself more than the people I want to hurt. I follow General Eisenhower's example: I never waste even a minute thinking about the people I don't like.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

Table of contents

VERTIGO (Dizziness)

Starting today I won't suffer from vertigo anymore. Every time I feel dizzy I will think that I feel as good as on the day I (insert a pleasant experience). I am serene, happy and confident. I can go wherever I like. I am in control of my sensations.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

VICE

I am free of the vice that has been sapping my strength. No negative impulses can make me renounce my freedom. They no longer have any power over me. I see my goal clearly, and nothing can distract me.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

VICTORY

I am the greatest of nature's miracles. And nature knows no failure. It always wins, as will I starting today. And thanks to my victories the struggles to come will be less severe.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

I embark on the path of life with a new ideal. I embark with a victorious attitude, and a generous and beautiful soul. I know I will be victorious. And I want to be worthy of my victory.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I am a victory.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Table of contents

I want to be victorious.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

I want to be victorious, and to do so I must start by triumphing over myself.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

VIGILANCE

(I always expect the unexpected.)

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I am always vigilant for opportunities.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I concentrate on performing with a smooth, relaxed alertness.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

VIGOR

I see myself as a vigorous person in the best of health.

Dr. Anthony and Mary Zaffuto, Alphagenics, Quebec - Amerique Publications, 1974.

A guaranteed way to stay young and vigorous is to first change my inner self. The energy will follow.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

VISION

I relax the muscles in my eyes, in both eyes, and my vision is improving.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

Table of contents

I can see better and better; I have excellent vision, in an intellectual, spiritual and physical sense.

The divine spirit, which has the infinite power of healing, is now opening my eyes and recreating my visual faculties. My eyes are the instruments of perfection desired by God, and allow me to see both inside myself and out into the exterior world. The magnificence of God is revealed to me through my eyes.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

My vision is becoming clear again... I can see better and better.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

VISION - POSITIVE

I see with love and joy.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

Visualization

Who I see in my imagination will always rule my world.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I increase my receptivity to mental images. I make them work for me more and more.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I use my senses on all mental levels as I experience the external world.

Christian Godefroy, Mental Dynamics Seminar, Godefroy Publications, 1978.

I can obtain what I want by visualizing it.

Sublipower, Sublisuccess, Edi Inter, 1989.

Table of contents

VITALITY (Also see Ambition, Dynamism, Enthusiasm, Beauty, Health)

Every breath I take increases my aliveness.
Every day that passes I feel stronger and more alive.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I am overflowing with more and more energy and strength.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I am overflowing with vitality and enthusiasm!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I am regaining my balance and vitality.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I am energetic and overflowing with vitality.
I give thanks for my ever increasing health, beauty and vitality.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I am strong and vital.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

My natural state is to have radiant health, boundless energy and vitality throughout my life.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

VIVACITY

I have a pleasant and lively mind, and I find that people appreciate it because I use it a little more each day.

Arthur Wassmer, The Art Of Making Friends And Being Happy, Belfond Publications, 1978.

Table of contents

I am intelligent, my mind is lively, alert, brilliant and amusing. Since my thoughts are positive, my mind creates harmonious situations in my life.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

VOCATION (Also see Money)

I trust my preferences to show me where my true vocation lies.

Louis Proto, Self Healing, Piatkus Publications, 1990.

My subconscious mind will infallibly guide me to the vocation where I will succeed best, and which will bring me all the money I need.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Subconscious Mind, help me discover the vocation that pleases me the most.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

VOICE

I am certain I won't lose my voice, not even for a moment.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I want my voice to be more confident; I want it to express my decisions not as commands, but rather as well thought out advice.

Henry Durville, I Want To Succeed, Durville Publications, 1968.

Table of contents

WAKING UP

I wake up every morning full of joy and confidence.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

All I have to do is concentrate on a given time in order to wake up at that time feeling refreshed and ready to face the world.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

When I wake up I feel great and full of energy.

Sublipower, Sublihealth, Edi Inter, 1989.

Whenever I use my mental clock and sincerely want it to work, I wake up at the exact time I choose.

Christian Godefroy, Mental Dynamics, Robert Laffont Publications, 1976.

Tomorrow at precisely —— o'clock I will wake up feeling refreshed, and get out of bed immediately.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I want to wake up at —— o'clock.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

WARTS

The blood vessels in my wart are contracting; the wart is no longer being nourished with blood, and is drying up.

Dr. Gaston Durville and Dr. Andre Durville, Mental Cure, Naturist Institute Publications, 1923.

Table of contents

WEAKNESS

I give up being helpless.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I have the right not to be strong.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

WEALTH (Also see Profession, Success, Value)

This year I will double my income to $———, and in six years from now, that is on —— (specify the date) I will be a millionaire.

Marc Fisher, The Instant Millionaire, Golden Publications Ltd. and Godefroy Publications, 1986.

Each day I am getting wealthier in all things.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Each day brings me closer to wealth.
I desire to be rich.
I am capable of being rich.
I want to be rich.
My subconscious is guiding me infallibly towards wealth.

Christian H. Godefroy, Prosperity: The Subliminal Method, Godefroy Publications, 1987.

Every day, in all ways, I am becoming more and more wealthy.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Every day I am more and more wealthy in everything.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

There is no logical reason which can prevent me from becoming wealthy.

I am getting more and more wealthy.

Table of contents

I am becoming wealthy.
I am getting wealthier day by day.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I have confidence in you, my inner Guide, and from now on everything will be fine. I feel my mental distress and the obstacles separating me from enjoying wealth disappearing. I feel I am flowing with the current of abundance, and I am moving forward with it. I know that with your help my wishes will be granted.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I have the right to be rich, healthy and prosperous.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

I opt for the richness of life here and now. Wealth is already uppermost in my thoughts. Yes, I am grateful for all the wealth of my mind and my life. I feel wealthy. I am wealthy. I am becoming wealthier every day.

All the riches of the world circulate joyously and freely in my life, and I am very grateful. I know that all my needs are satisfied because I accept wealth. The world is there for me to enjoy, and I am rich. I am rich because I accept being rich. I can feel all my wealth now. I feel it with gratitude.

Charles Baudouin, Psychology And Practise of Autosuggestion, Idegraph Publications, 1990.

I am becoming more and more wealthy.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I am becoming wealthy.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I enrich myself day by day.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

Table of contents

I do not believe that wealth is the private domain of a selected few, but rather that the abundance of life offers wealth to everyone who creates it.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I do things that are likely to bring me good fortune... I don't bargain with God... I don't set an amount that I'd like to reach... I conduct my business by submitting to His impulses, knowing that He will give me what I firmly desire.

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

I reflect with a positive mental attitude, and I become rich!

The more I share what I possess with others the more my wealth increases.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I am now a mental millionaire.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am rich.

Charles Baudouin, Psychology And Practice of Autosuggestion, Idegraph Publications, 1990.

I am a child of infinity, and wealth flows through me freely, joyously and eternally. I am enriched with happiness, peace, wealth, success and extraordinary sales. I seek wealth in the deepest recesses of my mind, and abundance is the result.

Dr. Joseph Murphy, Miraculous Power Attracts Infinite Riches, Godefroy Publications, 1978.

The power of 'collective consciousness' helps make my fortune and my money grow.

I think and become rich because nothing, absolutely nothing can stand in my way.

Napoleon Hill, Think And Get Rich, Tchou / Ariston, 1966.

Table of contents

My connection to infinite being and infinite intelligence is quite enough for me to amass a considerable personal fortune.

Christian H. Godefroy, Mental Techniques For Financial Independence, Godefroy Publications, 1983.

My life is a free flow of infinite wealth.
This universe is bursting with riches for every one of us.
Infinite wealth appears easily in my life.
I am wealthy within and without.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

My affairs are improving every day. I am making progress, moving forward, and I am richer every day.

Dr. Joseph Murphy, The Miracles Of Your Mind, Dangles Press, 1984.

One day I will be a millionaire.

J. Martin Kohe, Your Greatest Power, A Different World Ltd., 1979.

WEIGHT

Now that I weigh — pounds I feel fine, I look great and my physical condition is excellent.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

WELL BEING

I am responsible for creating my life.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

There is no limit to how good I can feel.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I have the power to feel good.

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

Table of contents

I love my body and accept it totally.
I love doing what makes me feel good.
It is good to be alive on this earth.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I experience continual well being.

Professor Robert Tocquet, The powers Of The Will, Godefroy Publications, 1989.¥

I am at home in my body.

Louise L. Hay, You Can Heal Your Life, Hay House, 1984.

I'm doing fine, intellectually, physically and financially. I feel fine, day and night.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I feel good about myself.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

I feel good, really good.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I feel fine.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

I feel better and better.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

I feel relaxed and happy. I feel good about myself.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

I am completely calm... I experience a marvelous sensation of calm and harmony spreading through me... a feeling of indescribable joy flows from my heart.

Professor Kurt Tepperwein, Think And Heal, Godefroy Publications, 1984.

My persevering quest for the principles of truth will be sure to

Table of contents

produce an inner change which, in turn, will produce a warm feeling of well being.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I refrain from doing anything that may inadvertently cause me harm.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

WILLPOWER
(Also see Self Control, Self Confidence)

I have confidence in myself. My willpower is already very strong, and it is getting stronger and stronger. I want to succeed. I want to follow the examples of those who have attained the goals they set for themselves. I will persevere because I know with certitude that properly directed willpower will succeed when it is working for a just and honorable goal.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I have willpower... I never give in to outside influences... I don’t care what people may think.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

I have the willpower to act.

Jean Chartier, How To Acquire A Superior Personality, Dangles Press, 1971.

I desire —— (specify) and I am in the process of obtaining it.

Emile Coue, Complete Works, Astra Publications, 1976.

I do not let circumstance defeat me. I control them psychologically.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

Table of contents

I can act according to my reason, and that is how I want to act.

Paul Clement Jagot, How To Develop Your Personal Magnetism, Dangles Press, 1982.

I can encourage my mind to think in a certain way, and direct my actions towards accomplishing a certain project.

When my willpower is intensified to the point where I can defy circumstances and realize the project I envisage, I will achieve results in my life which will astonish everyone.

Franck Rudolph Young, Cyclomancia, SIP, 1966.

I can have or be anything I want as long as I have enough energy and willpower.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

I can do it and I want to do it.

Leon Kendal, Personal Magnetism, Godefroy Publications, 1911.

I can do it! It's easy. I can do this task better than anyone else. Thanks to the power of my inner Guide no obstacle can stop me. I succeed at everything I do!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I know what I want and I believe I can get it.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

I know exactly what I want and I authorize my subconscious to act according to the law so that it becomes immediately manifest.

All paths are free, all doors are open. At this very moment all my actions are perfect, and I will get what I want.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I feel my willpower getting stronger and stronger.

Professor Lawrence Powers, Ten Secrets Of Hypnotic Power, Godefroy Publications, 1982.

I am in control of my actions, my thoughts and my emotions. I

Table of contents

am free of all restraints. My willpower is getting stronger and stronger. I have confidence in myself and in the future.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

I am a centre of conscious willpower.

Isabelle Capanio, The Powers Of the Will, De Vecchi Publications, 1987.

(I am going to develop the technique of self hypnosis in order to develop my willpower to improve, my desire to study, to learn and to make progress in all aspects of my life.)

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

I want to train my willpower until it is strong enough to change my life.

Paul Clement Jagot, The Power Of The Will, Dangles Press, 1973.

I want, I can, and I am sure of myself.

Professor Lawrence Powers, The Ten Secrets Of Hypnotic Power, Godefroy Publications, 1982.

I want, therefore I can.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

I want... I want... I want...

Claude M. Bristol, Harold Sherman, Your Inner Power = TNT, A Different World Publications, 1954.

Playing my role means trying to acquire the intellectual and moral qualities of a man of willpower. I want it with all my strength, with all the power I have. I want to create a beautiful future.

My willpower is getting stronger and stronger.

To play my role faithfully, I first develop the attitude of a person who is strong and who wants to succeed.

Professor Robert Tocquet, The Powers Of The Will, Godefroy Publications, 1989.

My willpower is getting stronger and stronger, more and more powerful.

Marcel Rouet, Techniques And Practice Of Hypnotism, Paris Productions N.O.E., 1974.

Table of contents

My willpower is consolidating.

Marcel Baugin, Hypnotism, Suggestion and Telepsyche, Scientific Distribution, 1956.

When I want to, I can.

Norman Vincent Peale, When You Want, You Can!, A Different World Press, 1974.

WINNING

I now win all the time.

Louis Proto, Self Healing, Piatkus Publications, 1990.

I won! I won! I won!

Richard Corriere, Joseph Hart, Getting Into Psychological Shape, Les Editions de l'Homme, 1979.

I have the right to win.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I know that everything depends on me, and nothing but me. Everything will depend on the way I see things, and on what I do. That's what success is all about, and that's why I always win.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

I play to win.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I'm a winner. I'm a winner.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

I'm a winner. I'm a likable person, I'm enthusiastic, warm and honest, the type of person people like to be with.

Every day my personality becomes stronger and more radiant, revealing ever more clearly the positive, optimistic spirit that animates all my actions.

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

Table of contents

My ability to become a full time winner depends entirely on my determination to want to think like a winner, and erase all self images of being a loser that I may have accumulated in the past. My capacity for being a person with No Limits, and reaching beyond even my own wildest dreams is entirely in my own hands.

Wayne. W, Dyer, The Sky's The Limit, Mortagne Publications, 1988.

I am a winner in my life. I am not a victim, I'm a winner!

Shad Helmstetter, The Power Of Inner Motivation, Published by Le Jour, 1987.

WISDOM

Now joy, wisdom and the peace of God are uppermost in my mind.

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

With God everything is possible. All powerful God is the spirit living in me, and the source of all wisdom and enlightenment.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

I trust myself and believe in my innate wisdom.

Liah Kraft-Macoy, 30 Days To Happiness, Stillpoint, 1987.

I pray every day, not to amass more wealth, but to become wiser so that I can recognize and benefit from the abundance of goods which are always in my possession, and take pleasure in them.

W. Clement Stone and Napoleon Hill, Success Through Positive Thinking, Godefroy Publications, 1978.

I am wiser than I think. When I rid my mind of false notions, wisdom surges upward like an underground spring.

Vernon Howard, Psycho-Pictography, S.I.P., 1965.

I am full of the wisdom of divine life.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

Table of contents

I am a balanced being of love. Creation is my playground. I open to my inner wisdom and live it every day.

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

My heart contains perfect wisdom.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

WISDOM - SUBCONSCIOUS

My subconscious knows exactly what is good for me, and what can help me in life.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

WISH

It's okay to ask for what I want - and get it.

Louis Proto, Self Healing, Piatkus Publications, 1990.

——— (specify your wish) will come to me easily and without effort.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

Life is a self fulfilling prophesy; I won't necessarily get what I want in life, but in the long run I will usually get what I expect.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

WIFE

My wife wishes to be loved and respected as a person.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

Table of contents

WONDER

I never lose my sense of wonder about life.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

WORK (Also see Reward, Salary, Worth)

Today I'll finish all the work I have joyously and easily. Everything I have to do interests me. My mind is constantly present and alert; I am ready to use the opportunities this work, or any other week provide, to do my best to succeed.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

In my life work and play are the same.

Shakti Gawain, Reflections In The Light, New World Library, 1978.

I like my job, my colleagues and my responsibilities. Through them I add value to life, and thus I become useful to God.

R. Charles Barker, The Science Of Success, Dangles Press, 1983.

I like my work, therefore my work likes me.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I like my work. It fulfils me on both a creative and financial level.

Shakti Gawain, Creative Visualization Techniques, Soleil Publications, 1978.

I choose to do this because it is in my best interests, based on the current realities and my current goals. No one is forcing me to do this, and I don't 'have to' do it. I've assessed the consequences and alternatives and on that basis I choose to do this.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

I make my work an exercise in concentration: I do it consciously,

Table of contents

with interest, and I apply myself body and soul. In no time at all my work becomes a pleasure. Instead of being bored, I discover new sources of interest and opportunities for success in my work that I had no idea existed until now.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I find my work more and more fulfilling.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

I'm happy in my work.

Emrika Padus, Encyclopedia of Emotions And Health, Edi Inter, 1991.

I work well.

Editorial Staff, Practical Health Guides, How To Stimulate Your Body's Natural Defences, Godefroy Publications, 1989.

My work is interesting and easy, and I do it with pleasure. Problems are made to be overcome. I will see things through. And I have the strength to do even better. Not only does my work provide me with real benefits, it also enriches my mind.

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

My work is a joy and a pleasure.

Louis Proto, Self Healing, Piatkus Publications, 1990.

When I think about my business and the office I am filled with love and joy, inner peace and harmony.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

All my work bears fruit in accordance with the divine order of things.

Dr. Joseph Murphy, Exploit The Power Of Your Subconscious, Tchou / Ariston, 1962.

All work becomes simple and pleasant for me.

R.L. Charpentier, Autosuggestion And Its Practical Application, Champs Elysees Publications, 1958.

Table of contents

WORRY

Instead of worrying about being afraid, I am going to do something about it. I am going to read various books explaining the psychology of fear. I am going to learn the difference between normal and abnormal fears. If I understand the facts about various fears I will be more successful in overcoming them.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

God is watching over me, and that's wonderful!

Dr. Joseph Murphy, These Truths Will Change Your Life, Published by Le Jour, 1982.

I describe the things around me to myself. While I do that I stop thinking about my worries.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I am getting stronger day by day. At the same time all my worries and fears, all my inner problems are dissolving. I am strong and free. I have all the energy of my Guide at my disposal, and S/He will surely lead me to my goal. My goal is near, and I will succeed!

K.O. Schmidt, Success At Your Service, Astra Publications, 1986.

I don't want to worry about that now; I'll worry about it tomorrow.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

Stop! Fear and worrying are a waste of time and energy, and they block me from using my skills.

Dr. Marty Seldman, Super Selling Through Self Talk, Price Stern Sloan, 1986.

God is the light shining on my path; I am no longer groping, trembling with vain hopes, I see no seeds of worry or struggle on my path, but only seeds of joy and love of life.

Robert Collier, Wealth At Your Doorstep, S.I.P., 1959.

Table of contents

I eliminate worrying, the major consumer of wasted time, as much as possible.

Christian H. Godefroy and John Clark, How To Have More Time, Godefroy Publications, 1989.

I count my reasons for being happy instead of unhappy.

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

Worries and negative thoughts slide off me like water off a duck's back.

Christian H. Godefroy, Positive Thinking: The Subliminal Method, Godefroy Publications, 1987.

My mind is free of all worry.

Francoise and Michel Moine, Develop Your Psi Powers, Stock Editions, 1982.

My mind is free of doubt and worry.

Since these words come from my soul, they erase all my negative thoughts and negative feelings.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

No matter what happens or doesn't happen to me today there is one thing I am sure of: I want to get the most I can out of this day.

Orison Swett Marden, The Joy Of Living, J.H. Jeheber Publications.

Two months from now I will have completely forgotten this setback, so why should I worry about it today?

Why not assume the attitude I'll probably have in two months right now?

Dale Carnegie, Overcome Your Worries, Flammarion, 1944.

From now on the setbacks in life no longer affect me. If I am assailed by doubt, fear and worry, I know that my faith will overcome them.

Dr. Joseph Murphy, Mastering Yourself And Others, Published by Le Jour, 1988.

If I am sometimes assailed, pursued, haunted by harmful and

Table of contents

unhealthy thoughts, by fears, phobias, temptations or resentment, I know they will fade away gradually, seeming to melt from my mind, growing faint like a distant cloud which will soon disappear completely.

As dreams disappear when I awaken, so will all these vain images disappear as well.

Emile Coue, Complete Works, Astra Publications, 1976.

WORTH (Also see Wealth, Work, Salary)

Today I will multiply my worth a thousand times.

Og Mandino, The Greatest Secret In The World, A different World Press, 1979.

Every day I multiply my worth a hundred times, and my success grows as a result.

Day by day, in all ways, I am becoming better and better. All areas of my life are enriched, because I multiply my worth a hundredfold.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

I am aware of my worth.

Claude Arpel, Self Confidence: The Subliminal Method, Procauvi Publications, 1986.

I have worth because I struggle to survive.

Matthew McKay and Patrick Fanning, Self Esteem, New Harbinger Publications Inc., 1990.

I evaluate my real worth by asking how good I feel about myself.

Recognizing my own worth is the beginning of a mature acceptance of myself and others.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I believe I am unique and special.

Denis Waitley, Seeds Of Greatness, Pocket Books Press, 1984.

Table of contents

I am a rare, exclusive, different, unique individual on this earth. These attributes give me enormous worth.

Zig Ziglar, Rendez-vous At The Top, A Different World Publications, 1975.

I am a worthy person.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

I am unique and unlimited.

Jean-Marie Boisvert and Madeline Beaudry, Self Affirmation and Communication, Godefroy Publications, 1979.

I am unique. My worth is multiplying, allowing me to do a job which I like and which pays very well.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

(I deserve to be who I am.)

Shakti Gawain, Reflections In The Light, New World Library, 1978.

The best way to increase my worth is to improve my self image.

Charles Albert Poissant & Christian Godefroy, The Secret Of Being A Millionaire, Godefroy Publications, 1987.

The more I realize my true worth, the more everybody respects me.

Louis Proto, Self Healing, Piatkus Publications, 1990.

Whatever anyone says or does to me, I remain a worthy person.

Alan Houel, How To Deal With Difficult People, Godefroy Publications, 1990.

WOUNDS (Also see Pain, Numbness)

Now the pain is disappearing from my —— (name the part of the body) and my blood is coagulating rapidly. The pain is diminishing rapidly. I won’t feel any more pain for half an hour. It will disappear completely. Now I’m going to count to five. And on the count of five my pain will disappear completely for half an hour (or substitute the

Table of contents

desired period). One, two, three, four, five!

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

WRINKLES

I am relaxing the muscles in my face... in my forehead... I feel a cool wave of relaxation...

Every time I feel myself getting tense or upset... I will think of the word serenity... and immediately all the muscles in my face will relax.

My face will look younger... it is going to look younger... releasing... relaxing all my features will prevent wrinkles from forming... smooth over those that are already there... and chase away my worries.

Marcel Rouet, Mastering Your Subconscious, Dangles Press, 1982.

Table of contents

YOUTH

I do not accept the passive lifestyle of many elderly persons. I live an active life.

I refuse to always think about the past, as too many elderly persons do. I am alive today; I live in he present moment.

Dr. Maxwell Maltz, Psychocybernetics and Self Realization, A Different World Ltd. Publications, 1970.

I am going to remain young in mind and heart by finding new pleasures, new interests and new friends.

Frank S. Caprio, M.D. & Joseph R. Berger, Helping Yourself With Self Hypnosis, Prentice Hall Inc., 1974.

My body is getting younger and more vigorous. I am regaining (or maintaining) optimum use of my bodily functions. My hearing, my vision and my memory are becoming more and more efficient and healthy. I am in excellent health. My face looks younger every day, and I'm looking better and better. I feel more and more young, more and more relaxed, more and more healthy. I am regaining my youthful enthusiasm and sense of curiosity. Youth. Youth. Youth. I am more and more energetic, creative, and young in body and mind.

Christian H. Godefroy, Helping Yourself Through Self Hypnosis, Godefroy Publications, 1985.

(I can be whoever I want to be with total support. I can go fast or slow - it's my choice.)

Barbara J. Gress, Personal Power Cards, Aslan Publishing, 1991.

I'm losing weight... I am happy to feel so good about myself...

Table of contents

day by day everything is getting better... my skin is supple... I feel younger and younger... slimmer and slimmer... full of newfound energy.

Professor Kurt Tepperwein, Secret Techniques Of Hypnosis, Godefroy Publications, 1981.

Table of contents

Table of Contents

ABUNDANCE 10
ACCOMPLISHMENT (Also see Success) 11
ACNE (See Urticaria, Eczema) 11
ACTION (Also see Opportunity) 11
ADVERSITY 13
AEROPHAGY (Flatulence) 13
ADVICE 14
AFFECTION 14
AFFIRMATION 14
AGING 14
AGITATION 15
AGREEMENT 15
AGGRESSION 15
AIDS 16
ALCOHOLISM (Also see Sobriety) 16
ALLERGIES 18
ALLERGIES (Food) 18
ALTRUISM 19
AMBITION (Also see Vitality, Dynamism, Enthusiasm) 19
ANAEMIA 21
ANAESTHESIA (Also see Pain, Wounds) 21
ANAESTHESIA - DENTAL 22
ANGER (Also see Migraines) 22
ANGINA (Chest) 23
ANSWERS 24
ANXIETY 24
ANXIETY - SOCIAL 25
APLOMB 26
APPEARANCE (PHYSICAL) 26
APPETITE (Also see Digestion, Stool) 27
APPREHENSION 27
APPROVAL 27
ARCHERY 28
ARTHRITIS 28
ARRHYTHMIA 29
ASKING 29

ASSIDUITY (Also see Perseverance) 29
ASSIMILATION 30
ASSISTANCE 30
ASSISTANCE - SPIRITUAL 30
ASSOCIATES 31
ASSURANCE (Also see Self Confidence) 31
ASTHMA 32
ASTHMA ATTACK 34
AUDACITY (Also see Courage) 34
AUTOSUGGESTION (Also see Hypnosis) 35
AVAILABILITY 35
AWARENESS (See Self Awareness) 35
BAD CHARACTER 36
BAD HABITS (See Habits - Negative) 36
BACKACHE 36
BALANCE (Also see Peace, Strength, Wisdom, Health, Harmony) 36
BALDNESS 37
BEAUTY (Also see Health) 38
BEHAVIOR 38
BEING 38
BELIEF 39
BELONGING 39
BENEVOLENCE (Also see Sincerity) 39
BEST 40
BIRTHING 40
BLAME 40
BLESSING 41
BLISS 41
BLUSHING 42
BODY 42
BOREDOM 42
BOWLING 43
BRAGGING 43
BRAVERY (Also see Strength, Courage) 43
BREAKING UP 43
BREASTS 43
BREATHING 44
BRIDGE 45
BUDGET 45
BUSINESS (Also see Money) 45

BUYING 46
CALM (Also see Self Control).. 47
CANCER 48
CARDIAC TROUBLE 49
CARE 49
CAREER 49
CHALLENGE 50
CHANGE (Also see Habit)... 51
CHARM (Also see Slimness, Health, Sincerity) 52
CHILL 53
CHOICE OF PROFESSION 53
CIRCULATION (Also see Anemia).. 53
CIRCUMSTANCE 54
CLARITY 54
CLIENTS 54
COLD (Common) 55
COLIC (Biliary or Hepatic) 55
COMFORT (Feeling At Ease) 55
COMMITMENT 56
COMMUNICATION (Also see Confidence, Tension)..................... 56
COMPANY 58
COMPASSION 58
COMPETENCE (Also see Money, Skill) 58
COMPETITION 59
COMPLEX 60
COMPLEX - INFERIORITY 60
COMPLEX - SEXUAL 61
COMPLIMENTS 62
COMPOSURE.. 62
COMPREHENSION 62
CONCENTRATION (Also see Delegating) 63
CONFIDENCE 65
CONFIDENCE IN THE FUTURE 66
CONFIDENCE - SELF (See Self Confidence) 67
CONFORMING 67
CONGRATULATIONS 67
CONSENSUS 68
CONSIDERATION (Also see Respect) 68
CONSTIPATION 69
CONSTRAINT 69

CONTACT 69
CONTRACT 70
CONVERSATION 70
CONVICTION 70
COOPERATION (Also see Help) 71
COUGH 71
COURAGE (Also see Dynamism, Resistance, Energy, Enthusiasm, Strength, Bravery) 71
COURTESY 72
COWARDICE (See Lying, Laziness) 73
CREATIVITY (Also see Sensitivity, Love) 73
CREDIT 75
CRISIS 76
CRITICISM 76
CURIOSITY 77
DANGER 78
DEAFNESS 78
DEBT (Also see Money, Projects) 78
DECISIONS 79
DEFEAT 81
DEFEATISM 81
DEFENCE 81
DEFIANCE 81
DELEGATING 82
DEPENDENCE 82
DEPRESSION 83
(Also see Conditioning, Confidence, Happiness, Health, Abundance, Optimism) 83
DERMATOSIS 85
DESIRE 85
DESIRE - SEXUAL (See Sexual Desire) 86
DESTINY 86
DETERMINATION (Also see Energy) 87
DIALOG 89
DIET (Also see Hygiene, Negative Habits) 89
DIFFERENCE 90
DIFFICULT TASKS 90
DIFFICULTY (Also see Worry) 90
DIGESTION (Also see Appetite, Stool) 91
DIGNITY 93

DIPLOMA 93
DIRECTING OTHERS 94
DISAGREEMENT (Also see Feud).. 94
DISAPPOINTMENT 94
DISAPPROVAL 95
DISCIPLINE (Also see Laziness, Disorder) 95
DISCOMFORT.. 95
DISCOURAGEMENT 96
DISCUSSION 96
DISOBEDIENCE 96
DISORDER (Also see Discipline, Laziness) 97
DISSATISFACTION 97
DISTRACTION 97
DISTRESS 98
DOUBT (Also see Self Confidence) 98
DREAMS (Also see Fear of the Unknown) 98
DRIVING 99
DRUG ADDICTION 99
DRUGS 100
DUTY 101
DYNAMISM (Mental - Also see Ambition, Enthusiasm, Vitality) 101
DYSFUNCTION (Organ) 102
DYSPEPSIA 102
EASE 103
ECONOMIZING 103
ECZEMA (Also see Acne, Urticaria) 103
EDUCATION 104
EFFICIENCY 105
EFFORT 107
EGOISM 107
ELIMINATION (Bowel Movement) 107
ELOCUTION 107
EMOTION 109
EMOTION - NEGATIVE 109
(Also see Fear, Anxiety, Nervousness) 109
EMOTIONAL SCARS 110
EMPHYSEMA (Also see Asthma Attacks) 110
ENCOURAGEMENT 110
ENDURANCE (Also see Dynamism, Courage) 111
ENERGY (Also see Courage, Determination, Strength, Vitality, Health)112

ENERGY - CREATIVE 114
ENERGY - VITAL 114
ENJOYMENT 114
ENLIGHTENED MIND 114
ENTERITIS 115
ENTERPRISING SPIRIT 115
ENTHUSIASM (Also see Ambition, Dynamism, Vitality, Energy, Courage) 116
ENURESIS (Bedwetting) 118
ENVY 119
EQUILIBRIUM (See Balance) 119
EQUANIMITY 119
ERRORS (See Mistakes) 120
ESTEEM (Also see Self Esteem) 120
EVOLUTION 120
EVOLVING 120
EXAMS 120
EXCHANGE 121
EXCUSES 122
EXERCISE (Also see Obesity, Nutrition) 122
EXPERIENCE 123
EXPRESSING ONESELF (See Self Expression) 124
FAILURE 125
FAILURE (In School) 126
FAITH (Also see Fear) 126
FALSE BELIEFS 126
FAMILY LIFE 127
FASCINATION 127
FATIGUE 128
FAULTS 128
FEAR (Also see Emotional Paralysis, Anxiety, Nervousness, Guilt, Rejection) 129
FEAR OF ANIMALS 132
FEAR OF DEATH 132
FEAR OF ELEVATORS 132
FEAR OF EXAMS (Also see Stagefright) 132
FEAR OF FAILURE (Also see Disapproval) 133
FEAR OF FLYING 133
FEAR OF REALITY 133
FEAR OF REJECTION 134

FEAR OF THE DARK 134
FEAR OF THE FUTURE 134
FEAR OF THE OPPOSITE SEX 135
FEAR OF THE UNKNOWN 135
FEAR OF VEGETABLES 136
FEAR OF WATER 136
FEELINGS 136
FEELINGS - NEGATIVE 137
FEELINGS - POSITIVE 137
FERMENTATION (Intestinal) 138
FEUDING 138
FEVER 138
FIBROMA 139
FIGHTING SPIRIT 139
FILING 139
FINANCE 139
FIRMNESS 140
FLAB 141
FORCE OF NATURE 141
FOREIGN LANGUAGES 141
FORGIVENESS (Also see Resentment) 142
FORESIGHT 143
FORTUNE 143
FOUNTAIN OF YOUTH 144
FRANKNESS (Condor) 144
FRATERNITY 144
FREEDOM 144
FREE TIME 146
FRIENDSHIP 146
FRIGIDITY 147
FRUGALITY 149
FRUSTRATION 149
FULFILLMENT 150
FUTURE 151
GAMBLING (Games Of Chance) 152
GASTRITIS (Inflammatory) 152
GENEROSITY 152
GIFTS (Talents) 153
GOALS (Aims) 153
GOLF 155

GOOD HUMOR 155
GOODNESS 156
GRATITUDE 156
GREED 157
GRIEF (Also see Forgiveness) 157
GRIEVANCES 157
GROWTH 157
GROWTH - PHYSICAL 158
GUILT (Also see Fear, Rejection) 158
HABIT 160
HABITS - NEGATIVE (Also see Diet, Habit, Hygiene) 160
HABITS - POSITIVE 161
HAIR 161
HAIR LOSS 162
HALITOSIS 162
HANDICAP 162
HAPPINESS (Also see Love of Self, Confidence, Intimacy) 162
HARMONY 165
HARMONY - CONJUGAL 165
HARMONY - FAMILIAL 167
HARVEST 167
HATE (Also see Love) 168
HEALING 168
HEALTH - GENERAL (Also see Beauty, Vitality, Confidence, Happiness, Looking Good, Slimness, Charm, Balance, Harmony, Self Expression, Peace, Success, Prosperity, Love of Life, Energy) 170
HEART 174
HEART ATTACK (See Tachycardia) 175
HELP (Also see Cooperation) 175
HESITATION 176
HINDRANCES 176
HOMEWORK (Also see Studies) 176
HOMOSEXUALITY 176
HOME 177
HONESTY (Also see Frankness, Sincerity) 177
HONOR 177
HOPE 178
HUMILIATION 178
HUMOR 178
HURT 179

HYGIENE (Also see Negative Habits, Dieting) 179
HYPERTENSION 180
HYPNOSIS 180
IDEALS 181
IDEAS 181
IDEAS - LUCRATIVE 182
IDEAS - NEGATIVE 183
IDEAS - PRECONCEIVED 183
IDENTITY 183
IGNORANCE (Also see Sickness) 184
ILLNESS (Also see Pain, Ignorance) 184
ILLUSION 185
IMAGINATION 186
IMMUNITY 187
IMPASSE 187
IMPATIENCE 187
IMPOTENCE (Also see Premature Ejaculation) 187
IMPULSE - NEGATIVE 188
INCOME 189
INDECISION 189
INDEPENDENCE 189
INDEPENDENCE - FINANCIAL 190
INDIGESTION 191
INDIVIDUALITY 191
INFARCTUS 191
INFERIORITY (See Complex) 191
INFLUENCE 191
INFORMATION 192
INNER DIALOG 193
INNER GUIDE 193
INNER PEACE 194
INNER STRENGTH (See Strength - Inner) 195
INSOMNIA 195
INSOMNIA - CHILDREN 198
INSPIRATION (Also see Creativity, Optimism) 198
INTELLECT 199
INTELLIGENCE (Also see Self Confidence) 199
INTIMACY 200
INTRANSIGENCE 200
INTRODUCTIONS 200

INTUITION 201
INVESTMENT 202
INVOLVEMENT 202
IRRITATION 203
ISOLATION 203
JEALOUSY 204
JOBS (Also see Remuneration) 205
JOIE DE VIVRE (See Love Of Life) 206
JOY 206
JUDGMENT (Also see Action, Memory) 207
JUSTICE 208
JUSTIFICATION 208
KLEPTOMANIA (Also see Honesty) 209
KNOW-HOW 209
KNOWLEDGE 209
LACK 211
LAUGHTER 211
LAZINESS 00(Also see Cowardice, Lying, Disorder, Discipline) 211
LEARNING (Also see Knowledge) 212
LEARNING WHILE ASLEEP 214
LEISURE 214
LESIONS 215
LEVEL HEADEDNESS 215
LIFE 215
LIKABILITY 215
LIMITATION 216
LISTENING 217
LOGIC 217
LOOKING GOOD (Also see Weight, Losing Weight, Health) 218
LOSING WEIGHT (Also see Strength, Body Fitness) 218
LOST OBJECTS 221
LOVE (Also see Success, Happiness) 221
LOVE - FILIAL (Also see Creativity, Sensitivity, Optimism, Peace, Joy, Tenderness) 223
LOVE LIFE 224
LOVE OF LIFE (Also see Prosperity, Happiness, Self Confidence, Courage, Peace, Love) 224
LOVE OF SELF 225
(Also see Self Confidence, Self Esteem) 225
LOYALTY 226

LUCIDITY (Also see Self Control) 226
LUCK (Also see Money) 227
LUNG DISEASE 227
LYING (Also see Cowardice, Laziness) 228
MAGNETISM (Also see Influence) 229
MAIL 231
MANAGEMENT 231
MANAGEMENT - MONEY 231
MANAGEMENT - TIME 232
MARRIAGE 233
MATURITY 233
MEDICAL TREATMENT 233
MEDITATION 233
MEETING PEOPLE 233
MEETINGS 235
MELANCHOLY 236
MEMORY (Also see Concentration, Judgment, Willpower) 236
MENOPAUSE 239
MENSTRUATION 239
MENTAL CONTROL 240
MENTAL FACULTIES (Also see Concentration) 240
MENTAL FATIGUE 240
MENTAL PROJECTION 241
MENTAL RETREAT 241
MERIT 241
MIGRAINE (Also see Emotion) 242
MIND (Also see Memory, Concentration) 243
MIND PROJECTION 244
MIRACLES 244
MISOGYNY 245
MISTAKES 245
MISTRUST 247
MISUNDERSTANDING 247
MODERATION (Also see Discernment) 247
MONEY (Also see Business, Luck, Competence, Creation, Projects, Debts, Vocations) 248
MOODS 250
MOROSITY 250
MOTIVATION 251
MOTIVATION - SCHOOL 252

MOVING 252
MUSCLES 252
MUTUAL AID 253
MYOPIA (See Nearsightedness) 253
NAIL BITING 254
NATURAL 254
NEARSIGHTEDNESS 254
NEED 255
NEGOTIATING 256
NERVOUS BREAKDOWN (Also see Nervousness) 257
NERVOUSNESS (Also see Agitation, Anxiety, Fear, Nervous Breakdown) 257
NERVOUS SYSTEM 258
NEW BEGINNING 258
NOISE 258
NOSTALGIA 258
NOVELTY 259
NUMBNESS 259
NUTRITION 260
Obesity (Also see Nutrition, Physical Exercise) 261
OBJECTIVES (Also see Goals, Self Control) 262
OBJECTIVES - FINANCIAL 264
OBLIGATION 265
OBSESSION 265
OBSTACLES 265
OFFERING 266
OPINIONS 266
OPPORTUNITY 267
OPTIMIZING 267
OPTIMISM (Also see Depression, Inspiration, Positive Thinking) 268
OPULENCE 269
ORDER 269
ORGANIZATION (Also see Efficiency) 270
ORIENTATION (See Choice of Profession) 270
ORIGINALITY 270
OUT OF BODY EXPERIENCE 271
OVERWORK 271
PACE 272
PAIN (Also see Hepatic Colic, Illness, Wounds, Anesthesia) 272
PARALYSIS 273

PARTNERSHIP 274
PASSION 274
PATIENCE (Also see Understanding) 274
PEACE (Also see Joy, Love, Wisdom, Prosperity, Health, Success) 275
PEACE OF MIND 276
PERFECTION 276
PERFECTIONISM 276
PERFORMANCE (Also see Self Image) 277
PERFORMANCE - SPORTS 277
PERSEVERANCE 278
PERSONAL AFFAIRS 279
PERSONAL DEVELOPMENT 279
PERSONALITY 280
PERSUASION 281
PESSIMISM 282
PHOBIAS (Also see Fear, Negative Thoughts) 282
PHYSICAL STRENGTH (See Strength - Physical) 282
PLANNING (Also see Money) 282
PLANS 285
PLAY 285
PLEASING OTHERS 285
PLEASURE 286
PLEASURE - SEXUAL 286
PLEURISY 286
POSITIVE MENTAL ATTITUDE 286
POSSESSION 287
POSSIBILITY 287
POTENTIAL 287
POVERTY 288
POWER (Also see Self Confidence) 288
POWER - PSYCHIC 289
POWER - SPIRITUAL 290
POWER - SUBCONSCIOUS 290
PRAISE 290
PRAYER 290
PRECAUTIONS 291
PREGNANCY 291
PREJUDICE 292
PREMATURE EJACULATION (Also see Impotence) 292
PREOCCUPATION 292

PRESSURE 292
PRIDE 293
PRIORITIES 293
PROBLEMS 293
PROCRASTINATION 296
PRODUCTION 298
PRODUCTIVITY 298
PROFESSION (Also see Wealth) 299
PROFIT 299
PROGRESS 299
PROJECTS (Also see Debt, Money) 300
PROMISES 301
PROMOTION 301
PROSPERITY (Also see Happiness, Budget, Love Of Life, Health, Peace, Success) 301
PROTECTION 303
PSYCHIC SHIELD 303
PUBLIC SPEAKING 303
PUBLISHING 305
PULMONARY DISEASE (See Lung Disease) 305
PUNCTUALITY 305
PURIFICATION 305
QUALIFICATIONS 306
QUALITY 306
QUALITY OF LIFE 306
RADIANT 307
REACTION 307
READING 307
REALIZATION 308
REALIZATION - SELF 309
REALISM 309
REBIRTH 309
RECEPTIVITY 310
REFLECTION 310
REFUSAL 311
REGULARITY - ABDOMINAL 311
REGULARITY - RESPIRATORY 311
REJECTION 312
REJOICING 312
RELATIONS - COMMERCIAL 312

RELATIONS - FAMILY 313
RELATIONS - HARMONIOUS 313
RELATIONS - HUMAN 314
RELATIONS - PERSONAL 317
RELATIONS - PROFESSIONAL 317
RELAXATION 318
RELAXATION - DIGESTIVE 320
RELAXATION - MENTAL (See Inner Peace) 320
REMUNERATION (Also see Job) 321
REPARTEE 321
REPRESSION 321
REPROACH 321
RESENTMENT (Also see Forgiveness) 322
RESOURCES 323
RESPECT (Also see Consideration) 323
RESPONSIBILITY 324
REST (Also see Sleep) 325
REST - MENTAL 326
RESULTS (Also see Work) 326
RESULTS - SCHOLASTIC 327
RETIREMENT 327
REVENUE (See Income) 327
REWARD 327
RICHES (See Wealth) 328
RISK 328
RIVALRY 329
ROUTINE 329
SADNESS 331
SALARY (Also see Work, Value) 331
SALES 332
SALES - REAL ESTATE 334
SATISFACTION 334
SAVINGS 335
SCHOOLWORK 335
SECURITY 336
SEDUCTION 336
SELF ACCEPTANCE (Also see Self Confidence, Self Expression) 337
SELF AFFIRMATION 338
SELF AWARENESS 339

SELF CONFIDENCE (Also see Self Esteem, Self Control, Competence, Depression) 340
SELF CONTROL (Also see Objectives, Calm, Self Confidence, Willpower) 343
SELF CRITICISM 345
SELF ESTEEM (Also see Self Confidence, Self Love) 345
SELF EVALUATION 347
SELF EXPRESSION (Also see Self Acceptance, Self Confidence, Health, Happiness) 347
SELF FORGIVENESS 348
SELF HEALING 349
SELF HYPNOSIS 349
SELF IMAGE 349
SELF IMPROVEMENT 351
SELF LOVE (See Love Of Self) 352
SELF PUNISHMENT 352
SELF REJECTION 352
SELF RESPECT 352
SELF SUFFICIENCY 352
SENSATION 352
SENSE OF SMELL 353
SENSES 353
SENSITIVITY 353
SENSUALITY 354
SERENITY 354
SERVICE 354
SETBACKS 355
SEXUAL BLOCKS 355
SEXUAL DESIRE 355
SEXUALITY 356
SHARING 357
SHORTNESS OF BREATH (Also see Breathing, Smoking) 358
SINCERITY (Also see Benevolence, Warmth, Honesty) 359
SKIN 359
SLANDER 359
SLAVERY 360
SLEEP (Also see Rest) 360
SLIMNESS (Also see Charm, Looking Good, Health, Weight Loss) 362
SMILING 363
SNACK 363

SOBRIETY (Also see Alcoholism) 364
SOLITUDE 365
SOLUTIONS 366
SORROW 367
SOULMATE 367
SPEECH MAKING 368
SPENDING 368
SPIRITUALITY 369
SPORT 369
STAGEFRIGHT (Also see Fear Of Exams) 370
STAYING IN SHAPE 371
STOMACH ACHE 371
STOOL (See Digestion, Appetite) 372
STRENGTH (Also see Courage) 372
STRENGTH - INNER 373
STRENGTH - PHYSICAL (Also see Losing Weight, Staying In Shape) 373
STRESS 373
STUBBORNNESS 375
STUDIES 375
STUTTERING 376
SUBCONSCIOUS MIND 377
SUBCONSCIOUS PROGRAMMING 377
SUBMISSIVENESS 377
SUCCEEDING 377
SUCCESS (Also see Wealth, Happiness, Self Love, Peace, Prosperity, Health) 379
SUCCESS - FINANCIAL (Also see Marketing, Happiness) 382
SUFFERING 383
SUGGESTION - POSITIVE 383
SUPERIORITY 383
SUPPLENESS 384
SUPPORT 384
SURGERY 384
SURPASSING 384
SWEETS 385
SYMPATHY 386
TACHYCARDIA 387
TACT 387
TALENT (Also see Gift, Salary, Service) 387
TELEMARKETING 388

TELEPATHY 388
TELEPHONE 389
TEMPTATION 390
TENACITY 390
TENDERNESS (See Love) 391
TENNIS 391
TENSION (Also see Confidence, Communication) 391
TEST 392
THOUGHTS 393
THOUGHTS - NEGATIVE 393
THOUGHTS - POSITIVE 393
TIME 395
TIMIDITY (Also see Inferiority Complex, Self Confidence) 395
TOBACCO ADDICTION (Also see Shortness Of Breath, Cough) 396
TOLERANCE 401
TOOTHACHE (Also see Pain) 402
TORMENT 402
TOXINS 403
TRANQUILLITY 403
TRANSACTIONS 404
TRANSFORMATION 404
TRAVEL TIME 404
TROUBLE 405
TRUTH 406
TUBERCULOSIS 406
TUMOUR 407
ULCERS (Also see Digestion) 408
UNCERTAINTY 408
UNDERTAKINGS 408
UNEMPLOYMENT 409
UNEXPECTED EVENTS 409
UNHAPPINESS 409
UNIFORMITY 410
UNION 410
URINE RETENTION (Uremia) 411
URTICARIA (See Eczema, Acne) 411
USED CARS 411
UTERINE BLEEDING 411
UTERINE SPASMS 411
VACATION 412

VENGEANCE 412
VERTIGO (Dizziness) 413
VICE 413
VICTORY 413
VIGILANCE 414
VIGOR 414
VISION 414
VISION - POSITIVE 415
VISUALIZATION 415
VITALITY (Also see Ambition, Dynamism, Enthusiasm, Beauty, Health) 416
VIVACITY 416
VOCATION (Also see Money) 417
VOICE 417
WAKING UP 418
WARTS 418
WEAKNESS 419
WEALTH (Also see Profession, Success, Value) 419
WEIGHT 422
WELL BEING 422
WILLPOWER (Also see Self Control, Self Confidence) 424
WINNING 427
WISDOM 428
WISDOM - SUBCONSCIOUS 429
WISH 429
WIFE 429
WONDER 430
WORK (Also see Reward, Salary, Worth) 430
WORRY 432
WORTH (Also see Wealth, Work, Salary) 434
WOUNDS (Also see Pain, Numbness) 435
WRINKLES 436
YOUTH 437

Sacred G Ascender



www.CoryHerter.com

© 2008 - Cory Herter

Everyone and Everything within the vicinity of Sacred G will get blasted with positive vibes that unlock energy and boost performance. Increasing the amount of Sacred G you use will increase the amount of energy you have.

Sacred G Stickers come in 6 unique designs:



The Sacred G Spot is designed to physically cleanse your cells, freeing up more energy for the body to run more efficiently.



The Sacred G Transporter is designed to free up usable energy trapped as emotion in your past memories. Each night that you sleep on Sacred G, more and more energy is released restoring you to your natural state of Peaceful Bliss.



The Sacred G Ascender is designed to boost energy and increase self confidence by solving conflicts within your thoughts and belief systems. This enables you to perceive more information at once increasing your level of focus and reaction time.



The Sacred G TranceNDance is a combination of the first three designs plus advanced memory systems that accelerate the learning and downloading of new information from the collective consciousness.



The Sacred G Simulator is designed to upgrade your friendships and relationships by attracting new productive ones while empowering you to let go of old ones that no longer serve you. This design will increase the number of synchronicities in your life and create an awakened sense of adventure and purpose.



The Sacred G L.O.V.E.™ Activator combines all of the designs with a new motion activation system that takes you beyond your limits to achieve your goals. The Activator is the Ultimate State-of-the-Art DNA Activation Technology.

Visit the website to learn about the most advanced Sacred G Design called "Fusion" which incorporates every design into One.

Sleep / Pillow Case

Place the Sacred G beneath your pillow or inside your pillowcase design side up.

Notice how the Sacred G alters your sleep and dream states. The body frees up the most amount of energy while you sleep. Sacred G enhances this process continually increasing the amount of energy you feel.

Energized Water

Super Charge your water with Energy by placing it on top of the Sacred G.

Test: Take two glasses of tap water, place one on top of the Sacred G, and the other at least six feet away. Allow the water to charge overnight, then taste the difference between the two glasses in the morning. This test shows how Sacred G Technology not only cleans your water, but is also instrumental in physically cleansing the toxins from your body increasing energy.

> **"I will never ride a board that's not G'd out again!"**
>
> *Rob Dyrdek*

X-treme Performance Enhancement: Place the Sacred G on skateboards, surfboards, team uniforms, or any gear and equipment that you use. Watch as your performance is enhanced and your game is improved.

Visit the website to learn over 35 ways to use Sacred G to boost your energy, plus 5 cool tests that you can do. Also, be sure to watch the Sacred G episode on MTV's Rob & Big show to see how Sacred G can boost your Performance.

Visit the website to download all of the Sacred G Designs for FREE! Bonus: Watch a 3 hour video on the science of Sacred Geometry!

www.CoryHerter.com

© 2008 - Cory Herter

Sacred G Spot



www.CoryHerter.com

© 2008 - Cory Herter

SACRED G TRANSPORTER



www.CoryHerter.com

© 2008 - Cory Herter

SACRED G ASCENDER



WWW.CORYHERTER.COM

© 2008 - CORY HERTER

SACRED G TRANCENDANCE



www.CoryHerter.com

© 2008 - Cory Herter

Sacred G Simulator



www.CoryHerter.com

© 2008 - Cory Herter

SACRED G ACTIVATOR



www.CoryHerter.com

© 2008 - Cory Herter

BKS IYENGAR

FOREWORD BY YEHUDI MENUHIN

The Illustrated Light on Yoga



An Easy-to-follow Version
of the Classic
Introduction to Yoga

FOR SALE IN THE INDIAN SUBCONTINENT ONLY

DEDICATED TO MY REVERED GURUJĪ

Sāmkya-yoga-Śikhāmaṇi; Veda-kesari; Vedāntavāgīśa;
Nyāyāchārya; Mīmāmsa-ratna; Mīmāmsa-thīrtha

Professor, Śrīmān, T. Krishnamāchārya of
Mysore (South India), India

PRAYER

'I bow before the noblest of sages, Patañjali, who brought serenity of mind by his work on yoga, clarity of speech by his work on grammar and purity of body by his work on medicine.'

'I salute Ādīśvara (the Primeval Lord Śiva) who taught first the science of Haṭha Yoga – a science that stands out as a ladder for those who wish to scale the heights of Rāja Yoga.'

PART I

What is Yoga?

The word Yoga is derived from the Sanskrit root yuj meaning to bind, join, attach and yoke, to direct and concentrate one's attention on, to use and apply. It also means union or communion. It is the true union of our will with the will of God. 'It thus means, says Mahadev Desai in his introduction to the *Gita according to Gandhi*, 'the yoking of all the powers of body, mind and soul to God; it means the disciplining of the intellect, the mind, the emotions, the will, which that Yoga presupposes; it means a poise of the soul which enables one to look at life in all its aspects evenly.'

Yoga is one of the six orthodox systems of Indian philosophy. It was collated, co-ordinated and systematized by Patañjali in his classical work, the *Yoga Sutras*, which consists of 185 terse aphorisms. In Indian thought, everything is permeated by the Supreme Universal Spirit (Paramātmā or God) of which the individual human spirit (jīvātmā) is a part. The system of yoga is so called because it teaches the means by which the jīvātmā can be united to, or be in communion with the Paramātmā, and so secure liberation (mokṣa).

One who follows the path of Yoga is a yogi or yogin.

In the sixth chapter of the *Bhagavad Gītā*, which is the most important authority on Yoga philosophy, Śri Krishna explains to Arjuna the meaning of Yoga as a deliverance from contact with pain and sorrow. It is said:

> 'When his mind, intellect and self (ahaṁkāra) are under control, freed from restless desire, so that they rest in the spirit within, a man becomes a Yukta – one in communion with God. A lamp does not flicker in a place where no winds blow; so it is with a yogi, who controls his mind, intellect and self, being absorbed in the spirit within him. When the restlessness of the mind, intellect and self is stilled through the practice of Yoga, the yogi by the grace of the Spirit within himself finds fulfilment. Then he knows the joy eternal which is beyond the pale of the senses which his reason cannot grasp. He abides in this reality and moves not therefrom. He has found the treasure above all others. There is nothing higher than this. He who has achieved it, shall not be moved by the greatest sorrow. This is the real meaning of Yoga – a deliverance from contact with pain and sorrow.

> As a well cut diamond has many facets, each reflecting a different colour of light, so does the word yoga, each facet reflecting a different shade of meaning and revealing different aspects of the entire range of human endeavour to win inner peace and happiness.

The *Bhagavad Gītā* also gives other explanations of the term yoga and lays stress upon Karma Yoga (Yoga by action). It is said: 'Work alone is your privilege, never the fruits thereof. Never let the fruits of action be your motive; and never cease to work. Work in the name of the Lord, abandoning selfish desires. Be not affected by success or failure. This equipoise is called Yoga.'

Yoga has also been described as wisdom in work or skilful living amongst activities with harmony and moderation. 'Yoga is not for him who gorges too much, nor for him who starves himself. It is not for him who sleeps too much, nor for him who stays awake. By moderation in eating and in resting, by regulation in working and by concordance in sleeping and waking, Yoga destroys all pain and sorrow.'

The *Kaṭhopanishad* describes Yoga thus: 'When the senses are stilled, when the mind is at rest, when the intellect wavers not – then, say the wise, is reached the highest stage. This steady control of the senses and mind has been defined as Yoga. He who attains it is free from delusion.'

In the second aphorism of the first chapter of the *Yoga Sutras*, Patañjali describes Yoga as *'chitta vṛtti nirodhah'*. This may be translated as the restraint (nirodhah) of mental (chitta) modifications (vṛtti) or as suppression (nirodhah) of the fluctuations (vṛtti) of consciousness (chitta). The word chitta denotes the mind in its total or collective sense as being composed of three categories:

(a) mind (manas, that is, the individual mind having the power and faculty of attention, selection and rejection; it is the oscillating indecisive faculty of the mind);
(b) intelligence or reason (buddhi, that is, the decisive state which determines the distinction between things);
(c) ago (ahaṁkāra, literally the I-maker, the state which ascertains that 'I know').

The word vṛtti is derived from the Sanskrit root vṛt meaning to turn, to revolve, to roll on. It thus means course of action, behaviour, mode of being, condition or mental state. Yoga is the method by which the restless mind is calmed and the energy directed into constructive channels. As a mighty river which when properly harnessed by dams and canals, creates a vast reservoir of water, prevents famine and provides abundant power for industry; so also the mind, when controlled, provides a reservoir of peace and generates abundant energy for human uplift.

The problem of controlling the mind is not capable of easy solution, as borne out by the following dialogue in the sixth chapter of the *Bhagavad Gītā*. Arjuna asks Śri Krishna:

> 'Krishna, you have told me of Yoga as a communion with Brahman (the Universal Spirit), which is ever one. But how can this be permanent, since the mind is so restless and inconsistent? The mind is impetuous and stubborn, strong and wilful, as difficult to harness as the wind.' Śri Krishna replies: 'Undoubtedly, the mind is restless and hard to control. But it can be trained by constant practice (abhyāsa) and by freedom from desire (vairāgya). A man who cannot control his mind will find it difficult to attain this divine communion; but the self-controlled man can attain it if he tries hard and directs his energy by the right means.'

THE STAGES OF YOGA

The right means are just as important as the end in view. Patañjali enumerates these means as the eight limbs or stages of Yoga for the quest of the soul. They are:

1. Yama (universal moral commandments);
2. Niyama (self purification by discipline);
3. Asana (posture);
4. Prāṇāyāma (rhythmic control of the breath);
5. Pratyāhāra (withdrawal and emancipation of the mind from the domination of the senses and exterior objects);
6. Dhāraṇa (concentration);
7. Dhyāna (meditation);
8. Samādhi (a state of super-consciousness brought about by profound meditation, in which the individual aspirant (sādhaka) becomes one with the object of his meditation – Paramātmā or the Universal Spirit).

Yama and Niyama control the yogi's passions and emotions and keep him in harmony with his fellow man. Ásanas keep the body healthy and strong and in harmony with nature. Finally, the yogi becomes free of body consciousness. He conquers the body and renders it a fit vehicle for the soul. The first three stages are the outward quests (bahiranga sādhanā).

The next two stages, Prāṇāyāma and Pratyāhāra, teach the aspirant to regulate the breathing, and thereby control the mind. This helps to free the senses from the thraldom of the objects of desire. These two stages of Yoga are known as the inner quests (antaranga sādhanā).

Dhāranā, Dhyāna and Samādhi take the yogi into the innermost recesses of his soul. The yogi does not look heavenward to find God. He knows that HE is within, being known as the Antarātmā (the Inner Self). The last three stages keep him in harmony with himself and his Maker. These stages are called antarātmā sādhanā, the quest of the soul.

By profound meditation, the knower, the knowledge and the known become one. The seer, the sight and the seen have no separate existence from each other. It is like a great musician becoming one with his instrument and the music that comes from it. Then, the yogi stands in his own nature and realizes his self (Ātman), the part of the Supreme Soul within himself.

There are different paths (mārgas) by which a man travels to his Maker. The active man finds realization through Karma Mārga, in which a man realizes his own divinity through work and duty. The emotional man finds it through Bhakti Mārga, where there is realization through devotion to and love of a personal God. The intellectual man pursues Jñana, Mārga, where realization comes through knowledge. The meditative or reflective man follows Yoga .Mārga, and realizes his own divinity through control of the mind.

Happy is the man who knows how to distinguish the real from the unreal, the eternal from the transient and the good from the pleasant by his discrimination and wisdom. Twice blessed is he who knows true love and can love all God's creatures. He who works selflessly for the welfare of others with love in his heart is thrice blessed. But the man who combines within his mortal frame knowledge, love and selfless service is holy and becomes a place of pilgrimage, like the confluence of the rivers Gangā, Saraswatī and Jamunā. Those who meet him become calm and purified.

Mind is the king of the senses. One who has conquered his mind, senses, passions, thought and reason is a king among men. He is fit for Rāja Yoga, the royal union with the Universal Spirit. He has Inner Light.

He who has conquered his mind is Rāja Yogi. The word rāja means a king. The expression Rāja Yoga implies a complete mastery of the Self. Though Patañjali explains the ways to control the mind, he nowhere states in his aphorisms that this science is Rāja Yoga, but calls it Aṣṭāṅga Yoga or the eight stages (limbs) of Yoga. As it implies complete mastery of the self one may call it the science of Rāja Yoga.

Swaźtmàrāma, the author of the *Hatha Yoga Pradīpikā* (haṭha = force or determined effort) called the same path Haṭha Yoga because it demanded rigorous discipline.

It is generally believed that Rāja Yoga and Haṭha Yoga are entirely distinct, different and opposed to each other, that the *Yoga Sutras* of Patañjāli deal with Spiritual discipline and that the *Haṭha Yoga Pradīpikā* of Swātmārāma deals solely with physical discipline. It is not so, for

Haṭha Yoga and Rāja Yoga complement each other and form a single approach towards Liberation. As a mountaineer needs ladders, ropes and crampons as well as physical fitness and discipline to climb the icy peaks of the Himālayas, so does the Yoga aspirant need the knowledge and discipline of the Haṭha Yoga of Swātmārāma to reach the heights of Rāja Yoga dealt with by Patañjali.

This path of Yoga is the fountain for the other three paths. It brings calmness and tranquillity and prepares the mind for absolute unqualified self-surrender to God, in which all these four paths merge into one.

Chitta Vṛtti (*Causes for the Modification of the Mind*)

In his *Yoga Sutras* Patañjali lists five classes of chitta vṛtti which create pleasure and pain. These are:

1. Pramāṇa (a standard or ideal), by which things or values are measured by the mind or known, which men accept upon (a) direct evidence such as perception (pratyakṣa), (b) inference (anumāna) and (c) testimony or the word of an acceptable authority when the source of knowledge has been checked as reliable and trustworthy (āgama).

2. Viparyaya (a mistaken view which is observed to be such after study). A faulty medical diagnosis based on wrong hypotheses, or the formerly held theory in astronomy that the Sun rotates round the Earth, are examples of viparyaya.

3. Vikalpa (fancy or imagination, resting merely on verbal expression without any factual basis). A beggar may feel happy when he imagines himself spending millions. A rich miser, on the other hand, may starve himself in the belief that he is poor.

4. Nidrā (sleep), where there is the absence of ideas and experiences. When a man is sleeping soundly, he does not recall his name, family or status, his knowledge or wisdom, or even his own existence. When a man forgets himself in sleep, he wakes up refreshed. But, if a disturbing thought creeps into his mind when he is dropping off, he will not rest properly.

5. Smṛti (memory, the holding fast of the impressions of objects that one has experienced). There are people who live in their past experiences, even though the past is beyond recall. Their sad or happy memories keep them chained to the past and they cannot break their fetters.

Patañjali enumerates five causes of chitta vṛtti creating pain (kleśa). These are:

1. Avidyā (ignorance or nescience);
2. asmitā (the feeling of individuality which limits a person and distinguishes him from a group and which may be physical, mental, intellectual or emotional);
3. rāga (attachment or passion);
4. dveṣa (aversion or revulsion);
5. abhiniveśa (love or thirst for life, the instinctive clinging to worldly life and bodily enjoyment and the fear that one may be cut off from all this by death).

These causes of pain remain submerged in the mind of the sādhaka (the aspirant or seeker). They are like icebergs barely showing their heads in the polar seas. So long as they are not studiously controlled and eradicated, there can be no peace. The yogi learns to forget the past and takes no thought for the morrow. He lives in the eternal present.

As a breeze ruffles the surface of a lake and distorts the images reflected therein, so also the chitta vṛtti disturb the peace of mind. The still waters of a lake reflect the beauty around it. When the mind is still, the beauty of the Self is seen reflected in it. The yogi stills his mind by constant study and by freeing himself from desires. The eight stages of Yoga teach him the way.

Chitta Vikṣepa (*Distractions and Obstacles*)

The distractions and obstacles which hinder the aspirant's practice of Yoga are:

1. Vyādhi – sickness which disturbs the physical equilibrium
2. Styāna – languor or lack of mental disposition for work
3. Saṁśaya – doubt or indecision
4. Pramāda – indifference or insensibility
5. Ālasya – laziness
6. Avirati – sensuality, the rousing of desire when sensory objects possess the mind
7. Bhrānti Darśana – false or invalid knowledge, or illusion
8. Alabdha Bhūmikatva – failure to attain continuity of thought or concentration so that reality cannot be seen
9. Anavasthitattva – instability in holding on to concentration which has been attained after long practice.

There are, however, four more distractions: (a) duḥkha – pain or misery, (b) daurmanasya – despair, (c) aṅgamejayatva – unsteadiness of the body and (d) śvāsa-praśvāsa – unsteady respiration.

To win a battle, a general surveys the terrain and the enemy and plans counter-measures. In a similar way the Yogi plans the conquest of the Self.

1. *Vyādhi.* It will be noticed that the very first obstacle is ill-health or sickness. To the yogi his body is the prime instrument of attainment. If his vehicle breaks down, the traveller cannot go far. If the body is broken by ill-health, the aspirant can achieve little. Physical health is important for mental development, as normally the mind functions through the nervous system. When the body is sick or the nervous system is affected, the mind becomes restless or dull and inert and concentration or meditation become impossible.

2. *Styāna.* A person suffering from languor has no goal, no path to follow and no enthusiasm. His mind and intellect become dull due to inactivity and their faculties rust. Constant flow keeps a mountain stream pure, but water in a ditch stagnates and nothing good can flourish in it. A listless person is like a living corpse for he can concentrate on nothing.

3. *Samśaya.* The unwise, the faithless and the doubter destroy themselves. How can they enjoy this world or the next or have any happiness? The seeker should have faith in himself and his master. He should have faith that God is ever by his side and that no evil can touch him. As faith springs up in the heart it dries out lust, ill-will, mental sloth, spiritual pride and doubt, and the heart free from these hindrances becomes serene and untroubled.

4. *Pramāda.* A person suffering from pramāda is full of self-importance, lacks any humility and believes that he alone is wise. No doubt he knows what is right or wrong, but he persists in his indifference to the right and chooses what is pleasant. To gratify his selfish passions and dreams of personal glory, he will deliberately and without scruple sacrifice everyone who stands in his way. Such a person is blind of God's glory and deaf to His words.

5. *Ālasya.* To remove the obstacle of laziness, unflagging enthusiasm (vīrya) is needed. The attitude of the aspirant is like that of a lover ever yearning to meet the beloved but never giving way to despair. Hope should be his shield and courage his sword. He should be free from hate and sorrow. With faith and enthusiasm he should overcome the inertia of the body and the mind.

6. *Avirati.* This is the tremendous craving for sensory objects after they have been consciously abandoned, which is so hard to restrain. Without being attached to the objects of sense, the yogi learns to enjoy them with the aid of the senses which are completely under his control. By the practice of pratyāhāra he wins freedom from attachment and emancipation from desire and becomes content and tranquil.

7. *Bhrānti Darśana*. A person afflicted by false knowledge suffers from delusion and believes that he alone has seen the true Light. He has a powerful intellect but lacks humility and makes a show of wisdom. By remaining in the company of great souls and through their guidance he sets his foot firmly on the right path and overcomes his weakness.

8. *Alabdha Bhūmikatva*. As a mountain climber fails to reach the summit for lack of stamina, so also a person who cannot overcome the inability to concentrate is unable to seek reality. He might have had glimpses of reality but he cannot see clearly. He is like a musician who has heard divine music in a dream, but who is unable to recall it in his waking moments and cannot repeat the dream.

9. *Anavasthitattva*. A person affected with anavasthitattva has by hard work come within sight of reality. Happy and proud of his achievements he becomes slack in his practice (sādhanā). He has purity and great power of concentration and has come to the final cross-roads of his quest. Even at this last stage continuous endeavour is essential and he has to pursue the path with infinite patience and determined perseverance and must never show slackness which hampers progress on the path of God realization. He must wait until divine grace descends upon him. It has been said in the *Kaṭhopanisad*: 'The Self is not to be realized by study and instruction, nor by subtlety of intellect, nor by much learning, but only by him who longs for Him, by the one whom He chooses. Verily to such a one the Self reveals His true being.

To overcome the obstacles and to win unalloyed happiness, Patañjali offered several remedies. The best of these is the fourfold remedy of Maitri (friendliness), Karuṇa (compassion), Muditā (delight) and Upekṣā (disregard).

1. Maitri is not merely friendliness, but also a feeling of oneness with the object of friendliness (ātmīyatā). A mother feels intense happiness at the success of her children because of ātmīyatā, a feeling of oneness. Patañjali recommends maitri for sukha (happiness or virtue). The yogi cultivates maitri and ātmīyatā for the good and turns enemies into friends, bearing malice towards none.

2. Karuṇa is not merely showing pity or compassion and shedding tears of despair at the misery (duḥkha) of others. It is compassion coupled with devoted action to relieve the misery of the afflicted. The yogi uses all his resources – physical, economic, mental or moral – to alleviate the pain and suffering of others. He shares his strength with the weak until they become strong. He shares his courage with those that are timid until they become brave by his example. He denies the maxim of the 'survival of the fittest', but makes the weak strong enough to survive. He becomes a shelter to one and all.

3. Muditā is a feeling of delight at the good work (punya) done by another, even though he may be a rival. Through muditā, the yogi saves himself from much heart-burning by not showing anger, hatred or jealousy for another who has reached the desired goal which he himself has failed to achieve.

4. Upekṣā: It is not merely a feeling of disdain or contempt for the person who has fallen into vice (apuṇya) or one of indifference or superiority towards him. It is a searching self-examination to find out how one would have behaved when faced with the same temptations. It is also an examination to see how far one is responsible for the state into which the unfortunate one has fallen and the attempt thereafter to put him on the right path. The yogi understands the faults of others by seeing and studying them first in himself. This self-study teaches him to be charitable to all.

The deeper significance of the fourfold remedy of maitri, karuṇa, muditā and upekṣā cannot be felt by an unquiet mind. My experience has led me to conclude that for an ordinary man or woman in any community of the world, the way to achieve a quiet mind is to work with determination on two of the eight stages of Yoga mentioned by Patañjali, namely, āsana and prāṇāyāma.

The mind (manas) and the breath (prāṇa) are intimately connected and the activity or the cessation of activity of one affects the other. Hence Patañjali recommended prāṇāyāma (rhythmic breath control) for achieving mental equipoise and inner peace.

Śiṣya and Guru *(A Pupil and a Master)*

The *Śiva Samhitā* divides sādhakas (pupils or aspirants) into four classes. They are (1) mṛdu (feeble), (2) madhyama (average), (3) adhimātra (superior) and (4) adhimātratama (the supreme one). The last, the highest, is alone able to cross beyond the ocean of the manifest world.

The feeble seekers are those who lack enthusiasm, criticize their teachers, are rapacious, inclined to bad action, eat much, are in the power of women, unstable, cowardly, ill, dependent, speak harshly, have weak characters and lack virility. The Guru (Teacher or Master) guides such seekers in the path of Mantra Yoga only. With much effort, the sādhaka can reach enlightenment in twelve years. (The word mantra is derived from the root 'man', meaning to think. Mantra thus means a sacred thought or prayer to be repeated with full understanding of its meaning. It takes a long time, perhaps years, for a mantra to take firm root in the mind of a feeble sādhaka and still longer for it to bear fruit.)

Of even mind, capable of bearing hardship, wishing to perfect the work, speaking gently, moderate in all circumstances, such is the average seeker. Recognizing these qualities, the Guru teaches him Laya Yoga, which gives liberation. (Laya means devotion, absorption or dissolution.)

Of stable mind, capable of Laya Yoga, virile, independent, noble, merciful, forgiving, truthful, brave, young, respectful, worshipping his teacher, intent on the practice of Yoga, such is a superior seeker. He can reach enlightenment after six years of practice. The Guru instructs this forceful man in Haṭha Yoga.

Of great virility and enthusiasm, good looking, courageous, learned in scriptures, studious, sane in mind, not melancholic, keeping young, regular in food, with his senses under control, free from fear, clean, skilful, generous, helpful to all, firm, intelligent, independent, forgiving, of good character, of gentle speech and worshipping his Guru, such is a supreme seeker, fit for all forms of Yoga. He can reach enlightenment in three years.

Although the *Śiva Samhitā* and the *Haṭha Yoga Pradīpikā* mention the period of time within which success might be achieved, Patañjali nowhere lays down the time required to unite the individual soul with the Divine Universal Soul. According to him abhyāsa (constant and determined practice) and vairāgya (freedom from desires) make the mind calm and tranquil. He defines abhyāsa as effort of long duration, without interruption, performed with devotion, which creates a firm foundation.

The study of Yoga is not like work for a diploma or a university degree by someone desiring favourable results in a stipulated time.

The obstacles, trials and tribulations in the path of Yoga can be removed to a large extent with the help of a Guru. (The syllable gu means darkness and ru means light. He alone is a Guru who removes darkness and brings enlightenment.) The conception of a Guru is deep and significant. He is not an ordinary guide. He is a spiritual teacher who teaches a way of life, and not merely how to earn a livelihood. He transmits knowledge of the Spirit and one who receives such knowledge is a śiṣya, a disciple.

The relationship between a Guru and a śiṣya is a very special one, transcending that between parent and child, husband and wife or friends. A Guru is free from egotism. He devotedly leads his śiṣya towards the ultimate goal without any attraction for fame or gain. He shows the path of God and watches the progress of his disciple, guiding him along that path. He inspires confidence, devotion, discipline, deep understanding and illumination through love. With faith in his pupil, the Guru strains hard to see that he absorbs the teaching. He encourages him to ask questions and to know the truth by question and analysis.

A śiṣya should possess the necessary qualifications of higher realization and development. He must have confidence, devotion and love for his Guru. The perfect examples of the relationship between a Guru and a śiṣya are those of Yama (the God of Death) and Nachiketā in the *Kaṭhopaniṣad* and of Śri Krishna and Arjuna in the *Bhagavad Gīta*. Nachiketā and Arjuna obtained enlightenment through their one-pointed mind, their eagerness and questioning spirit. The śiṣya should hunger for knowledge and have the spirit of humility, perseverance and tenacity of purpose. He should not go to the Guru merely out of curiosity. He should possess śraddhā (dynamic faith) and should not be discouraged if he cannot reach the goal in the time he had expected. It requires tremendous patience to calm the restless mind which is coloured by innumerable past experiences and saṁskāra (the accumulated residue of past thoughts and actions).

Merely listening to the words of the Guru does not enable the śiṣya to absorb the teaching. This is borne out by the story of Indra and Virochana. Indra, the king of Gods, and Virochana, a demon prince, went together to their spiritual preceptor Brahmā to obtain knowledge of the Supreme Self. Both stayed and listened to the same words of their Guru. Indra obtained enlightenment, whereas Virochana did not. Indra's memory was developed by his devotion to the subject taught by the love and faith which he had for his teacher. He had a feeling of oneness with his Guru. These were the reasons for his success. Virochana's memory was developed only through his intellect. He had no devotion either for the subject taught or for his preceptor. He remained what he originally was, an intellectual giant. He returned a doubter. Indra had intellectual humility, while Virochana had intellectual pride and imagined that it was condescending on his part to go to Brahmā. The approach of Indra was devotional while that of Virochana was practical. Virochana was motivated by curiosity and wanted the practical knowledge which he believed would be useful to him later to win power.

The śiṣya should above all treasure love, moderation and humility. Love begets courage, moderation creates abundance and humility generates power. Courage without love is brutish. Abundance without moderation leads to over-indulgence and decay. Power without humility breeds arrogance and tyranny. The true śiṣya learns from his Guru about a power which will never leave him as he returns to the Primeval One, the Source of His Being.

Sādhanā *(A Key to Freedom)*

All the important texts on Yoga lay great emphasis on sādhanā or abhyāsa (constant practice). Sādhanā is not just a theoretical study of Yoga texts. It is a spiritual endeavour. Oil seeds must be pressed to yield oil. Wood must be heated to ignite and bring out the hidden fire within. In the same way, the sādhaka must by constant practice light the divine flame within himself.

> 'The young, the old, the extremely aged, even the sick and the infirm obtain perfection in Yoga by constant practice. Success will follow him who practises, not him who practises not. Success in Yoga is not obtained by the mere theoretical reading of sacred texts. Success is not obtained by wearing the dress of a yogi or a sanyāsi (a recluse), nor by talking about it. Constant practice alone is the secret of success. Verily, there is no doubt of this.'
>
> *Haṭha Yoga Pradīpikā*, chapter 1, verses 64–6.

> 'As by learning the alphabet one can, through practice, master all the sciences, so by thoroughly practising first physical training one acquires the knowledge of Truth (Tattva Jñāna), that is the real nature of the human soul as being identical with the Supreme Spirit pervading the Universe.'
>
> *Gheraṇḍa Saṁhitā*, chapter 1, verse 5.

It is by the co-ordinated and concentrated efforts of his body, senses, mind, reason and Self that a man obtains the prize of inner peace and fulfils the quest of his soul to meet his Maker. The supreme adventure in a man's life is his journey back to his Creator. To reach the goal he needs well developed and co-ordinated functioning of his body, senses, mind, reason and Self. If the effort is not co-ordinated, he fails in his adventure. In the third valli (chapter) of the first part of the *Kaṭhopaniṣad*, Yama (the God of Death) explains this Yoga to the seeker Nachiketā by way of the parable of the individual in a chariot.

> 'Know the Ātman (Self) as the Lord in a chariot, reason as the charioteer and mind as the reins. The senses, they say, are the horses, and their objects of desire are the pastures. The Self, when united with the senses and the mind, the wise call the Enjoyer (Bhoktṛ). The undiscriminating can never rein in his mind; his senses are like the vicious horses of a charioteer. The discriminating ever controls his mind; his senses are like disciplined horses. The undiscriminating becomes unmindful, ever impure; he does not reach the goal, wandering from one body to another. The discriminating becomes mindful, ever pure; he reaches the goal and is never reborn. The man who has a discriminating charioteer to rein in his mind reaches the end of the journey – the Supreme Abode of the everlasting Spirit.
>
> 'The senses are more powerful than the objects of desire. Greater than the senses is the mind, higher than the mind is the reason

> and superior to reason is He – the Spirit in all. Discipline yourself by the Self and destroy your deceptive enemy in the shape of desire.'
>
> *Bhagavad Gītā*, chapter III, verses 42–3.

To realize this not only constant practice is demanded but also renunciation. As regards renunciation, the question arises as to what one should renounce. The yogi does not renounce the world, for that would mean renouncing the Creator. The yogi renounces all that takes him away from the Lord. He renounces his own desires, knowing that all inspiration and right action come from the Lord. He renounces those who oppose the work of the Lord, those who spread demonic ideas and who merely talk of moral values but do not practise them.

The yogi does not renounce action. He cuts the bonds that tie himself to his actions by dedicating their fruits either to the Lord or to humanity. He believes that it is his privilege to do his duty and that he has no right to the fruits of his actions.

While others are asleep when duty calls and wake up only to claim their rights, the yogi is fully awake to his duty, but asleep over his rights. Hence it is said that in the night of all beings the disciplined and tranquil man wakes to the light.

Aṣṭāṅga Yoga – The Eight Limbs of Yoga

The *Yoga Sutra* of Patañjali is divided into four chapters or pāda. The first deals with samādhi, the second with the means (sādhanā) to achieve Yoga, the third enumerates the powers (vibhūti) that the yogi comes across in his quest, and the fourth deals with absolution (kaivalya).

Yama

The eight limbs of Yoga are described in the second chapter. The first of these is yama (ethical disciplines) – the great commandments transcending creed, country, age and time. They are: ahimsā (non-violence), satya (truth), asteya (non-stealing), brahmacharya (continence) and aparigraha (non-coveting). These commandments are the rules of morality for society and the individual, which if not obeyed bring chaos, violence, untruth, stealing, dissipation and covetousness. The roots of these evils are the emotions of greed, desire and attachment, which may be mild, medium or excessive. They only bring pain and ignorance. Patañjali strikes at the root of these evils by changing the direction of one's thinking along the five principles of yama.

1. *Ahimsā*. The word ahimsā is made up of the particle 'a' meaning 'not' and the noun himsā meaning killing or violence. It is more than a negative command not to kill, for it has a wider positive meaning, love. This love embraces all creation for we are all children of the same Father – the Lord. The yogi believes that to kill or to destroy a thing or being is to insult its Creator. Men either kill for food or to protect themselves from danger. But merely because a man is a vegetarian, it does not necessarily follow that he is non-violent by temperament or that he is a yogi, though a vegetarian diet is a necessity for the practice of yoga. Bloodthirsty tyrants may be vegetarians, but violence is a state of mind, not of diet. It resides in a man's mind and not in the instrument he holds in his hand. One can use a knife to pare fruit or to stab an enemy. The fault is not in the instrument, but in the user.

Men take to violence to protect their own interests – their own bodies, their loved ones, their property or dignity. But a man cannot rely upon himself alone to protect himself or others. The belief that he can do so is wrong. A man must rely upon God, who is the source of all strength. Then he will fear no evil.

Violence arises out of fear, weakness, ignorance or restlessness. To curb it what is most needed is freedom from fear. To gain this freedom, what is required is a change of outlook on life and reorientation of the mind. Violence is bound to decline when men learn to base their faith upon reality and investigation rather than upon ignorance and supposition.

The yogi believes that every creature has as much right to live as he has. He believes that he is born to help others and he looks upon creation with eyes of love. He knows that his life is linked inextricably with that of others and he rejoices if he can help them to be happy. He puts the happiness of others before his own and becomes a source of joy to all who meet him. As parents encourage a baby to walk the first steps, he encourages those more unfortunate than himself and makes them fit for survival.

For a wrong done by others, men demand justice; while for that done by themselves they plead mercy and forgiveness. The yogi on the other hand, believes that for a wrong done by himself, there should be justice, while for that done by another there should be forgiveness. He knows and teaches others how to live. Always striving to perfect himself, he shows them by his love and compassion how to improve themselves.

The yogi opposes the evil in the wrong-doer, but not the wrong-doer. He prescribes penance not punishment for a wrong done. Opposition to evil and love for the wrong-doer can live side by side. A drunkard's wife whilst loving him may still oppose his habit. Opposition without love leads to violence; loving the wrong-doer without opposing the evil in him is folly and leads to misery. The yogi knows that to love a person whilst fighting the evil in him is the right course to follow. The battle is won because he fights it with love. A loving mother will sometimes beat her child to cure it of a bad habit; in the same way a true follower of ahimsā loves his opponent.

Along with ahimsā go abhaya (freedom from fear) and akrodha (freedom from anger). Freedom from fear comes only to those who lead a pure life. The yogi fears none and none need fear him, because he is purified by the study of the Self. Fear grips a man and paralyses him. He is afraid of the future, the unknown and the unseen. He is afraid that he may lose his means of livelihood, wealth or reputation. But the greatest fear is that of death. The yogi knows that he is different from his body, which is a temporary house for his spirit. He sees all beings in the Self and the Self in all beings and therefore he loses all fear. Though the body is subject to sickness, age, decay and death, the spirit remains unaffected. To the yogi death is the sauce that adds zest to life. He has dedicated his mind, his reason and his whole life to the Lord. When he has linked his entire being to the Lord, what shall he then fear?

There are two types of anger (krodha), one of which debases the mind while the other leads to spiritual growth. The root of the first is pride, which makes one angry when slighted. This prevents the mind from seeing things in perspective and makes one's judgement defective. The yogi, on the other hand, is angry with himself when his mind stoops low or when all his learning and experience fail to stop him from folly. He is stern with himself when he deals with his own faults, but gentle with the faults of others. Gentleness of mind is an attribute of a yogi, whose heart melts at all suffering. In him gentleness for others and firmness for himself go hand in hand, and in his presence all hostilities are given up.

2. *Satya.* Satya or truth is the highest rule of conduct or morality. Mahātma Gandhi said: 'Truth is God and God is Truth. As fire burns impurities and refines gold, so the fire of truth cleanses the yogi and burns up the dross in him.

If the mind thinks thoughts of truth, if the tongue speaks words of truth and if the whole life is based upon truth, then one becomes fit for union with the Infinite. Reality in its fundamental nature is love and truth and expresses itself through these two aspects. The yogi's life must conform strictly to these two facets of Reality. That is why ahimsā, which is essentially based on love, is enjoined. Satya presupposes perfect truthfulness in thought, word and deed. Untruthfulness in any form puts the sādhaka out of harmony with the fundamental law of truth.

Truth is not limited to speech alone. There are four sins of speech: abuse and obscenity, dealing in falsehoods, calumny or telling tales and lastly ridiculing what others hold to be sacred. The tale bearer is more poisonous than a snake. The control of speech leads to the rooting out of malice. When the mind bears malice towards none, it is filled with charity towards all. He who has learnt to control his tongue has attained self-control in a great measure. When such a person speaks he will be heard with respect and attention. His words will be remembered, for they will be good and true.

When one who is established in truth prays with a pure heart, then things he really needs come to him when they are really needed: he does not have to run after them. The man firmly established in truth gets the fruit of his actions without apparently doing anything. God, the source of all truth, supplies his needs and looks after his welfare.

3. *Asteya*. The desire to possess and enjoy what another has, drives a person to do evil deeds. From this desire spring the urge to steal and the urge to covet. Asteya (a = not, steya = stealing), or non-stealing includes not only taking what belongs to another without permission, but also using something for a different purpose to that intended, or beyond the time permitted by its owner. It thus includes misappropriation, breach of trust, mismanagement and misuse. The yogi reduces his physical needs to the minimum, believing that if he gathers things he does not really need, he is a thief. While other men crave for wealth, power, fame or enjoyment, the yogi has one craving and that is to adore the Lord. Freedom from craving enables one to ward off great temptations. Craving muddies the stream of tranquillity. It makes men base and vile and cripples them. He who obeys the commandment *Thou shalt not steal*, becomes a trusted repository of all treasures.

4. *Brahmacharya*. According to the dictionary brahmacharya means the life of celibacy, religious study and self-restraint. It is thought that the loss of semen leads to death and its retention to life. By the preservation of semen the yogi's body develops a sweet smell. So long as it is retained, there is no fear of death. Hence the injunction that it should be preserved by concentrated effort of the mind. The concept of brahmacharya is not one of negation, forced austerity and prohibition. According to Śankarāchārya, a brahmachārī (one who observes brahmacharya) is a man who is engrossed in the study of the sacred Vedic lore, constantly moves in Brahman and knows that all exists in Brahman. In other words, one who sees divinity in all is a brahmachārī. Patañjali, however, lays stress on continence of the body, speech and mind. This does not mean that the philosophy of Yoga is meant only for celibates. Brahmacharya has little to do with whether one is a bachelor or married and living the life of a householder. One has to develop the higher aspects of Brahmacharya in one's daily living. It is not necessary for

one's salvation to stay unmarried and without a house. On the contrary, all the smṛtis (codes of law) recommend marriage. Without experiencing human love and happiness, it is not possible to know divine love. Almost all the yogis and sages of old in India were married men with families of their own. They did not shirk their social or moral responsibilities. Marriage and parenthood are no bar to the knowledge of divine love, happiness and union with the Supreme Soul.

Dealing with the position of an aspirant who is a householder, the *Śiva Saṁhitā* says: Let him practise free from the company of men in a retired place. For the sake of appearances, he should remain in society, but not have his heart in it. He should not renounce the duties of his profession, caste or rank; but let him perform these as an instrument of the Lord, without any thought of the results. He succeeds by following wisely the method of Yoga; there is no doubt of it. Remaining in the midst of the family, always doing the duties of the householder, he who is free from merits and demerits and has restrained his senses, attains salvation. The householder practising Yoga is not touched by virtue or vice: if to protect mankind he commits any sin, he is not polluted by it. (Chapter V, verses 234–8.)

When one is established in brahmacharya, one develops a fund of vitality and energy, a courageous mind and a powerful intellect so that one can fight any type of injustice. The brahmachārī will use the forces he generates wisely: he will utilize the physical ones for doing the work of the Lord, the mental for the spread of culture and the intellectual for the growth of spiritual life. Brahmacharya is the battery that sparks the torch of wisdom.

5. *Aparigraha.* Parigraha means hoarding or collecting. To be free from hoarding is aparigraha. It is thus but another facet of asteya (non-stealing). Just as one should not take things one does not really need, so one should not hoard or collect things one does not require immediately. Neither should one take anything without working for it or as a favour from another, for this indicates poverty of spirit. The yogi feels that the collection or hoarding of things implies a lack of faith in God and in himself to provide for his future. He keeps faith by keeping before him the image of the moon. During the dark half of the month, the moon rises late when most men are asleep and so do not appreciate its beauty. Its splendour wanes but it does not stray from its path and is indifferent to man's lack of appreciation. It has faith that it will be full again when it faces the Sun and then men will eagerly await its glorious rising.

By the observance of aparigraha, the yogi makes his life as simple as possible and trains his mind not to feel the loss or the lack of anything. Then everything he really needs will come to him by itself at the proper time. The life of an ordinary man is filled with an unending series of disturbances and frustrations and with his reactions to them. Thus there is hardly any possibility of keeping the mind in a state of equilibrium. The sādhaka has developed the capacity to remain satisfied with whatever happens to him. Thus he obtains the peace which takes him beyond the realms of illusion and misery with which our world is saturated. He recalls the promise given by Sri Krishna to Arjuna in the ninth chapter of the *Bhagavad Gītā*: 'To those who worship Me alone with single-minded devotion, who are in harmony with Me every moment, I bring full security. I shall supply all their wants and shall protect them for ever.'

Niyama

Niyama are the rules of conduct that apply to individual discipline, while yama are universal in their application. The five niyama listed by Patañjali are: saucha (purity), santoṣa (contentment), tapas (ardour or austerity), svādhyāya (study of the Self) and Iśvara praṇidhāna (dedication to the Lord).

1. *Śaucha*. Purity of blood is essential for well-being. While good habits like bathing purify the body externally, āsana and prāāyāma cleanse it internally. The practice of āsanas tones the entire body and removes the toxins and impurities caused by over-indulgence. Prāṇāyāma cleanses and aerates the lungs, oxygenates the blood and purifies the nerves. But more important than the physical cleansing of the body is the cleansing of the mind of its disturbing emotions like hatred, passion, anger, lust, greed, delusion and pride. Still more important is the cleansing of the intellect (buddhi) of impure thoughts. The impurities of the mind are washed off in the waters of bhakti (adoration). The impurities of the intellect or reason are burned off in the fire of svādhyāya (study of the Self). This internal cleansing gives radiance and joy. It brings benevolence (saumanasya) and banishes mental pain, dejection, sorrow and despair (daurmanasya). When one is benevolent, one sees the virtues in others and not merely their faults. The respect which one shows for another's virtues, makes him self-respecting as well and helps him to fight his own sorrows and difficulties. When the mind is lucid, it is easy to make it one-pointed (ekāgra). With concentration, one obtains mastery over the senses (indriyajaya). Then one is ready to enter the temple of his own body and see his real self in the mirror of his mind.

Besides purity of body, thought and word, pure food is also necessary. Apart from cleanliness in the preparation of food it is also necessary to observe purity in the means by which one procures it.

Food, the supporting yet consuming substance of all life, is regarded as a phase of Brahman. It should be eaten with the feeling that with each morsel one can gain strength to serve the Lord. Then food becomes pure. Whether or not to be a vegetarian is a purely personal matter as each person is influenced by the tradition and habits of the country in which he was born and bred. But, in course of time, the practitioner of yoga has to adopt a vegetarian diet, in order to attain one-pointed attention and spiritual evolution.

Food should be taken to promote health, strength, energy and life. It should be simple, nourishing, juicy and soothing. Avoid foods which are sour, bitter, pungent, burning, stale, tasteless, heavy and unclean.

Character is moulded by the type of food we take and by how we eat it. Men are the only creatures that eat when not hungry and generally live to eat rather than eat to live. If we eat for flavours of the tongue, we over-eat and so suffer from digestive disorders which throw our systems out of gear. The yogi believes in harmony, so he eats for the sake of sustenance only. He does not eat too much or too little. He looks upon his body as the rest-house of his spirit and guards himself against over-indulgence.

Besides food, the place is also important for spiritual practices. It is difficult to practise in a distant country (away from home), in a forest, in a crowded city, or where it is noisy. One should choose a place where food is easily procurable, a place which is free from insects, protected from the elements and with pleasing surroundings. The banks of a lake or river or the sea-shore are ideal. Such quiet ideal places are hard to find in modern times; but one can at least make a corner in one's room available for practice and keep it clean, airy, dry and pest-free.

2. *Santoṣa.* Santoṣa or contentment has to be cultivated. A mind that is not content cannot concentrate. The yogi feels the lack of nothing and so he is naturally content. Contentment gives bliss unsurpassed to the yogi. A contented man is complete for he has known the love of the Lord and has done his duty. He is blessed for he has known truth and joy.

Contentment and tranquillity are states of mind. Differences arise among men because of race, creed, wealth and learning. Differences create discord and there arise conscious or unconscious conflicts which distract and perplex one. Then the mind cannot become one-pointed (ekāgra) and is robbed of its peace. There is contentment and tranquillity when the flame of the spirit does not waver in the wind of desire. The sādhaka does not seek the empty peace of the dead, but the peace of one whose reason is firmly established in God.

3. *Tapas.* Tapas is derived from the root 'tap' meaning to blaze, burn, shine, suffer pain or consume by heat. It therefore means a burning effort under all circumstances to achieve a definite goal in life. It involves

purification, self-discipline and austerity. The whole science of character building may be regarded as a practice of tapas.

Tapas is the conscious effort to achieve ultimate union with the Divine and to burn up all desires which stand in the way of this goal. A worthy aim makes life illumined, pure and divine. Without such an aim, action and prayer have no value. Life without tapas, is like a heart without love. Without tapas, the mind cannot reach up to the Lord.

Tapas is of three types. It may relate to the body (kāyika), to speech (vāchika) or to mind (mānasika). Continence (brahmacharya) and non-violence (ahimsā) are tapas of the body. Using words which do not offend, reciting the glory of God, speaking the truth without regard for the consequences to oneself and not speaking ill of others are tapas of speech. Developing a mental attitude whereby one remains tranquil and balanced in joy and sorrow and retains self-control are tapas of the mind.

It is tapas when one works without any selfish motive or hope of reward and with an unshakable faith that not even a blade of grass can move without His will.

By tapas the yogi develops strength in body, mind and character. He gains courage and wisdom, integrity, straightforwardness and simplicity.

4. *Svādhyāya.* Sva means self and adhyāya means study or education. Education is the drawing out of the best that is within a person. Svādhyāya, therefore, is the education of the self.

Svādhyāya is different from mere instruction like attending a lecture where the lecturer parades his own learning before the ignorance of his audience. When people meet for svādhyāya, the speaker and listener are of one mind and have mutual love and respect. There is no sermonizing and one heart speaks to another. The ennobling thoughts that arise from svādhyāya are, so to speak, taken into one's bloodstream so that they become a part of one's life and being.

The person practising svādhyāya reads his own book of life, at the same time that he writes and revises it. There is a change in his outlook on life. He starts to realize that all creation is meant for bhakti (adoration) rather than for bhoga (enjoyment), that all creation is divine, that there is divinity within himself and that the energy which moves him is the same that moves the entire universe.

According to Śri Vinobā Bhāve (the leader of the Bhoodan movement), svādhyāya is the study of one subject which is the basis or root of all other subjects or actions, upon which the others rest, but which itself does not rest upon anything.

To make life healthy, happy and peaceful, it is essential to study regularly divine literature in a pure place. This study of the sacred books of the world will enable the sādhaka to concentrate upon and solve the difficult problems of life when they arise. It will put an end to ignorance and bring knowledge. Ignorance has no beginning, but it has an end. There is a beginning but no end to knowledge. By svādhyāya the sādhaka understands the nature of his soul and gains communion with the divine. The sacred books of the world are for all to read. They are not meant for the members of one particular faith alone. As bees savour the nectar in various flowers, so the sādhaka absorbs things in other faiths which will enable him to appreciate his own faith better.

Philology is not a language but the science of languages, the study of which will enable the student to learn his own language better. Similarly, Yoga is not a religion by itself. It is the science of religions, the study of which will enable a sādhaka the better to appreciate his own faith.

5. *Īśvara praṇidhāna.* Dedication to the Lord of one's actions and will is Īśvara praṇidhāna. He who has faith in God does not despair. He has illumination (tejas). He who knows that all creation belongs to the Lord will not be puffed up with pride or drunk with power. He will not stoop for selfish purposes; his head will bow only in worship. When the waters of bhakti (adoration) are made to flow through the turbines of the mind, the result is mental power and spiritual illumination. While mere physical strength without bhakti is lethal, mere adoration without strength of character is like an opiate. Addiction to pleasures destroys both power and glory. From the gratification of the senses as they run after pleasures arise moha (attachment) and lobha (greed) for their repetition. If the senses are not gratified, then, there is śoka (sorrow). They have to be curbed with knowledge and forbearance; but to control the mind is more difficult. After one has exhausted one's own resources and still not succeeded, one turns to the Lord for help for He is the source of all power. It is at this stage that bhakti begins. In bhakti, the mind, the intellect and the will are surrendered to the Lord and the sādhaka prays: 'I do not know what is good for me. Thy will be done.' Others pray to have their own desires gratified or accomplished. In bhakti or true love there is no place for 'I' and 'mine'. When the feeling of 'I' and 'mine' disappears, the individual soul has reached full growth.

When the mind has been emptied of desires of personal gratification, it should be filled with thoughts of the Lord. In a mind filled with thoughts of personal gratification, there is danger of the senses dragging the mind after the objects of desire. Attempts to practise bhakti without emptying the mind of desires is like building a fire with wet fuel. It makes a lot of smoke and brings tears to the eyes of the person who builds it and of those around him. A mind with desires does not ignite and glow, nor does it generate light and warmth when touched with the fire of knowledge.

The name of the Lord is like the Sun, dispelling all darkness. The moon is full when it faces the sun. The individual soul experiences fullness (pūrṇatā) when it faces the Lord. If the shadow of the earth comes between the full moon and the sun there is an eclipse. If the feeling of 'I' and 'mine' casts its shadow upon the experience of fullness, all efforts of the sādhaka to gain peace are futile.

Actions mirror a man's personality better than his words. The yogi has learnt the art of dedicating all his actions to the Lord and so they reflect the divinity within him.

Āsana

The third limb of yoga is āsana or posture. Āsana brings steadiness, health and lightness of limb. A steady and pleasant posture produces mental equilibrium and prevents fickleness of mind. Āsanas are not merely gymnastic exercises; they are postures. To perform them one needs a clean airy place, a blanket and determination, while for other systems of physical training one needs large playing fields and costly equipment. Āsanas can be done alone, as the limbs of the body provide the necessary weights and counter-weights. By practising them one develops agility, balance, endurance and great vitality.

Āsanas have been evolved over the centuries so as to exercise every muscle, nerve and gland in the body. They secure a fine physique, which is strong and elastic without being muscle-bound and they keep the body free from disease. They reduce fatigue and soothe the nerves. But their real importance lies in the way they train and discipline the mind.

Many actors, acrobats, athletes, dancers, musicians and sportsmen also possess superb physiques and have great control over the body, but they lack control over the mind, the intellect and the Self. Hence they are in disharmony with themselves and one rarely comes across a balanced personality among them. They often put the body above all else. Though the yogi does not underrate his body, he does not think merely of its perfection but of his senses, mind, intellect and soul.

The yogi conquers the body by the practice of āsanas and makes it a fit vehicle for the spirit. He knows that it is a necessary vehicle for the spirit. A soul without a body is like a bird deprived of its power to fly.

The yogi does not fear death, for time must take its toll of all flesh. He knows that the body is constantly changing and is affected by childhood, youth and old age. Birth and death are natural phenomena but the soul is not subject to birth and death. As a man casting off worn-out garments takes on new ones, so the dweller within the body casting aside worn-out bodies enters into others that are new.

The yogi believes that his body has been given to him by the Lord not for enjoyment alone, but also for the service of his fellow men during every wakeful moment of his life. He does not consider it his property. He knows that the Lord who has given him his body will one day take it away.

By performing āsanas, the sādhaka first gains health, which is not mere existence. It is not a commodity which can be purchased with money. It is an asset to be gained by sheer hard work. It is a state of complete equilibrium of body, mind and spirit. Forgetfulness of physical and mental consciousness is health. The yogi frees himself from physical disabilities and mental distractions by practising āsanas. He surrenders his actions and their fruits to the Lord in the service of the world.

The yogi realizes that his life and all its activities are part of the divine action in nature, manifesting and operating in the form of man. In the beating of his pulse and the rhythm of his respiration, he recognizes the flow of the seasons and the throbbing of universal life. His body is a temple which houses the Divine Spark. He feels that to neglect or to deny the needs of the body and to think of it as something not divine, is to neglect and deny the universal life of which it is a part. The needs of the body are the needs of the divine spirit which lives through the body. The yogi does not look heaven-ward to find God for he knows that He is within, being known as the Antarātmā (the Inner Self). He feels the kingdom of God within and without and finds that heaven lies in himself.

Where does the body end and the mind begin? Where does the mind end and the spirit begin? They cannot be divided as they are inter-related and but different aspects of the same all-pervading divine consciousness.

The yogi never neglects or mortifies the body or the mind, but cherishes both. To him the body is not an impediment to his spiritual liberation nor is it the cause of its fall, but is an instrument of attainment. He seeks a body strong as a thunderbolt, healthy and free from suffering so as to dedicate it in the service of the Lord for which it is intended. As pointed out in the *Muṇḍakopaniṣad* the Self cannot be attained by one without strength, nor through heedlessness, nor without an aim. Just as an unbaked earthen pot dissolves in water the body soon decays. So bake it hard in the fire of yogic discipline in order to strength and purify it.

The names of the āsanas are significant and illustrate the principle of evolution. Some are named after vegetation like the tree (vṛkṣa) and the lotus (padma); some after insects like the locust (śalabha) and the scorpion (vṛśchika); some after aquatic animals and amphibians like the fish (matsya), the tortoise (kūrma), the frog (bheka or maṇḍūka) or the crocodile (nakra). There are āsanas called after birds like the cock (kukkuṭa), the heron (baka), the peacock (mayūra) and the swan (haṁsa). They are also named after quadrupeds like the dog (śvāna), the horse (vātāyana), the camel (uṣṭra) and the lion (siṁha). Creatures that crawl like the serpent (bhujaṅga) are not forgotten, nor is the human embryonic state (garbha-pinda) overlooked. Āsanas are named after legendary heroes like Vīrabhadra and Hanumān, son of the Wind. Sages like Bharadvāja, Kapila, Vasiṣṭha and Viśvāmitra are remembered by having āsanas named after them. Some āsanas are also called after gods of the Hindu pantheon and some recall the Avatārās, or incarnations of Divine Power. Whilst performing āsanas the yogi's body assumes many forms resembling a variety of creatures. His mind is trained not to despise any creature, for he knows that throughout the whole gamut of creation, from the lowliest insect to the most perfect sage, there breathes the same Universal Spirit, which assumes innumerable forms. He knows that the highest form is that of the Formless. He finds unity in universality. True āsana is that in which the thought of Brahman flows effortlessly and incessantly through the mind of the sādhaka.

Dualities like gain and loss, victory and defeat, fame and shame, body and mind, mind and soul vanish through mastery of the āsanas, and the sādhaka then passes on to prāṇāyāma, the fourth stage in the path of yoga. In prāṇayāma practices the nostrils, nasal passages and membranes, the windpipe, the lungs and the diaphragm are the only parts of the body which are actively involved. These alone feel the full impact of the force of prāṇa, the breath of life. Therefore, do not seek to master prāṇāyāma in a hurry, as you are playing with life itself. By its improper practice respiratory diseases will arise and the nervous system will be shattered. By its proper practice one is freed from most diseases. Never attempt to practice prāṇāyāma alone by yourself. For it is essential to have the personal supervision of a Guru who knows the physical limitations of his pupil.

Prāṇāyāma

Just as the word yoga is one of wide import, so also is prāṇa. Prāṇa means breath, respiration, life, vitality, wind, energy or strength. It also connotes the soul as opposed to the body. The word is generally used in the plural to indicate vital breaths. Āyāma means length, expansion, stretching or restraint. Prāṇāyāma thus connotes extension of breath and its control. This control is over all the functions of breathing, namely, (1) inhalation or inspiration, which is termed pūraka (filling up); (2) exhalation or expiration, which is called rechaka (emptying the lungs), and (3) retention or holding the breath, a state where there is no inhalation or exhalation, which is termed kumbhaka. In Haṭha Yoga texts kumbhaka is also used in a loose generic sense to include all the three respiratory processes of inhalation, exhalation and retention.

A kumbha is a pitcher, water pot, jar or chalice. A water pot may be emptied of all air and filled completely with water, or it may be emptied of all water and filled completely with air. Similarly, there are two states of kumbhaka namely (1) when breathing is suspended after full inhalation (the lungs being completely filled with life-giving air), and (2) when breathing is suspended after full exhalation (the lungs being emptied of all noxious air). The first of these states, where breath is held after a full inhalation, but before exhalation begins, is known as antara kumbhaka. The second, where breath is held after a full exhalation, but before inhalation begins is known as bāhya kumbhaka. Antara means inner or interior, while bāhya means outer or exterior. Thus, kumbhaka is the interval or intermediate time between full inhalation and exhalation (antara kumbhaka) or between full exhalation and inhalation (bāhya kumbhaka). In both these types breathing is suspended and restrained.

Prāṇāyāma is thus the science of breath. It is the hub round which the wheel of life revolves. 'As lions, elephants and tigers are tamed very slowly and cautiously, so should prāṇa be brought under control very slowly in gradation measured according to one's capacity and physical limitations. Otherwise it will kill the practitioner,' warns the *Haṭha Yoga Pradīpikā* (chapter II, verse 16).

The yogi's life is not measured by the number of his days but by the number of his breaths. Therefore, he follows the proper rhythmic patterns of slow deep breathing. These rhythmic patterns strengthen the respiratory system, soothe the nervous system and reduce craving. As desires and cravings diminish, the mind is set free and becomes a fit vehicle for concentration. By improper practice of prāṇāyāma the pupil introduces several disorders into his system like hiccough, wind, asthma, cough, catarrh, pains in the head, eyes and ears and nervous irritation. It takes a long time to learn slow, deep, steady and proper inhalations and exhalations. Master this before attempting kumbhaka.

As a fire blazes brightly when the covering of ash over it is scattered by the wind, the divine fire within the body shines in all its majesty when the ashes of desire are scattered by the practice of prāṇāyāma.

'The emptying the mind of the whole of its illusion is the true rechaka (exhalation). The realization that "I am Ātmā (spirit)" is the true pūraka (inhalation). And the steady sustenance of the mind on this conviction is the true kumbhaka (retention). This is true prāṇāyāma,' says Śankarāchārya.

Every living creature unconsciously breathes the prayer 'So'ham' (Saḥ = He: Aham = Aham = I–He, the Immortal Spirit, am I) with each inward breath. So also with each outgoing breath each creature prays 'Haṁsaḥ' (I am He). This ajapa-mantra (unconscious repetitive prayer) goes on for ever within each living creature throughout life. The yogi fully realizes the significance of this ajapa-mantra and so is released from all the fetters that bind his soul. He offers up the very breath of his being to the Lord as sacrifice and receives the breath of life from the Lord as his blessing.

Prāṇa in the body of the individual (jīvātmā) is part of the cosmic breath of the Universal Spirit (Paramātmā). An attempt is made to harmonize the individual breath (piṇḍaprāṇa) with the cosmic breath (Brahmāṇḍa-prāṇa) through the practice of prāṇāyāma.

It has been said by Kariba Ekken, a seventeenth-century mystic: 'If you would foster a calm spirit, first regulate your breathing; for when that is under control, the heart will be at peace; but when breathing is spasmodic, then it will be troubled. Therefore, before attempting anything, first regulate your breathing on which your temper will be softened, your spirit calmed.'

The chitta (mind, reason and ego) is like a chariot yoked to a team of powerful horses. One of them is prāṇa (breath), the other is vāsanā (desire). The chariot moves in the direction of the more powerful animal. If breath prevails, the desires are controlled, the senses are held in check and the mind is stilled. If desire prevails, breath is in disarray and the mind is agitated and troubled. Therefore, the yogi masters the science of breath and by the regulation and control of breath, he controls the mind and stills its constant movement. In the practice of prāṇāyāma the eyes are kept shut to prevent the mind from wandering. 'When the prāṇa and the manas (mind) have been absorbed, an undefinable joy ensues.' (*Haṭha Yoga Pradīpikā*, chapter IV, verse 30.)

Emotional excitement affects the rate of breathing; equally, deliberate regulation of breathing checks emotional excitement. As the very object of Yoga is to control and still the mind, the yogi first learns prāṇāyāma to master the breath. This will enable him to control the senses and so reach the stage of pratyāhāra. Only then will the mind be ready for concentration (dhyāna).

The mind is said to be twofold – pure and impure. It is pure when it is completely free from desires and impure when it is in union with desires. By making the mind motionless and freeing it from sloth and distractions, one reaches the state of mindlessness (amanaska), which is the supreme state of samādhi. This state of mindlessness is not lunacy or idiocy but the conscious state of the mind when it is free from thoughts and desires. There is a vital difference between an idiot or a lunatic on the one hand, and a yogi striving to achieve a state of mindlessness on the other. The former is careless; the latter attempts to be carefree. It is the oneness of the breath and mind and so also of the senses and the abandonment of all conditions of existence and thought that is designated Yoga.

Prāṇa Vāyu. One of the most subtle forms of energy is air. This vital energy which also pervades the human body is classified in five main categories in the Haṭha Yoga texts according to the various functions performed by the energy. These are termed vāyu (wind) and the five main divisions are: prāṇa (here the generic term is used to designate the particular), which moves in the region of the heart and controls respiration; apāna, which moves in the sphere of the lower abdomen and controls the function of eliminating urine and faeces; samāna, which stokes the gastric fires to aid digestion; udāna, which dwells in the thoracic cavity and controls the intake of air and food; and vyāna, which pervades the entire body and distributes the energy derived from food and breath. There are also five subsidiary vāyūs. These are: nāga, which relieves abdominal pressure by belching; kūrma, which controls the movements of the eyelids to prevent foreign matter or too bright a light entering the eyes; kṛkara, which prevents substances passing up the nasal passages and down the throat by making one sneeze or cough; devadatta, which provides for the intake of extra oxygen in a tired body by causing a yawn, and lastly dhanaṁjaya, which remains in the body even after death and sometimes bloats up a corpse.

Pratyāhāra

If a man's reason succumbs to the pull of his senses he is lost. On the other hand, if there is rhythmic control of breath, the senses instead of running after external objects of desire turn inwards, and man is set free from their tyranny. This is the fifth stage of Yoga, namely, pratyāhāra, where the senses are brought under control.

When this stage is reached, the sādhaka goes through a searching self-examination. To overcome the deadly but attractive spell of sensual objects, he needs the insulation of adoration (bhakti) by recalling to his mind the Creator who made the objects of his desire. He also needs the lamp of knowledge of his divine heritage. The mind, in truth, is for mankind the cause of bondage and liberation; it brings bondage if it is bound to the objects of desire and liberation when it is free from objects. There is bondage when the mind craves, grieves or is unhappy over something. The mind becomes pure when all desires and fears are annihilated. Both the good and the pleasant present themselves to men and prompt them to action. The yogi prefers the good to the pleasant. Others driven by their desires, prefer the pleasant to the good and miss the very purpose of life. The yogi feels joy in what he is. He knows how to stop and, therefore, lives in peace. At first he prefers that which is bitter as poison, but he perseveres in his practice knowing well that in the end it will become as sweet as nectar. Others hankering for the union of their senses with the objects of their desires, prefer that which at first seems sweet as nectar, but do not know that in the end it will be as bitter as poison.

The yogi knows that the path towards satisfaction of the senses by sensual desires is broad, but that it leads to destruction and that there are many who follow it. The path of Yoga is like the sharp edge of a razor, narrow and difficult to tread, and there are few who find it. The yogi knows that the paths of ruin or of salvation lie within himself.

According to Hindu philosophy, consciousness manifests in three different qualities. For man, his life and his consciousness, together with the entire cosmos are the emanations of one and the same prakṛti (cosmic matter or substance) – emanations that differ in designation through the predominance of one of the guṇās. The guṇās (qualities or attributes) are:

1. Sattva (the illuminating, pure or good quality), which leads to clarity and mental serenity.
2. Rajas (the quality of mobility or activity), which makes a person active and energetic, tense and wilful, and
3. Tamas (the dark and restraining quality), which obstructs and counteracts the tendency of rajas to work and of sattva to reveal.

Tamas is a quality of delusion, obscurity, inertia and ignorance. A person in whom it predominates is inert and plunged in a state of torpor. The quality of sattva leads towards the divine and tamas towards the demonic, while in between these two stands rajas.

The faith held, the food consumed, the sacrifices performed, the austerities undergone and the gifts given by each individual vary in accordance with his predominating guṇa.

He that is born with tendencies towards the divine is fearless and pure. He is generous and self-controlled. He pursues the study of the Self. He is non-violent, truthful and free from anger. He renounces the fruits of his labour, working only for the sake of work. He has a tranquil mind, with malice towards none and charity towards all, for he is free from craving. He is gentle, modest and steady. He is illumined, clement and resolute, being free from perfidy and pride.

A man in whom rajō-guṇa predominates has inner thirst. As he is passionate and covetous, he hurts others. Being full of lust and hatred, envy and deceit, his desires are insatiable. He is unsteady, fickle and easily distracted as well as ambitious and acquisitive. He seeks the patronage of friends and has family pride. He shrinks from unpleasant things and clings to pleasant ones. His speech is sour and his stomach greedy.

He that is born with demonic tendencies is deceitful, insolent and conceited. He is full of wrath, cruelty and ignorance. In such people there is neither purity, nor right conduct, nor truth. They gratify their passions. Bewildered by numerous desires, caught in the web of delusion, these addicts of sensual pleasures fall into hell.

The working of the mind of persons with different predominating gunās may be illustrated by their different ways of approach towards a universal commandment like 'Thou shalt not covet.' A man in whom tamō-guṇa predominates might interpret it thus: 'others should not covet what is mine, no matter how I obtained it. If they do, I shall destroy them.' The rajō-guṇa type is a calculating self-interested person who would construe the commandment as meaning: 'I will not covet others' goods lest they covet mine.' He will follow the letter of the law as a matter of policy, but not the true spirit of the law as a matter of principle. A person of sattvika temperament will follow both the letter and the spirit of the precept as a matter of principle and not of policy, as a matter of eternal value. He will be righteous for the sake of righteousness alone, and not because there is a human law imposing punishment to keep him honest.

The yogi who is also human is affected by these three guṇās. By his constant and disciplined study (abhyāsa) of himself and of the objects which his senses tend to pursue, he learns which thoughts, words and actions are prompted by tamas and which by rajas. With unceasing effort he weeds out and eradicates such thoughts and he works to achieve a sattvika frame of mind. When the sattva-guṇa alone remains, the human soul has advanced a long way towards the ultimate goal.

Like unto the pull of gravity is the pull of the guṇās. As intensive research and rigorous discipline are needed to experience the wonder of weightlessness in space, so also a searching self-examination and the discipline furnished by Yoga is needed by a sādhaka to experience union with the Creator of space when he is freed from the pull of the guṇās.

Once the sādhaka has experienced the fullness of creation or of the Creator, his thirst (tṛṣṇā) for objects of sense vanishes and he looks at them ever after with dispassion (vairāgya). He experiences no disquiet in heat or cold, in pain or pleasure, in honour or dishonour and in virtue or vice. He treats the two imposters – triumph and disaster – with equanimity. He has emancipated himself from these pairs of opposites. He has passed beyond the pull of the guṇās and has become a guṇātīta (one who has transcended the guṇās). He is then free from birth and death, from pain and sorrow and becomes immortal. He has no self-identity as he lives experiencing the fullness of the Universal Soul. Such a man, scorning nothing, leads all things to the path of perfection.

Dhāranā

When the body has been tempered by āsanas, when the mind has been refined by the fire of prāṇāyāma and when the senses have been brought under control by pratyāhāra, the sādhaka reaches the sixth stage called dhāraṇā. Here he is concentrated wholly on a single point or on a task in which he is completely engrossed. The mind has to be stilled in order to achieve this state of complete absorption.

The mind is an instrument which classifies, judges and co-ordinates the impressions from the outside world and those that arise within oneself.

Mind is the product of thoughts which are difficult to restrain for they are subtle and fickle. A thought which is well guarded by a controlled mind brings happiness. To get the best out of an instrument, one must know how it works. The mind is the instrument for thinking and it is therefore necessary to consider how it functions. Mental states are classified in five groups. The first of these is the kṣipta state, where the mental forces are scattered, being in disarray and in a state of neglect. Here the mind hankers after objects, the ragō-guṇa being dominant. The second is the vikṣipta state, where the mind is agitated and distracted. Here there is a capacity to enjoy the fruits of one's efforts, but the desires are not marshalled and controlled. Then in the mūḍha state the mind is foolish, dull and stupid. It is confounded and at a loss to know what it wants and here the tamō-guṇa predominates. The fourth state of the mind is the ekāgra (eka = one; agra = foremost) state, where the mind is closely attentive and the mental faculties are concentrated on a single object or focussed on one point only, with the sattva-guṇa prevailing. The ekāgra person has superior intellectual powers and knows exactly what he wants, so he uses all his powers to achieve his purpose. At times the ruthless pursuit of the desired object, irrespective of the cost to others, can create great misery, and it often happens that even if the desired object is achieved it leaves behind a bitter taste.

Arjuna, the mighty bowman of the epic Mahābhārata, provides us with an example of what is meant by dhāraṇā. Once Drona, the preceptor of the royal princes, organized an archery contest to test their proficiency. They were called upon one by one to describe the target, which was pointed out to them. It was a nesting bird. Some princes described the grove of trees, others the particular tree or the bough on which the nest stood. When Arjuna's turn came, he described first the bird. Then he saw only its head, and lastly he could see nothing but the shining eye of the bird, which was the centre of the target chosen by Droṇa.

There is danger, however, of an ekāgra person becoming supremely egotistical. Where the senses start roaming unchecked, the mind follows suit. They cloud a man's judgement and set him adrift like a battered ship on a storm-tossed sea. A ship needs ballast to keep her on an even keel and the helmsman needs a star to steer her by. The ekāgra person needs bhakti (adoration of the Lord) and concentration on divinity to keep his mental equilibrium so that he goes on always in the right direction. He will not know happiness until the sense of 'I' and 'mine' disappears.

The last mental state is that of niruddha, where the mind (manas), intellect (buddhi) and ego (ahaṁkāra) are all restrained and all these faculties are offered to the Lord for His use and in His service. Here there is no feeling of 'I' and 'mine'. As a lens becomes more luminous when great light is thrown upon it and seems to be all light and undistinguishable from it, so also the sādhaka who has given up his mind, intellect and ego to the Lord, becomes one with Him, for the sādhaka thinks of nothing but Him, who is the creator of thought.

Without ekāgratā or concentration one can master nothing. Without concentration on Divinity, which shapes and controls the universe, one cannot unlock the divinity within oneself or become a universal man. To achieve this concentration, what is recommended is eka-tattva-abhyāsa or study of the single element that pervades all, the inmost Self of all beings, who converts His one form into many. The sādhaka, therefore, concentrates upon AUM, which is His symbol, to achieve ekāgratā.

Aum: According to Śri Vinobā Bhāve, the Latin word Omne and the Sanskrit word Aum are both derived from the same root meaning all and both words convey the concepts of omniscience, omnipresence and omnipotence. Another word for Aum is praṇava, which is derived from the root nu meaning to praise, to which is added the prefix pra denoting superiority. The word, therefore, means the best praise or the best prayer.

The symbol AUM is composed of three syllables, namely the letters A, U, M, and when written has a crescent and dot on its top. A few instances of the various interpretations given to it may be mentioned here to convey its meaning.

The letter A symbolizes the conscious or waking state (jāgrata-avasthā), the letter U the dream state (svapna-avasthā) and the letter M the dreamless sleep state (suṣupta-avasthā) of the mind and spirit. The entire symbol, together with the crescent and the dot, stands for the fourth state (turīya-avasthā), which combines all these states and transcends them. This is the state of samādhi.

The letters A, U and M symbolize respectively speech (vak), the mind (manas) and the breath of life (prāṇa), while the entire symbol stands for the living spirit, which is but a portion of the divine spirit.

The three letters also represent the dimensions of length, breadth and depth, while the entire symbol represents Divinity, which is beyond the limitations of shape and form.

The three letters A, U and M symbolize the absence of desire, fear and anger, while the whole symbol stands for the perfect man (a sthitaprajñā), one whose wisdom is firmly established in the divine.

They represent the three genders, masculine, feminine and neuter, while the entire symbol represents all creation together with the Creator.

They stand for the three guṇās or qualities of sattva, rajas and tamas, while the whole symbol represents a guṇātīta, one who has transcended and gone beyond the pull of the guṇās.

The letters correspond to the three tenses – past, present and future – while the entire symbol stands for the Creator, who transcends the limitations of time.

They also stand for the teaching imparted by the mother, the father and the Guru respectively. The entire symbol represents Brahma Vidyā, the knowledge of the Self, the teaching which is imperishable.

The A, U and M depict the three stages of yogic discipline, namely, āsana, prāṇāyāma and pratyāhāra. The entire symbol represents samādhi, the goal for which the three stages are the steps.

They represent the triad of Divinity, namely, Brahmā – the creator, Viṣṇu – the Maintainer, and Śiva – the Destroyer of the universe. The whole symbol is said to represent Brahman from which the universate emanates, has its growth and fruition and into which it merges in the end. It does not grow or change. Many change and pass, but Brahman is the One that ever remains unchanged.

The letters A, U and M also stand for the mantra 'Tat Twam Asi' ('That Thou Art'), the realization of man's divinity within himself. The entire symbol stands for this realization, which liberates the human spirit from the confines of his body, mind, intellect and ego.

After realizing the importance of AUM, the yogi focusses his attention on his beloved Deity adding AUM to the name of the Lord. The word AUM being too vast and too abstract, he unifies his senses, will, intellect, mind and reason by focussing on the name of the Lord and adding the word AUM with one pointed devotion and so experiences the feeling and meaning of the mantra.

The yogi recalls the verses of the *Muṇḍakopaniṣad*: 'Taking as a bow the great weapon of the Upaniṣad, one should put upon it an arrow sharpened by meditation. Stretching it with a thought directed to the essence of That, penetrate the Imperishable as the mark, my friend. The mystic syllable AUM is the bow. The arrow is the Self (Ātmā). Brahman is the target. By the undistracted man is It penetrated. One should come to be in It, as the arrow in the mark.'

Dhyāna

As water takes the shape of its container, the mind when it contemplates an object is transformed into the shape of that object. The mind which thinks of the all-pervading divinity which it worships, is ultimately through long-continued devotion transformed into the likeness of that divinity.

When oil is poured from one vessel to another, one can observe the steady constant flow. When the flow of concentration is uninterrupted, the state that arises is dhyāna (meditation). As the filament in an electric bulb glows and illumines when there is a regular uninterrupted current of electricity, the yogi's mind will be illumined by dhyāna. His body, breath, senses, mind, reason and ego are all integrated in the object of his contemplation – the Universal Spirit. He remains in a state of consciousness which has no qualification whatsoever. There is no other feeling except a state of SUPREME BLISS. Like a streak of lightning the yogi sees LIGHT that shines beyond the earth and the heavens. He sees the light that shines in his own heart. He becomes a light unto himself and others.

The signs of progress on the path of Yoga are health, a sense of physical lightness, steadiness, clearness of countenance and a beautiful voice, sweetness of odour of the body and freedom from craving. He has a balanced, serene and a tranquil mind. He is the very symbol of humility. He dedicates all his actions to the Lord and taking refuge in Him, frees himself from the bondage of karma (action) and becomes a Jīvana Mukta (a Liberated Soul).

'What becomes of him who strives and fails to reach the end of Yoga, who has faith, but whose mind wanders away from Yoga?' To this query of Arjuna, the Lord Śri Krishna replied:

> 'No evil can befall a righteous man. He dwells long years in the heaven of those who did good, and then he is reborn in the house of the pure and the great. He may even be born in a family of illumined yogis; but to be born in such a family is most difficult in this world. He will regain the wisdom attained in his former life and strives ever for perfection. Because of his former study, practice and struggle which drive him ever onwards, the yogi ever strives with a soul cleansed of sin, attains perfection through many lives and reaches the supreme goal. The yogi goes beyond those who only follow the path of austerity, knowledge or service. Therefore, Arjuna, be thou a yogi. The greatest of all yogis is he who adores Me with faith and whose heart abides in Me.'
>
> *Bhagavad Gītā*, chapter VI, verses 38 to 47.

Samādhi

Samādhi is the end of the sādhaka's quest. At the peak of his meditation, he passes into the state of samādhi, where his body and senses are at rest as if he is asleep, his faculties of mind and reason are alert as if he is awake, yet he has gone beyond consciousness. The person in a state of samādhi is fully conscious and alert.

All creation is Brahman. The sādhaka is tranquil and worships it as that from which he came forth, as that in which he breathes, as that into which he will be dissolved. The soul within the heart is smaller than the smallest seed, yet greater than the sky, containing all works, all desires. Into this the sādhaka enters. Then there remains no sense of 'I' or 'mine' as the working of the body, the mind and the intellect have stopped as if one is in deep sleep. The sādhaka has attained true Yoga; there is only the experience of consciousness, truth and unutterable joy. There is a peace that passeth all understanding. The mind cannot find words to describe the state and the tongue fails to utter them. Comparing the experience of samādhi with other experiences, the sages say: 'Neti! Neti!' – 'It is not this! It is not this!' The state can only be expressed by profound silence. The yogi has departed from the material world and is merged in the Eternal. There is then no duality between the knower and the known for they are merged like camphor and the flame.

There wells up from within the heart of the yogi the Song of the Soul, sung by Śankarāchārya in his *Ātma Ṣaṭkam*.

PART II

Yogāsanas

HINTS AND CAUTIONS

THE REQUISITES

1. Without firm foundations a house cannot stand. Without the practice of the principles of yama and niyama, which lay down firm foundations for building character, there cannot be an integrated personality. Practice of āsanas without the backing of yama and niyama is mere acrobatics.

2. The qualities demanded from an aspirant are discipline, faith, tenacity, and perseverance to practice regularly without interruptions.

CLEANLINESS AND FOOD

3. Before starting to practise āsanas, the bladder should be emptied and the bowels evacuated. Topsy-turvy poses help bowel movements. If the student is constipated or it is not possible to evacuate the bowels before the practice of āsanas, start with Śīrṣāsana and Sarvāṅgāsana and their variations. Attempt other āsanas only after evacuation. Never practice advanced āsanas without having first evacuated the bowels.

BATH

4. Āsanas come easier after taking a bath. After doing them, the body feels sticky due to perspiration and it is desirable to bathe some fifteen minutes later. Taking a bath or a shower both before and after practising āsanas refreshes the body and mind.

FOOD

5. Āsanas should preferably be done on an empty stomach. If this is difficult, a cup of tea or coffee, cocoa or milk may be taken before doing them. They may be practised without discomfort one hour after a very light meal. Allow at least four hours to elapse after a heavy meal before starting the practice. Food may be taken half an hour after completing the āsanas.

TIME

6. The best time to practise is either early in the morning or late in the evening. In the morning āsanas do not come easily as the body is stiff.

The mind, however, is still fresh but its alertness and determination diminish as time goes by. The stiffness of the body is conquered by regular practice and one is able to do the āsanas as well. In the evening, the body moves more freely than in the mornings, and the āsanas come better and with greater ease. Practice in the morning makes one work better in one's vocation. In the evening it removes the fatigue of the day's strain and makes one fresh and calm. Do all the āsanas in the morning and stimulative āsanas (like Śīrṣāsana, Sarvāṅgāsana and their variations and Paśchimottānāsana) should be practised in the evening.

SUN

7. Do not practise āsanas after being out in the hot sun for several hours.

PLACE

8. They should be done in a clean airy place, free from insects and noise.

9. Do not do them on the bare floor or on an uneven place, but on a folded blanket laid on a level floor.

CAUTION

10. No undue strain should be felt in the facial muscles, ears and eyes or in breathing during the practice.

CLOSING OF THE EYES

11. In the beginning, keep the eyes open. Then you will know what you are doing and where you go wrong. If you shut your eyes you will not be able to watch the requisite movements of the body or even the direction in which you are doing the pose. You can keep your eyes closed only when you are perfect in a particular āsana for only then will you be able to adjust the bodily movements and feel the correct stretches.

MIRROR

12. If you are doing the āsanas in front of a mirror, keep it perpendicular to the floor and let it come down to ground level, for otherwise the poses will look slanting due to the angle of the mirror. You will not be able to observe the movements of placing the head and shoulders in the topsy-turvy poses unless the mirror reaches down to the floor. Use a mirror without a frame.

THE BRAIN

13. During the practice of āsanas, it is the body alone which should be active while the brain should remain passive, watchful and alert. If they are done with the brain, then you will not be able to see your own mistakes.

BREATHING

14. In all the āsanas, breathing should be done through the nostrils only and not through the mouth.

15. Do not restrain the breath while in the process of the āsana or while staying in it. Follow the instructions regarding breathing given in the technique sections of the various āsanas as described hereafter.

ŚAVĀSANA

16. After completing the practice of āsanas always lie down in Śavāsana for at least 10 to 15 minutes, as this will remove fatigue.

ASANAS AND PRĀṆĀYĀMA

17. Read carefully the hints and cautions for the practice of prāṇāyāma before attempting it (see Part III). Prāṇāyāma may be done either very early in the morning before the āsanas or in the evening after completing them. If early in the morning, prāṇāyāma may be done first for 15 to 30 minutes: then a few minutes of Śavāsana, and after allowing some time to elapse during which one may be engaged in normal activities, practise āsanas. If, however, these are done in the evening, allow at least half an hour to elapse before sitting for prāṇāyāma.

SPECIAL PROVISIONS FOR PERSONS SUFFERING FROM DIZZINESS OR BLOOD PRESSURE

18. Do not start with Śīrṣāsana and Sarvāṅgāsana if you suffer from dizziness or high blood pressure. First practise Paśchimottānāsana Uttānāsana, and Adho Mukha Śvānāsana before attempting topsy-turvy poses like Śīrṣāsana and Sarvāṅgāsana and after doing these poses repeat Paśchimottānāsana, Adho Mukha Śvānāsana and Uttānāsana in that order.

19. All forward bending poses are beneficial for persons suffering from either high or low blood pressure.

SPECIAL WARNING FOR PERSONS AFFECTED FROM PUS IN THE EARS OR DISPLACED RETINA

20. Those suffering from pus in the ears or displacement of the retina should not attempt topsy-turvy poses.

SPECIAL PROVISIONS FOR WOMEN

21. *Menstruation:* Avoid āsanas during the menstrual period. But if the flow is in excess of normal, Upaviṣṭha Koṇāsana, Baddha Koṇāsana, Vīrāsana, Jānu Śīrṣāsana, Paśchimottānāsana and Uttānāsana will be beneficial. On no account stand on your head nor perform sarvāngāsana, during the menstrual period.

22. *Pregnancy:* All the āsanas can be practised during the first three months of pregnancy. All the standing poses and the forward bending āsanas may be done with mild movements, for at this time the spine should be made strong and elastic and no pressure be felt on the abdomen. Baddha Koṇāsana and Upaviṣṭha Koṇāsana may be practised throughout pregnancy at any time of the day (even after meals, but not forward bending immediately after meals) as these two āsanas will strengthen the pelvic muscles and the small of the back and also reduce labour pains considerably. Prāṇāyāma without retention (kumbhaka) may be practised throughout pregnancy, as regular deep breathing will help considerably during labour.

23. *After delivery:* No āsanas should be done during the first month after delivery. Thereafter they may be practised mildly. Gradually increase the course as mentioned in the Appendix. Three months after delivery all āsanas may be practised with comfort.

EFFECTS OF ĀSANAS

24. Faulty practice causes discomfort and uneasiness within a few days. This is sufficient to show that one is going wrong. If you cannot find the fault yourself, it is better to approach a person who has practised well and get his guidance.

25. The right method of doing āsanas brings lightness and an exhilarating feeling in the body as well as in the mind and a feeling of oneness of body, mind and soul.

26. Continuous practice will change the outlook of the practiser. He will discipline himself in food, sex, cleanliness and character and will become a new man.

27. When one has mastered an āsana, it comes with effortless ease and causes no discomfort. The bodily movements become graceful. While performing āsanas, the student's body assumes numerous forms of life found in creation – from the lowliest insect to the most perfect sage – and he learns that in all these there breathes the same Universal Spirit – the Spirit of God. He looks within himself while practising and feels the presence of God in different āsanas which he does with a sense of surrender unto the feet of the LORD.

TECHNIQUE AND EFFECTS OF ĀSANAS

(After the name of each āsana, there is a number with an asterisk. These numbers before an asterisk indicate the intensity of the āsana; the lower the number, the easier the āsana, the higher the number, the more difficult the āsana.)

1| *Tāḍāsana*

(also called Samasthiti)

ONE*

Tāda means a mountain. Sama means upright, straight, unmoved. Sthiti is standing still, steadiness. Tāḍāsana therefore implies a pose where one stands firm and erect as a mountain. This is the basic standing pose.

TECHNIQUE

1. Stand erect with the feet together, the heels and big toes touching each other. Rest the heads of metatarsals on the floor and stretch all the toes flat on the floor.

2. Tighten the knees and pull the knee-caps up, contract the hips and pull up the muscles at the back of the thighs.

3. Keep the stomach in, chest forward, spine stretched up and the neck straight.

4. Do not bear the weight of the body either on the heels or the toes, but distribute it evenly on them both.

5. Ideally in Tāḍāsana the arms are stretched out over the head, but for the sake of convenience, one can place them by the side of the thighs. In this case, keep the arms parallel with the body. The fingers together and pointing downwards. Each of the standing poses described below can then be followed easily, starting with the pupil standing in Tāḍāsana with palms by the side of the thighs.

EFFECTS

People do not pay attention to the correct method of standing. Some stand with the body weight thrown only on one leg, or with one leg turned completely sideways. Others bear all the weight on the heels, or on the inner or outer edges of the feet. This can be noticed by watching where the soles and heels of the shoes wear out. Owing to our faulty method of standing and not distributing the body weight evenly on the feet, we acquire specific deformities which hamper spinal elasticity. Even if the feet are kept apart, it is better to keep the heel and toe in a line parallel to the median plane and not at an angle. By this method, the hips are contracted, the abdomen is pulled in and the chest is brought forward. One feels light in body and the mind acquires agility. If we stand with the body weight thrown only on the heels, we feel the centre of gravity changing; the hips become loose, the abdomen protrudes, the body hangs back and the spine feels the strain and consequently we soon feel fatigued and the mind becomes dull. It is therefore essential to master the art of standing correctly.



1

2| *Utthita Trikoṇāsana*

THREE*

Utthita means extended, stretched. Trikoṇa (tri = three; koṇa = angle) is a triangle. This standing āsana is the extended triangle pose.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1)

2. Inhale deeply and with a jump spread apart the legs sideways 3 to 3½ feet. Raise the arms sideways, in line with the shoulders, palms facing down. Keep the arms parallel to the floor. (Plate 2)

3. Turn the right foot sideways 90 degrees to the right. Turn the left foot slightly to the right, keeping the left leg stretched from the inside and tightened at the knee.

4. Exhale, bend the trunk sideways to the right, bringing the right palm near the right angle. If possible, the right palm should rest completely on the floor. (Plates 3 and 4)

5. Stretch the left arm up (as in the illustration), bringing it in line with the right shoulder and extend the trunk. The back of the legs, the back of the chest and the hips should be in line. Gaze at the thumb of the outstretched left hand. Keep the right knee locked tight by pulling up the knee-cap and keep the right knee facing the toes.

6. Remain in this position from half a minute to a minute, breathing deeply and evenly. Then lift the right palm from the floor. Inhale and return to position 2 above.

7. Now, turn the left foot sideways 90 degrees to the left, turn the right foot slightly to the left, keep both knees tight and continue from position 2 to 6, reversing all processes. Inhale and come to position 2. Hold the posture for the same length of time on the left side.

8. Exhale, and jump, coming back to Tāḍāsana. (Plate 1)

EFFECTS

This āsana tones up the leg muscles, removes stiffness in the legs and hips, corrects any minor deformity in the legs and allows them to develop evenly. It relieves backaches and neck sprains, strengthens the ankles and develops the chest.



2



3



4

3| Utthita Pārśvakoṇāsana

FOUR*

Pārśva means side or flank. Koṇa is an angle. This is the extended lateral angle pose.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1) Take a deep inhalation and with a jump spread the legs apart sideways 4 to 4½ feet. Raise the arms sideways, in line with the shoulders, palms facing down. (Plate 2)

2. While exhaling slowly, turn the right foot sideways 90 degrees to the right, and the left foot slightly to the right, keeping the left leg stretched out and tightened at the knee. Bend the right leg at the knee until the thigh and the calf form a right angle and the right thigh is parallel to the floor.

3. Place the right palm on the floor by the side of the right foot, the right armpit covering and touching the outer side of the right knee. Stretch the left arm out over the left ear. Keep the head up. (Plates 5 and 6)

4. Tighten the loins and stretch the hamstrings. The chest, the hips and the legs should be in a line and in order to achieve this, move the chest up and back. Stretch every part of the body, concentrating on the back portion of the whole body, specially the spine. Stretch the spine until all the vertebrae and ribs move and there is a feeling that even the skin is being stretched and pulled.



5



6

5. Remain in this pose from half a minute to a minute, breathing deeply and evenly. Inhale and lift the right palm from the floor.

6. Inhale, straighten the right leg and raise the arms as in position 1.

7. Continue with exhalation as in positions 2 to 5, reversing all processes, on the left side.

8. Exhale and jump back to Tāḍāsana. (Plate 1)

EFFECTS

This āsana tones up the ankles, knees and thighs. It corrects defects in the calves and thighs, develops the chest and reduces fat round the waist and hips and relieves sciatic and arthritic pains. It also increases peristaltic activity and aids elimination.

4| *Vīrabhadrāsana I*

THREE*

Dakṣa once celebrated a great sacrifice, but he did not invite his daughter Satī nor her husband Śiva, the chief of the gods. Satī, however, went to the sacrifice, but being greatly humiliated and insulted threw herself into the fire and perished. When Śiva heard this he was gravely provoked, tore a hair from his matted locks and threw it to the ground. A powerful hero named Vīrabhadra rose up and awaited his orders. He was told to lead Śiva's army against Dakṣa and destroy his sacrifice. Vīrabhadra and his army appeared in the midst of Dakṣa's assembly like a hurricane and destroyed the sacrifice, routed the other gods and priests and beheaded Dakṣa. Śiva in grief for Satī withdrew to Kailās and plunged into meditation. Satī was born again as Umā in the house of Himālaya. She strove once more for the love of Śiva and ultimately won his heart. The story is told by Kālidāsa in his great poem Kumāra saṁbhava *(The Birth of the War-Lord). This āsana is dedicated to the powerful hero created by Śiva from his matted hair.*


7


8


9

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1)

2. Raise both arms above the head; stretch up and join the palms. (Plate 7)

3. Take a deep inhalation and with a jump spread the legs apart sideways 4 to 4½ feet.

4. Exhale, turn to the right. Simultaneously turn the right foot 90 degrees to the right and the left foot slightly to the right. (Plate 8) Flex the right knee till the right thigh is parallel to the floor and the right shin perpendicular to the floor, forming a right angle between the right thigh and the right calf. The bent knee should not extend beyond the ankle, but should be in line with the heel.

5. Stretch out the left leg and tighten at the knee.

6. The face, chest and right knee should face the same way as the right foot, as illustrated. Throw the head up, stretch the spine from the coccyx and gaze at the joined palms. (Plate 9)

7. Hold the pose from 20 seconds to half a minute with normal breathing.

8. Repeat on the left side as in positions 4 to 6, reversing all processes.

9. Exhale and jump back to Tāḍāsana. (Plate 1)

All standing poses are strenuous, this pose in particular. It should not be tried by persons with a weak heart. Even people who are fairly strong should not stay long in this āsana.

EFFECTS

In this pose the chest is fully expanded and this helps deep breathing. It relieves stiffness in shoulders and back, tones up the ankles and knees and cures stiffness of the neck. It also reduces fat round the hips.

5| *Vīrabhadrāsana II*

ONE*

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1)

2. Take a deep inhalation, and with a jump spread the legs apart sideways 4 to 4½ feet. Raise the arms sideways in line with the shoulders, palms facing down. (Plate 2)

3. Turn the right foot sideways 90 degrees to the right and the left foot slightly to the right, keeping the left leg stretched out and tightened at the knee. Stretch the hamstring muscles of the left leg.

4. Exhale and bend the right knee till the right thigh is parallel to the floor, keeping the right shin perpendicular to the floor, thus forming a right angle between the right thigh and the right calf. The bent knee should not extend beyond the ankle, but should be in line with the heel. (Plate 10)



10

5. Stretch out the hands sideways, as though two persons are pulling you from opposite ends.

6. Turn the face to the right and gaze at the right palm. Stretch the back muscles of the left leg fully. The back of the legs, the dorsal region and the hips should be in one line.

7. Stay in the pose from 20 seconds to half a minute with deep breathing. Inhale and return to position 2.

8. Turn the left foot sideways 90 degrees to the left and the right foot slightly to the left, flex the left knee and continue from positions 3 to 6 on the left side, reversing all processes.

9. Inhale, again come back to position 2. Exhale and jump back to Tāḍāsana. (Plate 1)

EFFECTS

Through this pose the leg muscles become shapely and stronger. It relieves cramp in the calf and thigh muscles, brings elasticity to the leg and back muscles and also tones the abdominal organs.

Mastery of the standing poses prepares the pupil for the advanced poses in forward bending, which can then be acquired with ease.



11



12

6| *Pārśvōttānāsana*

SIX*

Pārśva means side or flank. Uttāna (ut = intense, and tān = to extend, stretch, lengthen) means an intense stretch. The name implies a pose in which the side of the chest is stretched intensely.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1) Inhale deeply and stretch the body forward.

2. Join the palms behind the back and draw the shoulders and elbows back.

3. Exhale, turn the wrists and bring both palms up above the middle of the back of the chest, the fingers at the level of the shoulder-blades. You are doing 'namaste' (the Indian gesture of respect by folding the hands) with your hands behind your back. (Plate 11)

4. Inhale and with a jump spread the legs apart sideways 3 to 3½ feet. Stay in this position and exhale.

5. Inhale and turn the trunk to the right. Turn the right foot 90 degrees sideways to the right keeping the toes and heel in a line with the trunk; turn the left foot with the leg 75 to 80 degrees to the right and keep the left foot stretched out and the leg tightened at the knee. Throw the head back. (Plate 12)

6. Exhale, bend the trunk forward and rest the head on the right knee. Stretch the back and gradually extend the neck until the nose, then the lips and lastly the chin touch and then rest beyond the right knee. (Plate 13) Tighten both the legs by pulling the knee-caps up.

7. Stay in the pose from 20 seconds to half a minute with normal breathing. Then slowly move the head and trunk towards the left knee by swinging the trunk round the hips. At the same time turn the left foot 90 degrees towards the left and the right foot 75 to 80 degrees to the left. Now raise the trunk and head as far back as you can, without bending the right leg. This movement should be done with one inhalation.

8. Exhale, bend the trunk forward, rest the head on the left knee and gradually extend the chin beyond the left knee by stretching the neck as in position 6.

9. After holding the pose from 20 seconds to half a minute with normal breathing, inhale, move the head to the centre and the feet to their original position so that the toes point forward. Then raise the trunk up.

10. Exhale and jump back to Tāḍāsana (Plate 1), releasing the hands from the back.

11. If you cannot fold the hands together behind the back, just grip the right wrist and follow the above technique. (Plate 14)



13

EFFECTS

This āsana relieves stiffness in the legs and hip muscles and makes the hip joints and spine elastic. While the head is resting on the knees, the abdominal organs are contracted and toned. The wrists move freely and any stiffness there disappears. The posture also corrects round and drooping shoulders. In the correct pose, the shoulders are drawn well back and this makes deep breathing easier.



14

7| *Prasārita Pādottānāsana*

FOUR*

Prasārita means expanded, spread, extended. Pāda means a foot. The pose is one where the expanded legs are stretched intensely.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1)

2. Inhale, place the hands on the waist and spread the legs apart 4½ to 5 feet. (Plate 15)

3. Tighten the legs by drawing up the knee-caps. Exhale, and place the palms on the floor in line with the shoulders between the feet. (Plate 16)

4. Inhale and raise the head up, keeping the back concave.



15



16

5. Exhale, bend the elbows and rest the crown of the head on the floor, keeping the weight of the body on the legs. (Plates 17 and 18) Do not throw the body weight on the head. Both feet, both palms and the head should be in a straight line.

6. Stay in the pose for half a minute, breathing deeply and evenly.

7. Inhale, raise the head from the floor and straighten the arms at the elbows. Keep the head well up by making the back concave as in position 4. (Plate 16)

8. Exhale and stand as in position 2. (Plate 15)

9. Jump back to Tāḍāsana. (Plate 1)

EFFECTS

In this pose the hamstring and abductor muscles are fully developed, while blood is made to flow to the trunk and the head. People who cannot do Sīrṣāsana (Plate 90) can benefit from this pose, which increases digestive powers.

All the standing poses described above are necessary for beginnings. As the pupil advances he attains better flexibility and then the standing poses can be dispensed with, though it is advisable to do them once a week. All these standing poses help to reduce the body weight.



17



18

8| *Uṣṭrāsana*

THREE*

Uṣṭra means a camel.

TECHNIQUE

1. Kneel on the floor, keeping the thighs and feet together, toes pointing back and resting on the floor.

2. Rest the palms on the hips. Stretch the thighs, curve the spine back and extend the ribs. (Plate 19)

3. Exhale, place the right palm over the right heel and the left palm over the left heel. If possible, place the palms on the soles of the feet.

4. Press the feet with the palms, throw the head back and push the spine towards the thighs, which should be kept perpendicular to the floor.

5. Contract the buttocks and stretch the dorsal and the coccyx regions of the spine still further, keeping the neck stretched back. (Plate 20)

6. Remain in this position for about half a minute with normal breathing.

7. Release the hands one by one and rest them on the hips. (Plate 19) Then sit on the floor and relax.

EFFECTS

People with drooping shoulders and hunched backs will benefit by this āsana.

The whole spine is stretched back and is toned. This pose can be tried conveniently by the elderly and even by persons with spinal injury.



19



20



21

9| *Pādānguṣṭhāsana*

THREE*

Pāda means the foot. Anguṣṭha is the big toe. This posture is done by standing and catching the big toes.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1) Spread the legs a foot apart.

2. Exhale, bend forward and hold the big toes between the thumbs and the first two fingers, so that the palms face each other. Hold them tight. (Plate 21)

3. Keep the head up, stretch the diaphragm towards the chest and make the back as concave as possible. Instead of stretching down from the shoulders, bend forward from the pelvic region to get the concave shape of the back from the coccyx.

4. Keep the legs stiff and do not slacken the grip at the knees and toes. Stretch the shoulder-blades also. Take one or two breaths in this position.



22

5. Now exhale, and bring the head in between the knees by tightening and pulling the toes without lifting them off the floor. (Plate 22) Remain in this pose for about 20 seconds, maintaining normal breathing.

6. Inhale, come to position 2 (Plate 21), release the toes and stand up. Return to Tāḍāsana. (Plate 1)

10| *Pādahastāsana*

SIX*

Pāda means the foot. Hasta means the hand. This posture is done by bending forward and standing on one's hands.

TECHNIQUE

1. Stand in Tāḍāsana. (Plate 1) Spread the legs a foot apart.

2. Exhale, bend forward and without bending the legs at the knees insert the hands under the feet so that the palms touch the soles. (Plate 23)

3. Keep the head up and make the back as concave as possible. Do not slacken the grip at the knees and take a few breaths in this position.

4. Now exhale, and move the head in between the knees by bending the elbows and pulling the feet up from the palms. (Plate 24) Stay in the pose for about 20 seconds with normal breathing.

5. Inhale, raise the head and come back to position 2 (Plate 23), with the head well up. Take two breaths.

6. Inhale, stand up and return to Tāḍāsana. (Plate 1)



23



24

EFFECTS OF PĀDĀNGUṢṬHĀSANA AND PĀDAHASTĀSANA

The second āsana is more strenuous than the first, but the effects of both are the same. The abdominal organs are toned and digestive juices increase, while the liver and spleen are activated. Persons suffering from a bloating sensation in the abdomen or from gastric troubles will benefit from practising these two āsanas.

Slipped spinal discs can only be adjusted in the concave back position as in Plates 21 and 23. Do not bring the head in between the knees if you have a displaced disc. I have experimented with persons suffering from slipped discs and the concave back position proved a boon to them. It is imperative to get guidance from a guru (master) before trying this pose, because it may not be possible to achieve the concave back position immediately. One has to master other minor poses before attempting this one.

11| *Uttānāsana*

EIGHT*

Ut is a particle indicating deliberation, intensity. The verb tān means to stretch, extend, lengthen out. In this āsana, the spine is given a deliberate and an intense stretch.

TECHNIQUE

1. Stand in Tāḍāsana (Plate 1), keeping the knees tight.

2. Exhale, bend forward and place the fingers on the floor. Then place the palms on the floor by the side of the feet, behind the heels. Do not bend the legs at the knees.

3. Try to hold the head up and stretch the spine. Move the hips a little forward towards the head so as to bring the legs perpendicular to the floor.

4. Remain in this position and take two deep breaths.

5. Exhale, move the trunk closer to the legs and rest the head on the knees. (Plate 25)

6. Do not slacken the grip at the knees, but pull the knee-caps well up. Hold this position for a minute with deep and even breathing.

7. Inhale and raise the head from the knees, but without lifting the palms from the floor as in position 3.

8. After two breaths, take a deep inhalation, lift the hands from the floor and come back to Tāḍāsana. (Plate 1)



25

EFFECTS

This āsana cures stomach pains and tones the liver, the spleen and the kidneys. It also relieves stomach pain during menstrual periods. The heart beats are slowed down and the spinal nerves rejuvenated. Any depression felt in the mind is removed if one holds the pose for two minutes or more. The posture is a boon to people who get excited quickly, as it soothes the brain cells. After finishing the āsana, one feels calm and cool, the eyes start to glow and the mind feels at peace.

Persons who feel heaviness in the head, flushing or any discomfort while attempting Śīrṣāsana (Plate 90), should do Uttānāsana first; then they will be able to do Śīrṣāsana (the head stand) with comfort and ease.

12| Śalabhāsana

ONE*

Śalabhā means a locust. The pose resembles that of a locust resting on the ground, hence the name.

TECHNIQUE

1. Lie full length on the floor on the stomach, face downwards. Stretch the arms back.

2. Exhale, lift the head, chest and legs off the floor simultaneously as high as possible. The hands should not be placed and the ribs should not rest on the floor. Only the abdominal front portion of the body rests on the floor and bears the weight of the body. (Plate 26)

3. Contract the buttocks and stretch the thigh muscles. Keep both legs fully extended and straight, touching at the thighs, knees and ankles.

4. Do not bear the weight of the body on the hands but stretch them back to exercise the upper portion of the back muscles.

5. Stay in the position as long as you can with normal breathing.

6. In the beginning it is difficult to lift the chest and the legs off the floor, but this becomes easier as the abdominal muscles grow stronger.



26



27

EFFECTS

The pose aids digestion and relieves gastric troubles and flatulence. Since the spine is stretched back it becomes elastic and the pose relieves pain in the sacral and lumbar regions. In my experience, persons suffering from slipped discs have benefited by regular practice of this āsana without recourse to enforced rest or surgical treatment. The bladder and the prostate gland also benefit from the exercise and remain healthy.

A variation of the pose may also be tried to relieve aches in the lower part of the back. Here, the legs are bent at the knees and the thighs are kept apart while the shins are kept perpendicular to the floor. Then with an exhalation, the thighs are lifted off the floor and brought closer together until the knees touch, the shins still being kept perpendicular. (Plate 27)

13| Dhanurāsana

FOUR*

Dhanu means a bow. The hands here are used like a bowstring to pull the head, trunk and legs up and the posture resembles a bent bow.

TECHNIQUE

1. Lie full length on the floor on the stomach, face downwards.

2. Exhale and bend the knees. Stretch the arms back and hold the left ankle with the left hand and the right ankle with the right hand. Take two breaths.

3. Now exhale completely and pull the legs up by raising the knees above the floor, and simultaneously lift the chest off the floor. The arms and hands act like a bow-string to tauten the body like a bent bow. (Plate 28)



28

4. Lift up the head and pull it as far back as possible. Do not rest either the ribs or the pelvic bones on the floor. Only the abdomen bears the weight of the body on the floor.

5. While raising the legs do not join them at the knees, for then the legs will not be lifted high enough. After the full stretch upwards has been achieved, join together the thighs, the knees and the ankles.

6. Since the abdomen is extended, the breathing will be fast, but do not worry about it. Stay in the pose to your capacity from 20 seconds to one minute.

7. Then, with an exhalation, release the ankles, stretch the legs straight, bring the head and the legs back to the floor and relax.

EFFECTS

In this posture the spine is stretched back. Elderly people do not normally do this, so their spines get rigid. This āsana brings back elasticity to the spine and tones the abdominal organs. In my experience, persons suffering from slipped discs have obtained relief by the regular practice of Dhanurāsana and Śalabhāsana (Plate 26) without being forced to rest or to undergo surgical treatment.

14| Chaturaṅga Daṇḍāsana

ONE*

Chatur means four. Aṅga means a limb or a part thereof. Daṇḍa means a staff. Lie flat on the floor, face down and take the weight of the body on the palms and toes, exhale and keep the body parallel to the floor, stiff as a staff. The four limbs supporting the body are the hands and feet. The pose is similar to dips in western gymnastics.

TECHNIQUE

1. Lie flat on the floor, face downwards.

2. Bend the elbows and place the palms by the side of the chest. Keep the feet about a foot apart.



29



30

3. With an exhalation, raise the whole body a few inches above the floor, balancing it on the hands and the toes. (Plate 29) Keep the body stiff as a staff, parallel to the floor from head to heel and the knees taut. Stay for some time with normal breathing.

4. Then gradually extend the whole body forward so that the feet rest on the upper portion of the toes on the floor. (Plate 30)

5. Stay in the pose for about 30 seconds with normal or deep breathing. The movement may be repeated several times. Then relax on the floor.

EFFECTS

The pose strengthens the arms and the wrists develop mobility and power. It also contracts and tones the abdominal organs.

15| *Bhujaṅgāsana I*

ONE*

Bhujanga means a serpent. In this posture, lie flat on the floor, face downwards, lift the body up from the trunk and throw the head back like a serpent about to strike.

TECHNIQUE

1. Lie on the floor face downwards. Extend the legs, keeping the feet together. Keep the knees tight and the toes pointing.

2. Rest the palms by the side of the pelvic region.

3. Inhale, press the palms firmly on the floor and lift the body up from the trunk until the pubis is in contact with the floor and stay in this position with the weight on the legs and palms. (Plate 31)

4. Contract the anus and the buttocks, tighten the thighs.

5. Maintain the pose for about 20 seconds, breathing normally.

6. Exhale, bend the elbows and rest the trunk on the floor. Repeat the pose two or three times and then relax.

EFFECTS

The posture is a panacea for an injured spine and in cases of slight displacement of spinal discs the practice of this pose replaces the discs in their original position. The spinal region is toned and the chest fully expanded.



31

16| Ūrdhva Mukha Śvānāsana

ONE*

Ūrdhva Mukha means having the mouth upwards. Śvāna means a dog. The pose resembles a dog stretching itself with the head up in the air, hence the name.

TECHNIQUE

1. Lie on the floor on the stomach, face downwards.

2. Keep the feet about one foot apart. The toes should point straight back. Place the palms on the floor by the side of the waist, the fingers pointing to the head.

3. Inhale, raise the head and trunk, stretch the arms completely and push the head and trunk as far back as possible, without resting the knees on the floor.



32

4. Keep the legs straight and tightened at the knees, but do not rest the knees on the floor. The weight of the body rests on the palms and toes only. (Plate 32)

5. The spine, thighs and calves should be fully stretched, and the buttocks contracted tight. Push the chest forward, stretch the neck fully and throw the head as far back as possible. Stretch also the back portions of the arms.

6. Stay in the pose from half a minute to a minute with deep breathing.

7. *Bend the elbows, release the stretch and rest on the floor.*

EFFECTS

The pose rejuvenates the spine and is specially recommended for people suffering from a stiff back. The movement is good for persons with lumbago, sciatica and those suffering from slipped or prolapsed discs of the spine. The pose strengthens the spine and cures backaches. Due to chest expansion, the lungs gain elasticity. The blood circulates properly in the pelvic region and keeps it healthy.

17| Adho Mukha Śvānāsana

FIVE*

Adho Mukha means having the face downwards. Śvāna means a dog. The pose resembles a dog stretching itself with head and forelegs down and the hind legs up, hence the name.

TECHNIQUE

1. Lie full length on the floor on the stomach, face downwards. The feet should be kept one foot apart.

2. Rest the palms by the side of the chest, the fingers straight and pointing in the direction of the head.

3. Exhale and raise the trunk from the floor. Straighten the arms, move the head inwards towards the feet and place the crown of the head on the floor, keeping the elbows straight and extending the back. (Side view: Plate 33. Back view: Plate 34)

4. Keep the legs stiff and do not bend the knees but press the heels down. The heels and soles of the feet should rest completely on the floor, while the feet should be parallel to each other, the toes pointing straight ahead.

5. Stay in the pose for about a minute with deep breathing. Then with an exhalation lift the head off the floor, stretch the trunk forward and lower the body gently to the floor and relax.



33

EFFECTS

When one is exhausted, a longer stay in this pose removes fatigue and brings back the lost energy. The pose is especially good for runners who get tired after a hard race. Sprinters will develop speed and lightness in the legs. The pose relieves pain and stiffness in the heels and helps to soften calcaneal spurs. It strengthens the ankles and makes the legs shapely. The practice of this āsana helps to eradicate stiffness in the region of the shoulder-blades, and arthritis of the shoulder joints is relieved. The abdominal muscles are drawn towards the spine and strengthened. As the diaphragm is lifted to the chest cavity the rate of the heart beat is slowed down. This is an exhilarating pose.

Those who are afraid to do Śīrṣāsana (Plate 90) can conveniently practise this position. As the trunk is lowered in this āsana it is fully stretched and healthy blood is brought to this region without any strain on the heart. It rejuvenates the brain cells and invigorates the brain by relieving fatigue.

Persons suffering from high blood pressure can do this pose.



34

18| *Daṇḍāsana*

TWO*

Daṇḍa means a staff or rod.

TECHNIQUE

Sit on the floor with the legs stretched in front. Place the palms on the floor by the hips, the fingers pointing to the feet. Stretch the hands straight and keep the back erect. (Plate 35)



35

19| *Paripūrṇa Nāvāsana*

TWO*

Paripūrṇa means entire or complete. The posture here resembles that of a boat with oars, hence the name.

TECHNIQUE

1. Sit on the floor as in Daṇḍāsana (18 above).

2. Exhale, recline the trunk slightly back and simultaneously raise the legs from the floor and keep them stiff as a poker with the knees tight and the toes pointing forwards. Balance is maintained only on the buttocks and no part of the spine should be allowed to touch the floor, from which the legs should be kept at an angle of 60 to 65 degrees. The feet are higher than the head and not level with it as in Ardha Nāvāsana. (Plate 37)

3. Remove the hands from the floor and stretch the arms forward, keeping them parallel to the floor and near the thighs. The shoulders and the palms should be on one level, and the palms should face each other. (Plate 36)

4. Stay in the pose for half a minute, with normal breathing. Gradually increase the time to one minute. One feels the effect of the exercise after only 20 seconds.

5. Then exhale, lower the hands, rest the legs on the floor and relax by lying on the back.



36



37

EFFECTS

This āsana gives relief to persons who feel a bloating sensation in the abdomen due to gas and also to those suffering from gastric complaints. It reduces fat around the waistline and tones the kidneys.

20| *Ardha Nāvāsana*

TWO*

Ardha means half. Nāva is a ship, boat or vessel. This posture resembles the shape of a boat, hence the name.

TECHNIQUE

1. Sit on the floor. Stretch the legs out in front and keep them straight. (Plate 35)

2. Interlock the fingers and place them on the back of the head just above the neck.

3. Exhale, recline the trunk back and simultaneously raise the legs from the floor, keeping the thighs and knees tight and the toes pointed. The balance of the body rests on the buttocks and no part of the spine should be allowed to touch the floor. (Plate 37) One feels the grip on the muscles of the abdomen and the lower back.

4. Keep the legs at an angle of about 30 to 35 degrees from the floor and the crown of the head in line with the toes.

5. Hold this pose for 20 to 30 seconds with normal breathing. A stay for one minute in this posture indicates strong abdominal muscles.

6. Do not hold the breath during this āsana, though the tendency is always to do it with suspension of breath after inhalation. If the breath is held, the effect will be felt on the stomach muscles and not on the abdominal organs. Deep inhalation in this āsana would loose the grip on the abdominal muscles. In order to maintain this grip, inhale, exhale and hold the breath and go on repeating this process but without breathing deeply. This will exercise not only the abdominal muscles but the organs also.

7. The difference between Ardha Nāvāsana and Paripūrṇa Nāvāsana should be noted; in the latter, the legs are moved higher and the distance between them and the stomach is less than in the former.

EFFECTS

The effects of Ardha Nāvāsana and that of Paripūrṇa Nāvāsana (Plate 36) differ due to the position of the legs. In Paripūrṇa Nāvāsana the exercise is effective on the intestines; whereas, Ardha Nāvāsana works on the liver, gall bladder and spleen.

In the beginning, the back is too weak to bear the strain of the pose. When power to retain this pose comes, it indicates that the back is gaining strength. A weak back is a handicap in many ways, especially to women as they need strong backs for child-bearing. These two āsanas coupled with lateral twistings of the spine will help to strengthen the back.

The importance of having a healthy lower back can be realized if we watch old people when they sit down, get up and walk, for consciously or unconsciously they support their backs with their hands. This indicates that the back is weak and cannot withstand the strain. As long as it is strong and needs no support, one feels young though advanced in age. The two āsanas bring life and vigour to the back and enable us to grow old gracefully and comfortably.

21| *Siddhāsana*

ONE*

Siddha means a semi-divine being supposed to be of great purity and holiness, and to possess supernatural faculties called siddhis. Siddha means also an inspired sage, seer or prophet.

'The Siddhas say that as among niyamas, the most important is not to harm anyone, and among the yamas a moderate diet, so is Siddhāsana among the āsanas.'

'Of the 84 lacs of āsanas, one should always practise Siddhāsana. It purifies 72,000 nāḍīs. (Nāḍīs are channels in the human body through which nervous energy passes.)

'The yogin practising contemplation upon Ātman and observing a moderate diet, if he practises Siddhāsana for twelve years, obtains the yoga siddhis.' (Ātman means the Self and the supreme Soul. Siddhīs are supernatural faculties.)

'When Siddhāsana is mastered, the Unmanī Avasthā (Samādhi) that gives delight follows without effort and naturally.'

The soul has three avasthās or conditions which are included in a fourth. They are waking, dreaming, sleeping and what is called Turīya.

'The first condition is that of wakefulness, where the self is conscious of the common world of gross objects. It enjoys gross things. Here the dependence of body is predominant. The second condition is that of dreaming, where the self enjoys subtle things, fashioning for itself a new world of forms from the material of its waking experience. The spirit is said to roam freely unfettered by the bonds of the body. The third condition is that of sound sleep, where we have neither dreams nor desires. It is called suṣupti. In it the soul is said to become temporarily one with Brahman and to enjoy bliss. In deep sleep we are lifted above all desires and freed from the vexations of spirit. . . . The soul is divine in origin, though clogged with the flesh. In sleep it is said to be released from the shackles of the body and to regain its own nature. . . . But this (that is, the eternal dreamless sleep) is likely to be confused with sheer unconsciousness. . . . The highest is not this dreamless sleep, but another, a fourth state of the soul, a pure intuitional consciousness where there is no knowledge of objects internal or external. In deep sleep the spirit dwells in a region far above the changeful life of sense in absolute union with Brahman. The turīya condition brings out the positive aspect of the negative emphasized in the condition of deep sleep.'

Radhakrishnan in Philosophy of the Upanishads.

This fourth condition has been thus described in the Māṇḍūkya Upanishad as follows:

'The fourth, say the wise, is not subjective experience, nor objective experience, nor experience intermediate between the two, nor is it a negative condition which is neither consciousness nor unconsciousness. It is not the knowledge of the senses, nor is it relative knowledge, nor yet inferential knowledge. Beyond the senses, beyond understanding, beyond all expression, is the fourth. It is pure unitary consciousness, wherein all awareness of the world and of multiplicity is completely obliterated. It is the supreme good. It is One without a second. It is the Self. Know it alone!'

'Rāja-Yoga, Samādhi, Unmanī, Manomanī, Immortality, Concentration, Śūnyāśūnya (void and yet non-void), Parama Pāda (the Supreme State), Amanaska (suspended operation of the mind), Advaita (non-duality), Nirālamba (without support), Nirañjana (pure), Jīvanmukti (emancipated state), Sahajāvasthā (natural state) and Turīyā (literally the Fourth), all mean the same thing. As a grain of salt thrown into water unites and becomes one with it, a like union between the Mind and the Ātman is Samādhi. When Praṇa and Manas (mind) are annihilated (absorbed), the state of harmony then arising is called Samādhi.'

Haṭha Yoga Pradīpikā,
chapter IV, verses 3 to 6.

There is no āsana like Siddha, no kumbhaka like Kevala, no mudrā like Khecharī, and no laya (absorption of the mind) like Nāda.

(Khecharī Mudrā, literally roaming through space, is described in the Gheranda Saṁhitā *as follows in verses 25 to 28 of the third chapter:*

'Cut the lower tendon of the tongue and move the tongue constantly; rub it with fresh butter, and draw it out (to lengthen it) with an iron instrument. By practising this always, the tongue becomes long and when it reaches the space between the eyebrows, then Khecharī is accomplished. Then (the tongue being lengthened) practise turning it up and back so as to touch the palate, till at

length it reaches the holes of the nostrils opening into the mouth. Close those holes with the tongue (thus stopping inspiration), and gaze on the space between the eyebrows. This is called Khecharī. By this practice there is neither fainting, nor hunger, nor thirst, nor laziness. There comes neither disease, nor decay, nor death. The body becomes divine.')

(Nāda is the inner mystical sound. Verses 79 to 101 of the fourth chapter describes it in great detail with a variety of similes. Yoga is defined as control over the aberrations of the mind. In order to control the mind it is necessary that it should first be absorbed in concentration of some object, then it is gradually withdrawn from that object and made to look within one's own self. This is where the yogi is asked to concentrate upon the inner mystical sounds. 'The mind is like a serpent, forgetting all its unsteadiness by hearing Nāda, it does not run away anywhere.' Gradually as Nāda becomes latent so does the mind along with it. 'The fire, catching the wood, is extinguished along with it (after burning it up); and so the mind also, working with Nāda, becomes latent along with it.')

TECHNIQUE

1. Sit on the floor, with legs stretched straight in front. (Plate 35)

2. Bend the left leg at the knee. Hold the left foot with the hands, place the heel near the perineum and rest the sole of the left foot against the right thigh.



38

3. Now bend the right leg at the knee and place the right foot over the left ankle, keeping the right heel against the pubic bone.

4. Place the sole of the right foot between the thigh and the calf of the left leg.

5. Do not rest the body on the heels.

6. Stretch the arms in front and rest the back of the hands on the knees so that the palms face upwards. Join the thumbs and the forefingers and keep the other fingers extended. (Plate 38).

7. Hold this position as long as you can, keeping the back, neck and head erect and the vision indrawn as if gazing at the tip of the nose.

8. Release the feet and relax for some time. Then repeat the pose for the same length of time, now placing the right heel near the perineum first and then the left foot over the right ankle as described above.

EFFECTS

This posture keeps the pubic region healthy. Like Padmāsana (Plate 53), it is one of the most relaxing of āsanas. The body being in a sitting posture is at rest, while the position of the crossed legs and erect back keeps the mind attentive and alert. This āsana is also recommended for the practice of prāṇāyāma and for meditation.

From the purely physical point of view, the āsana is good for curing stiffness in the knees and ankles. In it the blood circulates in the lumbar region and the abdomen, and this tones the lower region of the spine and the abdominal organs.



39



40

22| *Vīrāsana*

ONE*

Vīra means a hero, warrior, champion. This sitting posture is done by keeping the knees together, spreading the feet and resting them by the side of the hips.

The pose is good for meditation and prāṇāyāma.

TECHNIQUE

1. Kneel on the floor. Keep the knees together and spread the feet about 18 inches apart.

2. Rest the buttocks on the floor, but not the body on the feet. The feet are kept by the side of the thighs, the inner side of each calf touching the outer side of its respective thigh. Keep the toes pointing back and touching the floor. Keep the wrists on the knees, palms facing up, and join the tips of the thumbs and forefingers. Keep the other fingers extended. Stretch the back erect. (Back view: Plate 42. Front view: Plate 43)

3. Stay in this position as long as you can, with deep breathing.

4. Now interlock the fingers and stretch the arm straight over the head, palms up. (Plate 44)

5. Stay in this position for a minute with deep breathing.

6. Exhale, release the fingerlock, place the palms on the soles, bend forward and rest the chin on the knees. (Plate 45)

7. Stay in this position for a minute with normal breathing.

8. Inhale, raise the trunk up, bring the feet forward and relax.

9. If you find it difficult to perform the pose as described above, try placing the feet one above the other and rest the buttocks on them. (Plate 39) Gradually move the toes further apart, separate the feet (Plates 40 and 41) and bring them to rest outside the thighs. Then, in time the buttocks will rest properly on the floor and the body will not rest on the feet.

EFFECTS

The pose cures rheumatic pains in the knees and gout, and is also good for flat feet. Due to the stretching of the ankles and the feet, proper arches will be formed. This, however, takes a long time and requires daily practice of the pose for a few minutes for several months. Those suffering from pain in the heels or growth of calcaneal spurs there will get relief and the spurs will gradually disappear.

The pose can even be done immediately after food and will relieve heaviness in the stomach.


41


42


43


45


44

23| *Supta Vīrāsana*

TWO*

Supta means lying down. In this āsana one reclines back on the floor and stretches the arms behind the head.

TECHNIQUE

1. Sit in Vīrāsana. (Plate 43)

2. Exhale, recline the trunk back and rest the elbows one by one on the floor. (Plate 46)

3. Relieve the pressure on the elbows one after the other by extending the arms.

4. At first rest the crown of the head on the floor. (Plate 47) Gradually rest the back of the head and then the back on the floor. (Plate 48) Take the arms over the head and stretch them out straight. (Plate 49) Hold this pose as long as you can while breathing deeply. Then place the arms beside the trunk, press the elbows to the floor and sit up again with an exhalation.

5. The hands may be stretched over the head or placed beside the thighs. When they are stretched over the head, do not raise the shoulder-blades from the floor.

6. Beginners may keep the knees apart.


46


47


48


49

EFFECTS

This āsana stretches the abdominal organs and the pelvic region. People whose legs ache will get relief from holding this pose for 10 to 15 minutes and it is recommended to athletes and all who have to walk or stand about for long hours. It can be done after meals and if before retiring at night the legs feel rested next morning. Several of my pupils who were cadets at the National Defence Academy after long route marches found great relief by combining this āsana with Sarvāngāsana I. (Plate 102)

24| *Baddha Koṇāsana*

THREE*

Baddha means caught, restrained. Koṇa means an angle. In this posture, sit on the floor, bring the heels near the perineum, catch the feet and widen the thighs until the knees touch the floor on either side. This is how Indian cobblers sit.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. (Plate 35)

2. Bend the knees and bring the feet closer to the trunk.

3. Bring the soles and heels of the feet together and catching the feet near the toes, bring the heels near the perineum. The outer sides of both feet should rest on the floor, and the back of the heels should touch the perineum.



50



51

4. Widen the thighs and lower the knees until they touch the floor.

5. Interlock the fingers of the hands, grip the feet firmly, stretch the spine erect and gaze straight ahead or at the tip of the nose. (Plate 50) Hold the pose as long as you can.

6. Place the elbows on the thighs and press them down. Exhale, bend forward, rest the head, then the nose and lastly the chin on the floor. (Plate 51) Hold this position from half a minute to a minute with normal breathing.

7. Inhale, raise the trunk from the floor and come back to position 5. (Plate 50)

8. Then release the feet, straighten the legs and relax.



52

EFFECTS

The pose is specially recommended for those suffering from urinary disorders. The pelvis, the abdomen and the back get a plentiful supply of blood and are stimulated. It keeps the kidneys, the prostate and the urinary bladder healthy. It is well known that diseases of the urinary tract are rarely found among the Indian cobblers and the reason for that is that they sit all day in this pose.

It relieves sciatic pain and prevents hernia. If practised regularly, it relieves pain and heaviness in the testicles.

The pose is a blessing to women. Coupled with Sarvāngāsana I (Plate 102) and its cycle (Plates 113 to 125) it checks irregular menstrual periods and helps the ovaries to function properly. It is found that pregnant women who sit daily in this pose for a few minutes will have much less pain during delivery and will be free from varicose veins. (It is recommended for pregnant women in Dr Grantly Dick Reed's book *Childbirth Without Fear*.)

Along with Padmāsana (Plate 53) and Vīrasana (Plate 43) this āsana is recommended for Prāṇāyāma practice and for meditation. When sitting in meditation in this pose the palms should be folded in front of the chest (Plate 52), but to do this with the back erect requires practice. This asana can be done without fear even after meals as long as the head is not rested on the floor.

25 *Padmasana*

FOUR*

Padma means a lotus. This is the lotus posture, one of the most important and useful āsanas. It is the posture for meditation and the Buddha is often depicted in it.

Verse 48 of the first chapter of the Hatha Yoga Pradīpikā *describes the posture and the practice of breath control while seated in it thus:*

'Assuming Padmasana and having placed the palms one upon another, fix the chin firmly upon the breast and contemplating upon Brahman, frequently contract the anus and raise the apana up; by similar contraction of the throat force the prana down. By this he obtains unequalled knowledge through the favour of Kundalinī (which is roused by this process).'

Kundalinī is the Divine Cosmic Energy in bodies. It is symbolized by a coiled and sleeping serpent in the lowest bodily centre at the base of the spinal column. This latent energy has to be awakened and made to go up the spine to the brain through Suṣumnā Naḍi, a channel through which nervous energy passes, and through the six chakras, the subtle centres in the body, the fly-wheels in the nervous system of the human machine. The awakening of Kundalinī is discussed in detail in Arthur Avalon's (Sir John Woodroffe's) book entitled The Serpent Power.

This is one of the basic postures and is often used in the variations of Śīrṣāsana and Sarvangāsana.

TECHNIQUE

1. Sit on the floor with the legs straight. (Plate 35)

2. Bend the right leg at the knee, hold the right foot with the hands and place it at the root of the left thigh so that the right heel is near the navel.

3. Now bend the left leg, and holding the left foot with the hands place it over the right at the root, the heel being near the navel. The soles of the feet should be turned up. This is the basic Padmāsana pose. (Plate 53)

4. People not used to sitting on the floor seldom have flexible knees. At the start they will feel excruciating pain around the knees. By perseverance and continued practice the pain will gradually subside and they can then stay in the pose comfortably for a long time.

5. From the base to the neck the spine should remain erect. The arms may be stretched out, the right hand being placed on the right knee and the left hand on the left knee. The forefingers and the thumbs are bent and touch each other.

6. Change the leg position by placing the left foot over the right thigh and the right foot over the left thigh. This will develop the legs evenly.



53

EFFECTS

After the initial knee pains have been overcome, Padmāsana is one of the most relaxing poses. The body being in a sitting posture, it is at rest without being sloppy. The position of the crossed legs and the erect back keeps the mind attentive and alert. Hence it is one of the āsanas recommended for practising prāṇāyāma (breath control).

On the purely physical level, the pose is good for curing stiffness in the knees and ankles. Since the blood is made to circulate in the lumbar region and the abdomen, the spine and the abdominal organs are toned.

26| *Parvatāsana*

FOUR*

Parvata means a mountain. In this variation of Padmāsana the arms are stretched over the head with the fingers interlocked.

TECHNIQUE

1. Sit in Padmāsana. (Plate 53)

2. Interlock the fingers, and stretch the hands vertically up over the head. Keep the head bent forward with the chin on the breast bone.

3. Stretch the arms up from the latissimus dorsi (near the floating ribs at the back) and the shoulder-blades. The palms should face upwards. (Plate 54)

4. Hold the pose for a minute or two with deep and even breathing. Change the crossing of the legs and the interlock of the fingers and repeat the pose, keeping the back erect.

EFFECTS

The āsana relieves rheumatic pains and stiffness in the shoulders. It helps draw free movement and to develop the chest. The abdominal organs are drawn in and the chest expands fully.



54

27| *Matsyāsana*

FIVE*

Matsya means a fish. This posture is dedicated to Matsya the Fish Incarnation of Viṣṇu, the source and maintainer of the universe and of all things. It is related that once upon a time the whole earth had become corrupt and was about to be overwhelmed by a universal flood. Viṣṇu took the form of a fish and warned Manu (the Hindu Adam) of the impending disaster. The fish then carried Manu, his family and the seven great sages in a ship, fastened to a horn on his head. It also saved the Vedas from the flood.

TECHNIQUE

1. Sit in Padmāsana. (Plate 53)

2. Lie flat on the back with the legs on the floor.

3. Exhale, arch the back by lifting the neck and the chest, take the head back and rest the crown on the floor. Drag the head further back by holding the crossed legs with the hands and increase the back arch. (Plate 55)

4. Now take the hands from the legs, bend the arms, hold the elbows with the hands and rest the forearms on the floor behind the head. (Plate 56)

5. Stay in this position from 30 to 60 seconds while breathing deeply.

6. Rest the back of the head on the floor, lie flat on the back, inhale and then come up to Padmāsana, release the legs and relax.

7. Recross the legs the other way and repeat the pose for the same length of time.

8. If positions 3 and 4 are difficult to achieve, lie flat on the back with the arms stretched straight over the head. (Plate 57)

EFFECTS

The dorsal region is fully extended in this posture and the chest is well expanded. Breathing becomes fuller. The thyroids benefit from the exercise due to the stretching of the neck. The pelvic joints become elastic. The āsana relieves inflamed and bleeding piles.



55



56



57

28| *Baddha Padmāsana*

SIX*

Baddha means caught, restrained. In this position the hands are crossed at the back and the big toes are caught from behind. The body is caught between the crossed legs in front and the crossed hands behind, hence the name.

TECHNIQUE

1. Sit in Padmāsana. (Plate 53)

2. Exhale, swing the left arm back from the shoulders and bring the hand near the right hip. Catch the left big toe, hold the position and inhale.

3. Similarly, with an exhalation, swing the right arm back from the shoulder, bring it near the left hip and catch the right big toe. (Front view: Plate 58. Back view: Plate 59)

4. If the toes are difficult to catch stretch the shoulders back, so that the shoulder-blades are brought near each other. A little practice in swinging the arms back with an exhalation will enable one to catch the big toes.

5. If the right foot is placed over the left thigh and then the left foot over the right thigh, catch the left big toe first and then the right big toe. If, on the other hand, the left foot is placed over the right thigh first and then the right foot over the left thigh, catch the right big toe first and then the left big toe. Catch first the big toe of the foot which is uppermost.



58



59

6. Throw the head as far back as possible and take a few deep breaths.

7. Inhale deeply, and then with an exhalation bend the trunk forward from the hips and rest the head on the floor, without releasing the toes from the hand grip. Bending the head forward in Baddha Padmāsana (Plate 58) and touching it on the floor is called:

29| *Yoga Mudrāsana*

SIX*

This āsana is especially useful in awakening Kuṇḍalinī.

EFFECTS

Crossing the hands behind the back expands the chest and increases the range of shoulder movement. Yoga Mudrāsana (Plate 60) intensifies the peristaltic activity and pushes down the accumulated waste matter in the colon and thereby relieves constipation and increases digestive power.

30| *Mahā Mudrā*

FIVE*

Mahā means great or noble. Mudrā means shutting, closing or sealing. In this sitting posture the apertures at the top and bottom of the trunk are held fast and sealed.

TECHNIQUE

1. Sit on the floor with the legs stretched in front. (Plate 35)

2. Bend the left knee and move it to the left, keeping the outer side of the left thigh and the left calf on the floor.

3. Place the left heel against the inner side of the left thigh near the perineum. The big toe of the left foot should touch the inner side of the right thigh. The angle between the extended right leg and the bent left leg should be a right angle of 90 degrees.



60

4. Stretch the arms forward towards the right foot and hook the big toe with the thumbs and forefingers.

5. Lower the head to the trunk until the chin rests in the hollow between the collar bones just above the breast-bone.

6. Keep the spine fully stretched and do not allow the right leg to tilt to the right.

7. Inhale completely. Tighten the entire abdomen from the anus to the diaphragm. Pull the abdomen back towards the spine and also up towards the diaphragm.

8. Relax the abdominal tension, then exhale, again inhale and hold the breath, maintaining the abdominal grip. Hold this posture as stated above from one to three minutes. (Plate 61)

9. Relax the abdominal tension, exhale, raise the head, release the hands and straighten the bent leg.

10. Repeat on the other side, keeping the left leg straight and the right one bent for an equal length of time.

EFFECTS

This āsana tones the abdominal organs, the kidneys and adrenal glands. Women suffering from a prolapsed womb find relief as it pulls the womb up to its original position. Persons suffering from spleen ailments and from enlargement of the prostate gland will benefit by staying in this pose longer. It cures indigestion.

'This Mahāmudrā destroys death and many other pains. 'There is nothing that one cannot eat or has to avoid (if one has practised it). All food regardless of taste and even when deadly poisonous is digested.' 'He who practices Mahāmudrā, overcomes consumption, leprosy, piles, enlargement of the spleen, indigestion and other complaints of long duration.' (*Haṭha Yoga Pradīpikā*, chapter 3, verses 14, 16 and 17.)



61

31| *Jānu Śīrṣāsana*

FIVE*

Jānu means the knee. Śīrṣa is the head. In this posture sit with one leg stretched out on the ground and the other bent at the knee. Then catch the extended foot with both the hands and place the head on that knee.

TECHNIQUE

1. Sit on the floor, with legs stretched straight in front. (Plate 35)

2. Bend the left knee and move it to the left, keeping the outer side of left thigh and the left calf on the floor.

3. Place the left heel against the inner side of the left thigh near the perineum. The big toe of the left foot should touch the inner side of the right thigh. The angle between the two legs should be obtuse. Do not keep the left knee in line with the left thigh at a right angle to the extended right leg. Try and push the left knee as far back as possible, so that the body is stretched from the bent leg.

4. Extend the arms forward towards the right foot and hold it with the hands. First catch the toes of the right foot, then gradually catch the sole, then the heel and finally extend the arms and catch the wrist of one hand with the other, beyond the outstretched foot. (Plate 62)



62



63

5. Keep the right leg stretched throughout by tightening the knee. See that the back of the right knee rests on the floor.

6. Exhale, move the trunk forward by bending and widening the elbows, and rest first the forehead, then the nose, then the lips and lastly the chin beyond the right knee. (Plate 63) The right foot will tilt to the right in the beginning. Do not allow the leg to tilt.

7. Stretch the back fully, pull the trunk forward and keep the chest against the right thigh.

8. Stay in this position with deep breathing from half a minute to a minute. One can also do the pose holding the breath after each exhalation.

9. Inhale, raise the head and trunk, straighten the arms and gaze up for a few seconds, extending the spine and trying to make it concave. (Plate 62)

10. Release the hand grip on the right foot, straighten the left leg and come back to position 1.

11. Repeat the pose keeping the left leg stretched out and bending the right leg at the knee. Stay in the pose for the same length of time on both the sides.

EFFECTS

This āsana tones the liver and the spleen and thereby aids digestion. It also tones and activates the kidneys, the effect on which can be felt while one is performing the pose as explained above.

Persons suffering from enlargement of the prostate gland will benefit by staying longer in this pose. They should practice this āsana along with Sarvāngāsana. (Plate 102)

The pose is also recommended for people suffering from low fever for a long time.

32| *Ardha Baddha Padma Paschimottānāsana*

EIGHT*

Ardha means half, baddha means caught, restrained and padma a lotus. Paschimottānāsana (Plate 81) is the posture where the back of the whole body is intensely stretched.

TECHNIQUE

1. Sit on the floor, with the legs stretched straight in front. (Plate 35)

2. Bend the left leg at the knee, and place the left foot over the right thigh. The left heel should press the navel and the toes should be stretched and pointing. This is the half lotus posture.



64



65

3. Bring the left arm round the back from behind and with an exhalation catch the big toe of the left foot. If the toe cannot be grasped easily, swing back the left shoulder.

4. After holding the left big toe, move the bent left knee nearer to the extended right leg. Stretch the right arm forward and catch the right foot with the right hand, the palm touching the sole. (Plates 64 and 65)



66



67

5. Inhale, stretch the back and gaze up for a few seconds, without releasing the grip on the left big toe.

6. Exhale, move the trunk forward by bending the right elbow outwards. Rest the forehead, then the nose, then the lips and lastly the chin on the right knee. (Plate 66)

7. In the initial stages, the knee of the extended leg will be lifted off the floor. Tighten the thigh muscles and rest the entire back of the extended right leg on the floor.

8. Stay in this position from 30 to 60 seconds, breathing evenly.

9. Inhale, raise the head and trunk, release the hands, straighten the left leg and come to position 1.

10. Repeat the pose on the other side, keeping the left leg stretched out on the ground, bending the right knee and placing the right foot on the left thigh. Stay for the same length of time on both sides.

11. If you cannot hold the toe with the hand from behind, hold the extended leg with both hands and follow the above techniques. (Plate 67)

EFFECTS

Due to the half lotus pose, the knees become flexible enough to execute the full lotus pose. While placing the chin on the knee of the extended leg, the bent knee is brought close to the stretched leg. This gives a good pull to the navel and abdominal organs. Blood is made to flow round the navel and the genital organs. The navel is considered to be a nerve centre, and the Svādhiṣṭhāna Chakra, one of the purificatory fly-wheels in the human nervous system, is situated there. This chakra corresponds to the hypo-gastric plexus. The pose is recommended for persons with rounded and drooping shoulders.

33| Triaṅgā Mukhaikapda Paschimottānāsana

FIVE*

Trianga means three limbs or parts thereof. In this posture the three parts are the feet, knees and buttocks. Mukhaikapāda (a compound of three words, mukha = face, eka = one, and pāda = leg or foot) corresponds to the face (or mouth) touching one (extended) leg. In Paschimottānāsana (Plate 81) the back of the whole body is intensely stretched.



68



69

TECHNIQUE

1. Sit on the floor, with the legs stretched straight in front. (Plate 35)

2. Bend the right leg at the knee and move the right foot back. Place the right foot by the side of the right hip joint, keep the toes pointing back and rest them on the floor. The inner side of the right calf will touch the outer side of the right thigh.

3. Balance in this position, throwing the weight of the body on the bent knee. In the beginning, the body tilts to the side of the outstretched leg, and the foot of the outstretched leg also tilts outwards. Learn to balance in this position, keeping the foot and toes stretched and pointing forward.

4. Now hold the left foot with both the palms, gripping the sides of the sole. If you can, then extend the trunk forward and hook the wrists round the outstretched left foot. (Plate 68) Take two deep breaths. It usually takes several months before one can hook the wrists in this way, so do not despair after the first few attempts.

5. Join the knees, exhale and bend forward. Rest first the forehead, then the nose, next the lips and ultimately the chin on the left knee. (Plate 69) To achieve this, widen the elbows and push the trunk forward with an exhalation.

6. Do not rest the left elbow on the floor. In the beginning, one loses balance and topples over to the side of the extended leg. The trunk should, therefore, be slightly bent towards the side of the bent leg and the weight of the body should be taken by the bent knee.

7. Stay in this position from half a minute to a minute, breathing evenly.

8. Inhale, raise the head and trunk, release the hands, straighten the right leg and come to position 1.

9. Repeat the pose on the other side, keeping the right leg stretched out on the ground, bending the left knee and placing the left foot by the left hip joint. Stay for the same length of time on both sides.

EFFECTS

This āsana is recommended for persons suffering from dropped arches and flat feet. It cures sprains in the ankle and the knee, and any swelling in the leg is reduced.

Along with Jānu Śīrṣāsana (Plate 63) and Ardha Baddha Padma Paschimottānāsana (Plate 66), this āsana tones the abdominal organs and keeps them free from sluggishness. We abuse our abdominal organs by over-indulgence or by conforming to social etiquette. Abdominal organs cause a majority of diseases and ancient sages emphasized that their health was essential for longevity, happiness and peace of mind. These forward bending āsanas keep the abdominal organs healthy and in trim. Apart from keeping the muscles in shape, they work on the organs as well.

34| *Marīchyāsana I*

FIVE*

This āsana is dedicated to the sage Marīchi, son of the Creator, Brahmā. Marīchi was the grandfather of Sūrya (the Sun God).

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. (Plate 35)

2. Bend the left knee and place the sole and heel of the left foot flat on the floor. The shin of the left leg should be perpendicular to the floor and the calf should touch the thigh. Place the left heel near the perineum. The inner side of the left foot should touch the inner side of the outstretched right thigh.

3. Stretch the left shoulder forward till the left armpit touches the perpendicular left shin. Turn the left arm round the left shin and thigh, bend the left elbow and throw the left forearm behind the back at the level of the waist. Then move the right hand behind the back and clasp the left hand with the right at the wrist or vice versa. If that is not possible then clasp the palms or the fingers. (Plate 70)

4. Now, turn the spine to the left, keeping the outstretched right leg straight. Remain in this position gazing at the outstretched right big toe and take a few deep breaths.



70

5. Exhale, and bend forward. Rest the forehead, then the nose, next the lips and lastly the chin on the right knee. (Plate 71). While in this position, keep both shoulders parallel to the floor and breathe normally. Stay in the pose for about 30 seconds and see that the back of the entire extended leg rests on the floor throughout.

6. Inhale, raise the head from the right knee (Plate 70), release the hands, straighten the left leg and come to position 1.

7. Repeat the pose on the other side for an equal length of time.

EFFECTS

The fingers gain in strength by the practice of this āsana. In the preceding āsanas (namely, Jānu Śīrṣāsana (Plate 63), Ardha Baddha Padma Paschimottānāsana (Plate 66) and Triang Mukhaikapāda Paschimottānāsana (Plate 69) the abdominal organs are made to contract by gripping a leg with the hands. In this pose the hands do not hold the legs. To bend forward and to rest the chin on the knee of the extended leg the abdominal organs have to contract vigorously. This creates a better circulation of blood round the abdominal organs and keeps them healthy. In the beginning it is very difficult to bend forward at all after gripping both hands behind the back, but it comes with practice. The dorsal region of the spine is also exercised in this pose.

NOTE

The four poses, Jānu Śīrṣāsana, Ardha Baddha Padma Paschimottānāsana, Triang Mukhaikapāda Paschimottānāsana and Marīchyāsana I, are preparatory poses for the correct Paschimottānāsana. (Plate 81) It is difficult for many to get a good grip on the feet in Paschimottānāsana even after several attempts. These four āsanas give one sufficient elasticity in the back and legs so that one gradually achieves the correct Paschimottānāsana (Plate 81) as described later. Once this is done with ease, these four āsanas can be practised once or twice a week instead of daily.



71

35| *Upaviṣṭha Koṇāsana*

NINE*

Upaviṣṭha means seated. Koṇa means an angle.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. (Plate 35)

2. Move the legs sideways one by one and widen the distance between them as far as you can. Keep the legs extended throughout and see that the back of the entire legs rests on the floor.

3. Catch the big toes between the respective thumbs and index and middle fingers.

4. Keep the spine erect and extend the ribs. Pull the diaphragm up and hold the pose for a few seconds with deep breaths. (Plate 72)



72

5. Now clasp the feet with the hands. Exhale, bend forward and rest the head on the floor. (Plate 73) Then extend the neck and place the chin on the floor.

6. Then, try to rest the chest on the floor. (Plate 74) Stay in this position from 30 to 60 seconds with normal breathing.

7. Inhale, raise the trunk off the floor (Plate 72) and release the hold on the feet, bring them together and relax.



73



74

EFFECTS

The āsana stretches the hamstrings and helps the blood to circulate properly in the pelvic region and keeps it healthy. It prevents the development of hernia of which it can cure mild cases and relieves sciatic pains. Since the āsana controls and regularizes the menstrual flow and also stimulates the ovaries, it is a boon to women.

36| *Paschimottānāsana (also called Ugrāsana or Brahmacharyāsana)*

SIX*

Paschima literally means the west. It implies the back of the whole body from the head to the heels. The anterior or eastern aspect is the front of the body from the face down to the toes. The crown of the head is the upper or northern aspect while the soles and heels of the feet form the lower or southern aspect of the body. In this āsana the back of the whole body is intensely stretched, hence the name.

Ugra means formidable, powerful and noble. Brahmacharya means religious study, self-restraint and celibacy.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. Place the palms on the floor by the side of the hips. Take a few deep breaths. (Plate 35)

2. Exhale, extend the hands and catch the toes. Hold the right big toe between the right thumb and the index and middle fingers and likewise the left big toe. (Plate 75)

3. Extend the spine and try to keep the back concave. To start with the back will be like a hump. This is due to stretching the spine only from the area of the shoulders. Learn to bend right from the pelvic region of the back and also to extend the arms from the shoulders. Then the hump will disappear and the back will become flat as in Plate 75. Take a few deep breaths.

4. Now exhale, bend and widen the elbows, using them as levers, pull the trunk forward and touch the forehead to the knees. (Plate 76) Gradually rest the elbows on the floor, stretch the neck and trunk, touch the knees with the nose and then with the lips. (Plate 77)



75



76



77



78



79



80

5. When this becomes easy, make a further effort to grip the soles and rest the chin on the knees. (Plate 78)

6. When this also becomes easy, clasp the hands by interlocking the fingers and rest the chin on the shins beyond the knees. (Plate 79)

7. When position 6 becomes easy, grip the right palm with the left hand or the left palm with the right hand beyond the outstretched feet exhale and rest the chin on the shins beyond the knees. (Plate 80)

8. If position 8 also becomes easy, hold the right wrist with the left hand or the left wrist with the right hand and rest the chin on the shins beyond the knees. (Plate 81)

9. See that the back of the legs at the knee joints rests firmly on the ground. In the initial stages the knees will be lifted off the floor. Tighten the muscles at the back of the thighs and pull the trunk forward. Then the back of the knee joints will rest on the floor.

10. Try and stay in whichever of the above positions you can achieve from 1 to 5 minutes, breathing evenly.

11. Inhale, raise the head from the knees and relax.

EFFECTS

This āsana tones the abdominal organs and keeps them free from sluggishness. It also tones the kidneys, rejuvenates the whole spine and improves the digestion.

The spines of animals are horizontal and their hearts and below the spine. This keeps them healthy and gives them great power of endurance. In humans the spine is vertical and the heart is not lower than the spine, so that they soon feel the effects of exertion and are also susceptible to the heart diseases. In Paschimottānāsana the spine is kept straight and horizontal and the heart is at a lower level than the spine. A good stay in this pose massages the heart, the spinal column and the abdominal organs, which feel refreshed and the mind is rested. Due to the extra stretch given to the pelvic region more oxygenated blood is brought there and the gonad glands absorb the required nutrition from the blood. This increases vitality, helps to cure impotency and leads to sex control. Hence, this āsana was called Brahmacharyāsana. Brahmacharya means celibacy and a Brahmachāri is one who has controlled the sex appetite.



81

37| *Pūrvottānāsana*

ONE*

Pūrva literally means the East. It means the front of the whole body from the forehead to the toes. Uttāna means an intense stretch. In this posture, the whole front of the body is stretched intensely.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. Place the palms on the floor by the hips, with the fingers pointing in the direction of the feet. (Plate 35)

2. Bend the knees and place the soles and heels on the floor.

3. Take the pressure of the body on the hands and feet, exhale and lift the body off the floor. Straighten the arms and the legs and keep the knees and elbows tightened. (Plate 82)

4. The arms will be perpendicular to the floor from the wrists to the shoulders. From the shoulders to the pelvis, the trunk will be parallel to the floor.

5. Stretch the neck and throw the head as far back as possible.

6. Stay in this posture for one minute, breathing normally.

7. Exhale, bend the elbows and knees, lower the body to sit on the floor and relax.

EFFECTS

This posture strengthens the wrists and ankles, improves the movement of the shoulder joints and expands the chest fully. It gives relief from the fatigue caused by doing other strenuous forward bending āsanas.

38| *Sālamba Śīrṣāsana I*

FOUR*

Sālamba means with support. Śīrṣa means the head. This is the head stand pose, one of the most important Yogi āsanas. It is the basic posture. It has several variations, which are described later as the Śīrṣāsana cycle. Its mastery gives one balance and poise, both physically and mentally. The technique of doing it is given at length in two parts; the first is for beginners, the second for those who can remain balanced in the pose. Attention is specially directed to the hints on Śīrṣāsana given after the two techniques.



82

TECHNIQUE FOR BEGINNERS

1. Spread the blanket fourfold on the floor and kneel near it.

2. Rest the forearms on the centre of the blanket. While doing so take care that the distance between the elbows on the floor is not wider than the shoulders.

3. Interlock the fingers right up to the finger-tips (Plate 83), so that the palms form a cup. Place the sides of the palms near the little fingers on the blankets. While going up on to your head or balancing, the fingers should be kept tightly locked. If they are left loose, the weight of the body falls on them and the arms ache. So remember to lock them well.



83



84



85

4. Rest the crown of the head only on the blanket, so that the back of the head touches the palms which are cupped. (Plate 84) Do not rest the forehead nor the back but only the crown of the head on the blanket. To do this move the knees towards the head.

5. After securing the head position, raise the knees from the floor by moving the toes closer to the head. (Plate 85)

6. Exhale, take a gentle swing from the floor and lift the legs off the ground with bent knees. Take the swing in such a way that both feet leave the floor simultaneously, to come to position as in Plate 86. When once this position is secured, follow the various stages of the leg movements as in Plates 87, 88 and 89, step by step.

7. Stretch the legs and stand on the head, keeping the whole body perpendicular to the floor. (Front view: Plate 90. Back view: Plate 91. Side view: Plate 96)

8. After staying in the final position to capacity, from one to five minutes, flex the knees and slide down to the floor in the reverse order as in Plates 89, 88, 87, 86, 85, 84 and raise head from the floor.

9. A beginner must have the assistance of a friend or do the āsana against a wall. While practising against a wall, the distance between it and the head should not be more than 2 or 3 inches. If the distance is greater, the spine will curve and the stomach will protrude. The weight of the body will be felt on the elbows and the position of the head may change. The face will appear to be flushed and the eyes either strained or puffed. It is, therefore, advisable for a beginner to do the head stand in a corner where two walls meet, placing the head some 2 to 3 inches from either wall.


86


87


88


89

10. While doing the head stand against a wall or in a corner, the beginner should exhale, swing the legs up, support the hips against the side of the wall and move the feet up. In a corner, he can touch the heels to either side of the walls. He should then stretch the back vertically up, gradually leave the support of the wall and learn to master the balance. While coming down, he can rest the feet and hips against the wall, slide down and kneel, resting his knees on the floor. The movements of coming down and going up should be done with an exhalation.

11. The advantage which the beginner has of balancing in a corner is that his head and legs will be in the right angle formed by the walls, and he will be sure of his right position. This will not be the case if he balances against a straight wall. For while his balance is insecure he may sway from the wall, or his body may tilt or swing to the stronger side, while his legs may rest against the wall with a bend either at the waist or the hips. The beginner will not be in a position to know that he has tilted to one side, much less to correct it. In time he may learn to balance on the head, but by habit his body may still tilt or his head may not be straight. It is as hard to correct a wrong pose in the head stand as it is to break a bad habit. Moreover this wrong posture may well lead to aches and pains in the head, neck, shoulders and back. But the two walls of a corner will help the beginner to keep the āsana symmetrical.


90


91



92



93

12. When once balance is secured, it is advisable to come down to the floor with the legs straight (that is, without bending the knees at all) and with a backward action of the hips. At first, it is not possible to go up and come down without bending the legs, but the correct method should be learnt. Once the beginner has confidence in the head stand, he will find it more beneficial to go up and down with the legs together and straight, without any jerks.

13. It takes time for the beginner to become oriented to his surroundings while he is balancing on his head. Everything will seen at first to be completely unfamiliar. The directions and instructions will appear confusing and he will find it an effort to think clearly or to act logically. This is due to fear of a fall. The best way to overcome fear is to face with equanimity the situation of which one is afraid. Then one gets the correct perspective, and one is not frightened any more. To topple over while learning the head stand is not as terrible as we imagine. If one overbalances, one should remember to loosen the interlocked fingers, relax, go limp and flex the knees. Then one will just roll over and smile. If the fingers are not loosened they will take the jerk of the fall which will be painful. If we do not relax and go limp while falling we hit the floor with a hard bump. If we flex the knees, we are unlikely to graze them in the fall. After one has learnt to balance against a wall or in a corner, one should try the head stand in the middle of the room. There will be a few spills and one must learn the art of falling as indicated above. Learning to do Śīrṣāsana in the middle of a room gives the beginner more confidence.

TECHNIQUE FOR THOSE WHO CAN BALANCE EIGHT*

1. Follow the technique described for beginners from positions 1 to 4.

2. After securing the head position, stretch the legs straight by raising the knees from the floor. Move the toes nearer to the head and try to press the heels to the floor, keeping the back erect. (Plate 92)

3. Stretch the dorsal or middle region of the spine and stay in this position for about 30 seconds while breathing evenly.

4. Exhale, raise the heels and take the toes off the floor with a backward movement of the hips. Raise both legs simultaneously, keeping them poker stiff. (Plate 93) Take a breath.

5. Again with an exhalation move the legs up until they are parallel to the floor. This position is called:

39| Ūrdhvā Daṇḍāsana

EIGHT*

(Ūrdhvā = up, daṇḍ = a staff)
Stay in this position for 10 seconds with normal breathing.

6. Exhale, move the legs up as in Plate 95, and then pull them up to the vertical position. (Side view: Plate 96) Stay in this pose from 1 to 5 minutes while breathing evenly.

7. Come down gradually, observing the above technique in a reverse order. (Plates 95, 94, 93 and 92) Rest the feet on the floor, bend the knees (Plate 84) and raise the head from the floor or blanket. (Plate 83)

8. While coming down, it is advisable to stay in Ūrdhvā Daṇḍāsana according to capacity up to one minute while breathing normally. In this position, the neck and trunk will not be perpendicular to the floor but will sway slightly backwards. The neck, shoulders and spine will be put to a very great strain and in the initial stages one cannot stay with the legs parallel to the floor for more than a few seconds. The stay will become longer as the neck, shoulders, abdomen and spine become stronger.

HINTS ON ŚĪRṢĀSANA

1. In Śīrṣāsana the balance alone is not important. One has to watch from moment to moment and find out the subtle adjustments. When we stand on our feet, we need no extra effort, strength or attention, for the position is natural. Yet the correct method of standing affects our bearing and carriage. It is, therefore, necessary to master the correct method as pointed out in the note on Tāḍāsana. In Śīrṣāsana also, the correct position should be mastered, as a faulty posture in this āsana will lead to pains in the head, neck and back.



94

95

2. The whole weight of the body should be borne on the head alone and not on the forearms and hands. The forearms and hands are to be used only for support to check any loss of balance. In a good pose you feel a circle, about the size of an Indian rupee, of the head in contact with the blanket on the floor.

3. The back of the head, the trunk, the back of the thighs and the heels should be in a line perpendicular to the floor and not inclined to one side. The throat, chin and breast-bone should be in one line, otherwise the head will tilt to one side or move forward. As regards the interlocked hands behind the head, the palms should not be stuck into the head. The upper and the lower sides of the palms should be in a line, otherwise the crown of the head will not rest on the floor correctly.

4. The elbows and the shoulders should be in a line and the elbows should not be widened. The shoulders should be kept as high above the floor as possible

by moving them up and stretching them sideways. In order to learn the correct shoulder stretch, release the interlocked fingers and remove the hands from behind the head and widen the wrists from the forearms, keeping the elbows stationary. Place the wrists on the floor with the palms facing up, touch the shoulders with the fingers, keeping the wrists on the floor and maintain the balance. (Plate 97) This will not only improve the balance but also prepare you for the other Śīrṣāsana poses described later.

5. As to the position of the trunk, the dorsal region should be pushed forward as well as up. The lumbar (waist) and pelvic regions should not be pushed forward, while the trunk from the shoulders to the pelvis should be kept perpendicular. If the pelvic area juts forward, it means that you are bearing the weight of the body not on the head alone but also on the elbows for you have not stretched the dorsal region (the chest) correctly. When viewed from the side, the body from the neck to the heels should appear straight.

6. As far as possible try and join the thighs, knees, ankles and toes. Stretch the legs fully, especially the back of the knees and thighs. If the legs swing back tighten the knees and the lower median portion of the abdomen above the pubes. This will keep the legs perpendicular. Keep the toes pointing up. If the legs swing forward, stretch the dorsal region and push the pelvic area slightly back until it is in line with the shoulders. The body will then feel light and the pose will be exhilarating.

7. While going up or holding the head stand the eyes should never become bloodshot. If they do, the pose is faulty.*

8. The time limit for Śīrṣāsana depends upon individual capacity and the time at one's disposal. One can hold it comfortably from 10 to 15 minutes. A beginner can do it for 2 minutes and go up to 5 minutes. It is always difficult for a beginner to balance for one minute, but once he succeeds he can be sure that from then on he will be able to master Śīrṣāsana soon.

9. While going up or coming down, move both legs together, inch by inch. All the movements should be done with exhalation. Inhale while waiting in a position. The effect of going down and coming up straight without bending the legs at the knees is that harmonious slow movement is gained and the flow of blood to the head is controlled. The face does not flush from jerky and fast movements, as the flow of blood to the waist and the legs is also controlled.



96

---

* I have taught this pose to a lady of 65 who was suffering from glaucoma. Now she finds the eyes are completely rested and the pain in them is much lessened. Medical examination revealed that the tension in the eyeballs had decreased. I am mentioning this to prove the value of the correct head stand.



97

Then there is no danger of losing balance from giddiness or numbness of the feet when one stands up immediately after the head balance. In course of time the whole movement of going up, staying and coming down should become as effortless as possible. In a perfect Śīrṣāsana your body feels completely stretched and at the same time you experience a feeling of complete relaxation.

10. It is always safe to perfect Sarvāngāsana (Plate 102) first before attempting Śīrṣāsana. If the standing poses described earlier (Plates 1 to 18) and the various movements of Sarvangāsana and Halāsana (Plates 108 to 125) are mastered first, Śīrṣāsana will come without much effort. If these elementary āsanas have not been mastered, the period taken to learn Śīrṣāsana will be longer.

11. After one has learnt to balance in Śīrṣāsana, however, it is preferable to perform Śīrṣāsana first before practising any other āsana. This is because one cannot balance or hold the head stand if the body is exhausted by doing other poses or if the breathing becomes fast and shaky. Once the body is tired or the breathing is not free and easy, the body will shake and it will be difficult to maintain the balance. It is always better to do Śīrṣāsana first when one is fresh.

12. Śīrṣāsana should always be followed by Sarvāngāsana and its cycle. It has been observed that people who devote themselves to Śīrṣāsana alone without doing the Sarvāngāsana poses are apt to lose their temper over trifling things and become irritated quickly. The practice of Sarvāngāsana coupled with Śīrṣāsana checks this trait. If Sarvāngāsana is the Mother, then Śīrṣāsana may be regarded as the Father of all āsanas. And just as both parents are necessary for peace and harmony in a home, so the practice of both these āsanas is essential to keep the body healthy and the mind tranquil and peaceful.

EFFECTS OF ŚĪRṢĀSANA

The ancient books have called Śīrṣāsana the king of all āsanas and the reasons are not hard to find. When we are born, normally the head comes out first and then the limbs. The skull encases the brain, which controls the nervous system and the organs of sense. The brain is the seat of intelligence, knowledge, discrimination, wisdom and power. It is the seat of Brahman, the soul. A country cannot prosper without a proper king or constitutional head to guide it; so also the human body cannot prosper without a healthy brain.

The *Bhagavad-Gītā* says: 'Harmony (sattva), mobility (rajas), inertia (tamas), such are the qualities, matter-born; they bind fast, O great armed one (Arjuna), the indestructible dweller in the body.' (Fourteenth Discourse, verse 5) All these qualities stem from the brain, and sometimes one quality prevails and sometimes the others. The head is the centre of sattvic qualities which control discrimination; the trunk of Rājasic qualities which control passion, emotion and actions; and the region below the diaphragm of tāmasic qualities which control sensual pleasures like the enjoyment of food and drink, and the thrills and pleasures of sex.

Regular practice of Śīrṣāsana makes healthy pure blood flow through the brain cells. This rejuvenates them so that thinking power increases and thoughts become clearer. The āsana is a tonic for people whose brains tire quickly. It ensures a proper blood supply to the pituitary and pineal glands in the brain. Our growth, health and vitality depend on the proper functioning of these two glands.

People suffering from loss of sleep, memory and vitality have recovered by the regular and correct practice of this āsana and have become fountains of energy. The lungs gain the power to resist any climate and stand up to any work, which relieves one from colds, coughs, tonsillitis, halitosis (foul breath) and palpitations. It keeps the body warm. Coupled with Sarvāngāsana movements (Plates 108 to 125), it is a boon to people suffering from constipation. Regular practice of Śīrṣāsana will show marked improvement in the haemoglobin content of the blood.

It is not advisable to start with Śīrṣāsana and Sarvāngāsana when one suffers from high or low blood pressure.

Regular and precise practice of Śīrṣāsana develops the body, disciplines the mind and widens the horizons of the spirit. One becomes balanced and self-reliant in pain and pleasure, loss and gain, shame and fame and defeat and victory.



98

40| *Sālamba Sarvāngāsana I*

TWO*

Ālamba means a prop, a support and sa together with or accompanied by. Sālamba, therefore means supported or propped up. Sarvānga (Sarva = all, whole, entire, complete; anga = limb or body) means the entire body or all the limbs. In this pose the whole body benefits from the exercise, hence the name.

TECHNIQUE FOR BEGINNERS

1. Lie flat on the back of the carpet keeping the legs stretched out, tightened at the knees. Place the hands by the side of the legs, palms down. (Plate 98) Take a few deep breaths.

2. Exhale, bend the knees and move the legs towards the stomach till the thighs press it. (Plate 99) Take two breaths.

3. Raise the hips from the floor with an exhalation and rest the hands on them by bending the arms at the elbows. (Plate 100) Take two breaths.

4. Exhale, raise the trunk up perpendicularly supported by the hands until the chest touches the chin. (Plate 101)



99

5. Only the back of the head and the neck, the shoulders and the backs of the arms up to the elbows should rest on the floor. Place the hands in the middle of the spine as in Plate 101. Take two breaths.

6. Exhale and stretch the legs straight with the toes pointing up. (Front view: Plate 102. Back view: Plate 103)

7. Stay in this position for 5 minutes with even breathing.

8. Exhale, gradually slide down, release the hands, lie flat and relax.

9. If you cannot do the āsana without support use a stool and follow the technique. See Plate 104.



100



101



102



103



104

TECHNIQUE FOR ADVANCED PUPILS

1. Lie flat on the back on the carpet.

2. Keep the legs stretched out, tightened at the knees. Place the hands by the side of the legs, palms down. (Plate 98)

3. Take a few deep breaths. Exhale slowly and at the same time raise both legs together and bring them at a right angle to the body. (Plate 105) Remain in this position and inhale, keeping the legs steady.

4. Exhale, again raise the legs further up by lifting the hips and back from the floor, pressing the palms gently against the floor as in Plate 106.

5. When the whole trunk is raised off the ground, bend the elbows and place the palms on the back of the ribs, resting the shoulders well on the floor.

6. Utilize the palm pressure and raise the trunk and legs up vertically as in Plate 107 so that the breast-bone presses the chin to form a firm chinlock. The contraction of the throat and pressing the chin against the breast-bone to form a firm chinlock is known as Jālandhara Bandha. Remember to bring the chest forward to touch the chin and not to bring the chin towards the chest. If the latter is done, the spine is not stretched completely and the full effect of this āsana will not be felt.

7. Only the back of the head and neck, the shoulders and the upper portion of the arms up to the elbows should rest well on the floor. The remainder of the body should be in one straight line, perpendicular to the floor. This is the final position. (Side view: Plate 108)

8. In the beginning, there is a tendency for the legs to swing out of the perpendicular. To correct this, tighten the back thigh muscles and stretch up vertically.



105

9. The elbows should not be placed wider than the shoulders. Try and stretch the shoulders away from the neck and also to bring the elbows close to each other. If the elbows are widened, the trunk cannot be pulled up properly and the pose will look imperfect. Also see that the neck is straight with the centre of the chin resting on the sternum. In the beginning, the neck moves sideways and if this is not corrected, it will cause pain and injure the neck.



106

10. Remain in this pose for not less than 5 minutes. Gradually increase the time to 15 minutes; this will have no ill effects.

11. Release the hands, slide to the floor, lie flat and relax.

As the weight of the whole body is borne on the neck and shoulders and as the hands are used to support the weight this āsana is called Sālamba Sarvāngāsana. In Sarvāngāsana there are various movements which can be done in addition to the basic pose described above.



107



108

EFFECTS

The importance of Sarvāngāsana cannot be over-emphasized. It is one of the greatest boons conferred on humanity by our ancient sages. Sarvāngāsana is the mother of āsanas. As a mother strives for harmony and happiness in the home, so this āsana strives for the harmony and happiness of the human system. It is a panacea for most common ailments. There are several endocrine organs or ductless glands in the human system which bathe in blood, absorb the nutriments from the blood and secrete hormones for the proper functioning of a balanced and well developed body and brain. If the glands fail to function properly, the hormones are not produced as they should be and the body starts to deteriorate. Amazingly enough many of the āsanas have a direct effect on the glands and help them to function properly. Sarvāngāsana does this for the thyroid and parathyroid glands which are situated in the neck region, since due to the firm chinlock their blood supply is increased. Further, since the body is inverted the venous blood flows to the heart without any strain by force of gravity. Healthy blood is allowed to circulate around the neck and chest. As a result, persons suffering from breathlessness, palpitation, asthma, bronchitis and throat ailments get relief. As the head remains firm in this inverted position, and the supply of the blood to it is regulated by the firm chinlock, the nerves are soothed and headaches – even chronic ones – disappear. Continued practice of this āsana eradicates common colds and other nasal disturbances. Due to the soothing effect of the pose on the nerves, those suffering from hypertension, irritation, shortness of temper, nervous breakdown and insomnia are relieved. The change in bodily gravity also affects the abdominal organs so that the bowels move freely and constipation vanishes. As a result the system is freed from toxins and one feels full of energy. The āsana is recommended for urinary disorders and uterine displacement, menstrual trouble, piles and hernia. It also helps to relieve epilepsy, low vitality and anaemia. It is no over-statement to say that if a person regularly practises Sarvāngāsana he will feel new vigour and strength, and will be happy and confident. New life will flow into him, his mind will be at peace and he will feel the joy of life. After a long illness, the practice of this āsana regularly twice a day brings back lost vitality. The Sarvāngāsana cycle activates the abdominal organs and relieves people suffering from stomach and intestinal ulcers, severe pains in the abdomen and colitis.

People suffering from high blood pressure should not attempt Sālamba Sarvāngāsana unless they do Halāsana (Plate 113) first and can stay in it for not less than 3 minutes.

Do not perform Sarvāngāsana during menstruation.

Halāsana is described on the following pages.

THE SARVĀNGĀSANA CYCLE

These various movements can be practised at one stretch after staying in Sarvāngāsana (Plate 102) from 5 to 10 minutes or more according to capacity; do them for 20 to 30 seconds at a time each side except Halāsana, which should last from 3 to 5 minutes at a stretch.

41| *Halāsana*

FOUR*

Hala means a plough, the shape of which this posture resembles, hence the name. It is a part of Sarvāngāsana I and a continuation thereof.

TECHNIQUE

1. Do Sālamba Sarvāngāsana (Plate 103) with a firm chinlock.

2. Release the chinlock, lower the trunk slightly, moving the arms and legs over the head and resting the toes on the floor. (Plate 109)

3. Tighten the knees by pulling up the hamstring muscles at the back of the thighs and raise the trunk. (Plate 110)

4. Stretch the arms on the floor in the direction opposite to that of the legs. (Plate 111)



109



110



111

5. Interlock the fingers (Plate 112) and turn the wrists so that the thumbs rest on the floor. (Plate 113) Stretch the palms along with the fingers, tighten the arms at the elbows and pull them from the shoulders.

6. The legs and the hands are stretched in opposite directions and this stretches the spine completely.

7. While interlocking the fingers, it is advisable to change the interlock. Suppose that the right thumb touches the floor first, maintain the position for a minute. Then release the grip and bring the left thumb first on the floor, follow the interlock, finger by finger, and stretch out the arms for the same length of time. This will lead to harmonious development and elasticity of both the shoulders, elbows and wrists.

8. In the beginning interlocking will be difficult. By gradual practice of the above mentioned positions, you will interlock the fingers easily.

9. In the beginning it is also difficult to keep the toes firmly on the floor behind the head. If you lengthen the timing and stretch of Sarvāngāsana (Plate 102) before going into Halāsana, the toes will remain longer on the floor.

10. Remain in the attainable pose from one to five minutes with normal breathing.

11. Release the hands. Raise the legs up to Sarvāngāsana and gradually slide down to the floor. Lie flat on the back and relax.



112



113

EFFECTS

The effect of Halāsana is the same as that of Sarvāngāsana. (Plate 102) In addition, the abdominal organs are rejuvenated due to contraction. The spine receives an extra supply of blood due to the forward bend and this helps to relieve backache. Cramps in the hands are cured by interlocking and stretching the palms and fingers. People suffering from stiff shoulders and elbows, lumbago and arthritis of the back find relief in this āsana. Griping pain in the stomach due to wind is also relieved and lightness is felt immediately.

The pose is good for people with a tendency for high blood pressure. If they perform Halāsana first and then Sarvāngāsana, they will not feel the rush of blood or the sensation of fullness in the head.

Halāsana is a preparatory pose to Paschimottānāsana. (Plate 81) If one improves in Halāsana, the resulting mobility of the back will enable one to perform Paschimottānāsana well.

NOTE

For persons suffering from high blood pressure the following technique is recommended for doing Halāsana before they attempt Sālamba Sarvāngāsana.

1. Lie flat on the back on the floor.

2. Exhale, slowly raise the legs to a perpendicular position and stay there breathing normally for about 10 seconds.

3. Exhale, bring the legs over and beyond the head and touch the toes on the floor. Keep the toes on the floor and the legs stiff at the knees.

4. If you have difficulty in keeping the toes on the floor, then place a chair or a stool behind the head and rest the toes on it.

5. If the breathing becomes heavy or fast do not rest the toes on the floor, but on a stool or chair. Then fullness or pressure is not felt in the head.

6. Extend the arms over the head, keep them on the floor and stay in this position with normal breathing for 3 minutes.

7. Throughout the āsana, gaze at the tip of the nose with the eyes shut.

42| *Karṇapīḍāsana*

ONE*

Karṇa means the ear. Pīḍa means pain, discomfort or pressure. This is a variant of Halāsana and can be done along with it.

TECHNIQUE

1. Do Halāsana (Plate 113) and after completing the time limit for that pose, flex the knees and rest the right knee by the side of the right ear and the left knee by the side of the left.

2. Both knees should rest on the floor, pressing the ears.

3. Keep the toes stretched out and join the heels and toes. Rest the hands either on the back of the ribs (Plate 114a), or interlock the fingers and stretch out the arms (Plate 114b).

4. Remain in this position for half a minute or a minute with normal breathing.

EFFECTS

This āsana rests the trunk, heart and legs. The spine is stretched more while bending the knees, and this helps the circulation of blood round the waistline.



114A



114B

43| *Supta Koṇāsana*

TWO*

Supta means lying down and koṇa an angle. It is a variation of Halāsana in which the legs are spread apart.

TECHNIQUE

1. From Karṇapīdāsana (Plates 114a, 114b), stretch the legs straight and spread the legs as far apart as you can.

2. Pull the trunk up and tighten the knees.

3. Hold the right toe with the right hand and the left toe with the left one. Keep the heels up. After gripping the toes, move the dorsal region of the spine still further up and extend the hamstring muscles. (Plate 115).

4. Stay in the pose from 20 to 30 seconds with normal breathing.

EFFECTS

This pose tones the legs and helps to contract the abdominal organs.



115

44| *Pārśva Halāsana*

FOUR*

In Halāsana (Plate 114) both the legs rest behind the head. In this pose they rest sideways on one side of and in line with the head. This is the lateral plough pose.

TECHNIQUE

1. Do Supta Koṇāsana (Plate 115) and come back to Halāsana.

2. Place the palms on the back of the ribs.

3. Move both the legs as far as you can to the left.

4. Tighten both knees, raise the trunk up with the help of the palms and stretch the legs. (Plate 116)

5. Remain in this position for half a minute with normal breathing.

6. Exhale, move the legs to the right until they are in line with the head and hold the pose for half a minute. Do not disturb the position of the chest and trunk when the legs are moved. The chest and trunk should remain as in Sarvāngāsana or Halāsana.



116

EFFECTS

In this āsana, the spine moves laterally and becomes more elastic. The colon, which is inverted during the movements, is exercised properly and elimination will be complete. People suffering from acute or chronic constipation which is the mother of several diseases derive great benefit from this āsana. If rubbish is dumped outside our house we feel sick. How much more so when waste matter which creates toxins is allowed to accumulate in our own system? If this waste matter is not eliminated, diseases will enter the body like thieves and rob us of health. If the bowels do not move freely, the mind becomes dull and one feels heavy and irritable. This āsana helps us keep the bowels free and thereby win the prize of health.

45| *Eka Pāda Sarvāngāsana*

FIVE*

Eka means one, single. Pāda means the foot. In this variation of Sarvāngāsana, one leg is on the floor in Halāsana, while the other is in a vertical position along with the trunk.

TECHNIQUE

1. Do Sālamba Sarvāngāsana I. (Plate 102)

2. Keep the left leg up in Sarvāngāsana. Exhale and move the right leg down to the floor to Halāsana. (Plate 117) It should remain stiff and straight and not bend at the knee. If it is not possible to touch the floor, lower the leg as far as possible.

3. While resting the right leg on the floor, the left knee should be kept taut and not allowed to tilt sideways. The left leg should be kept straight, facing the head.

4. Stay in the pose for 20 seconds maintaining normal breathing.

5. Exhale, lift the right leg back to Sarvāngāsana, and then move the left leg down to the floor in Halāsana, keeping the right leg vertically up and stiff. Lifting the leg from the floor back to Sarvāngāsana exercises the abdominal organs more than if one brings both legs down to Halāsana.

6. Stay on this side for the same length of time.

EFFECTS

This āsana tones the kidneys and the leg muscles.



117

46| *Pārśvaika Pāda Sarvāngāsana*

SIX*

Pārśva means the side. In Eka Pāda Sarvāngāsana (Plate 117) the lower leg rests behind the head, whereas here it rests sideways in line with the trunk.

TECHNIQUE

1. Perform Eka Pāda Sarvāngāsana on both sides as described above and come back to Sarvāngāsana.

2. Exhale, move the right leg down sideways to the floor until it is in line with the trunk. (Plate 118) Keep the right leg straight and stiff and do not bend it at the knee. If it is not possible to touch the floor, lower the leg as far as possible.

3. The left leg which is vertically up should be kept straight and not allowed to tilt to the right. The ribs should be lifted with the palms to expand the chest fully.

4. Remain in the pose for 20 seconds with normal breathing, exhale, and go back to Sarvāngāsana. Repeat with the other leg for the same length of time and return to Sarvāngāsana.

EFFECTS

This pose relieves constipation and also tones the kidneys.



118

47| *Setu Bandha Sarvāṅgāsana (also called Uttāna Mayūrāsana)*

TEN*

Setu means a bridge and Setu Bandha means the formation or construction of a bridge. In this position, the body is arched and supported on the shoulders, soles and heels. The arch is supported by the hands at the waist.

Ut means intense and tān means to stretch. This āsana resembles a stretched peacock (Mayūra), hence the name.

TECHNIQUE

1. Do Sālamba Sarvāṅgāsana. (Plate 102)

2. Rest the palms well on the back, raise the spine up, bend the knees (Plate 119) and throw the legs back over the wrists to the floor. (Plate 120) Stretch out the legs and keep them together. (Plate 121)

3. The whole body forms a bridge, the weight of which is borne by the elbows and the wrists. The only parts of the body in contact with the ground will be the back of the head and neck, the shoulders, the elbows and the feet. Stay in the pose from half a minute to a minute with normal breathing.

4. It is possible to lessen the pressure on the elbows and the wrists by stretching the spine towards the neck, keeping the heels firmly on the ground.


119


120


121

EFFECTS

This āsana gives the spine a backward movement and removes the strain on the neck caused by the other various movements of Sarvāngāsana.

A healthy and flexible spine indicates a healthy nervous system. If the nerves are healthy a man is sound in mind and body.

48| *Ūrdhva Padmāsana in Sarvāngāsana*

FOUR*

Ūrdhva means above, high. Padma means a lotus. In this Sarvāngāsana variation, the legs, instead of being kept straight up, are bent at the knees and crossed so that the right foot rests on the left thigh and the left foot on the right thigh as in the lotus pose. (Plate 53)

TECHNIQUE

1. From Sālamba Sarvāngāsana, bend the legs at the knees and cross them. First place the right foot over the left thigh, and then the left foot over the right thigh.

2. Stretch the crossed legs vertically up, move the knees closer to each other and the legs as far back as possible from the pelvic region. (Plate 122)

3. Stay in this pose from 20 to 30 seconds with deep and even breathing.



122

4. Uncross the legs, return to Sālamba Sarvāngāsana and repeat the pose by first placing the left foot over the right thigh and then the right foot over the left thigh. Stay for an equal length of time in all these positions as in the earlier ones.

49| *Pinḍāsana in Sarvāngāsana*

FIVE*

Pinḍa means embryo or foetus. In this variation of Sarvāngāsana which is a continuation of the earlier posture, the bent crossed legs are brought down until they rest on the head. The posture resembles that of an embryo in the womb, hence the name.

TECHNIQUE

1. From Ūrdhva Padmāsana in Sarvāngāsana (Plate 122), exhale, bend and lower the crossed legs from the hips towards the head.

2. Rest the legs over the head. (Plate 123)

3. Remain in this position from 20 to 30 seconds with normal breathing and go back to Ūrdhva Padmāsana in Sarvāngāsana.



123

50| *Pārśva Piṇḍāsana in Sarvāṅgāsana*

EIGHT*

Pārśva means the side or flank. In this Piṇḍāsana variation of the earlier pose, both the bent knees are moved sideways and placed on the floor on the same side of the trunk. This is the lateral embryo pose in Sarvāṅgāsana.

TECHNIQUE

1. After staying in Pindāsana (Plate 123) turn the hips sideways to the right, exhale and lower both knees to the floor. The left knee should be by the side of the right ear. (Plate 124)

2. The left shoulder will be raised off the floor in the beginning. Push the shoulder against the floor and press the left hand firmly against the back. If this is not done, you will lose balance and roll over to one side.

3. Due to the lateral twist, breathing will be fast and difficult as the diaphragm is pressed in this position.

4. The knee near the ear will not rest on the floor to start with, but only after long practice.

5. Stay in this position for 20 to 30 seconds, with normal breathing.

6. Exhale, come up from the right side and move the crossed legs over to the left, so that the left foot will be near the left ear. (Plate 125) Stay here also for the same length of time.



124



125

7. Go back to Ūrdhva Padmāsana. (Plate 122) Release the lotus pose by uncrossing the legs and return to Sālamba Sarvāngāsana.

8. Now change the position of the crossed legs. Cross the legs again by putting the left foot over the right thigh first and then the right foot over the left thigh instead of the other way as done earlier.

9. Repeat the movements again on both the sides as described earlier.

EFFECTS OF ŪRDHVA PADMĀSANA AND PĀRŚVA PINḌĀSANA MOVEMENTS IN SARVĀNGĀSANA

The change of crossing the legs brings equal pressure on both sides of the abdomen and colon and relieves constipation. For those suffering from chronic constipation a longer stay in Pārśva Pinḍāsana is recommended, and one minute on each side will prove most efficacious. Griping pain in the stomach is relieved by these poses.

Persons with extremely flexible knees, can easily perform these positions. It is, however, difficult for many people to cross the legs in Padmāsana. For them a longer stay in Pārśva Halāsana (Plate 116) – (there also the spine and trunk get a lateral twist but the legs remain straight) – is recommended.

In all these positions breathing at first will be fast and laboured. Try to maintain normal breathing.

NOTE

The spine is given the forward, lateral and backward movements in these variations of Sarvāngāsana. In Halāsana, Eka Pāda Sarvāngāsana, Karṇa Pīdāsana and Pinḍāsana the spine moves in the forward direction. In Pārśvaika Pāda Sarvānga, Pārśva Halāsana and Pārśva Pinḍāsana the spine moves laterally. In Setu Bandha it is given a backward movement. These movements tone the spine on all sides and keep it healthy.

It is related that in the Krita Age (the first Age of the Universe) a host of Dānavās (giants and demons) became invincible in battle under the leadership of Vṛtra and scattered the Devas (or Gods) in all directions. Realizing that they could not regain their power until Vṛtra was destroyed, the gods appeared before their Grandsire, Brahmā, the creator. Brahmā instructed them to consult Viṣṇu who asked them to obtain the bones of a sage called Dadhīcha, from which to make a demon-slaying weapon. The gods appeared before the sage and begged the boon according to Viṣṇu's advice. The sage renounced his body for the benefit of the gods. From the spine of Dadhīcha was fashioned Vajra, the thunderbolt, which Indra the king of the gods hurled and slew Vṛtra.

The story is symbolical. The Dānavās represent the tāmasic qualities in men and diseases. The Devas represent health, harmony and peace. To destroy the tāmasic qualities and the diseases due to them and to enjoy health and happiness, we have to make our spines strong as a thunderbolt like the spine of Dadhīcha. Then we shall enjoy health, harmony and happiness in abundance.

51| *Jaṭara Parivartanāsana*

FIVE*

Jaṭara means the stomach, the belly. Parivartana means turning or rolling about, turning round.

TECHNIQUE

1. Lie flat on the back on the floor. (Plate 98)

2. Exhale, raise both legs together until they are perpendicular to the floor. They should remain poker stiff, so do not bend them at the knees. (Plate 105)

3. Stretch out both arms sideways in line with the shoulders, so that the body resembles a cross.

4. Remain in this position for a few breaths. Then exhale, and move both the legs sideways (Plate 126) down towards the floor to the left until the toes of the left foot almost touch the finger-tips of the outstretched left hand. (Plate 127) Try and keep the back well on the floor. In the initial stages, the right shoulder will be lifted off the floor. To prevent this ask a friend to press it down, or catch hold of a heavy piece of furniture with the right hand when the legs are turned sideways to the left.



126



127

5. Both legs should go down together, the knees being kept tight throughout. As far as possible keep the lumbar portion of the back on the floor and turn the legs only from the hips. When the legs are near the outstretched left hand, move the abdomen to the right.

6. Stay in the pose for about 20 seconds, keeping the legs stiff throughout. Then move the still stiffened legs slowly back to the perpendicular with an exhalation.

7. Remain with the legs perpendicular for a few breaths and then repeat the movements by lowering the legs to the right and turning the abdomen to the left. (Plate 128) Stay here also for the same length of time and with an exhalation, come back to the perpendicular legs position and then gently lower the legs to the floor (Plate 98) and relax.



128

EFFECTS

This āsana is good for reducing excess fat. It tones and eradicates sluggishness of the liver, spleen and pancreas. It also cures gastritis and strengthens the intestines. By its regular practice all the abdominal organs are kept in trim. It helps to relieve sprains and catches in the lower back and the hip region.

52| *Supta Pādānguṣṭhāsana*

THIRTEEN*

Supta means lying down. Pāda is the foot. Anguṣṭha means the big toe. Hence the name.

TECHNIQUE

1. Lie flat on the back, stretch both legs and keep the knees tight. (Plate 98)

2. Inhale, raise the left leg from the floor until it is perpendicular. Keep the right leg stretched fully on the floor and rest the right hand on the right thigh.

3. Raise the left arm and catch the left big toe between the thumb and the fore and middle fingers. (Plate 129) Take 3 or 4 deep breaths.

4. Exhale, raise the head and trunk from the floor, bend the left arm at the elbow and pull the left leg towards the head without bending it at the knee. Pull the leg down, lift the head and trunk up together and rest the chin on the left knee. (Plate 130) Stay in this position for about 20 seconds, keeping the right leg fully stretched straight along the floor while breathing normally.

5. Inhale, move the head and trunk back to the floor and the left leg back to the perpendicular. (Plate 129) This completes the first movement.

6. Exhale, release the toe grip, rest the left leg on the floor beside the right one and keep the left hand on the left thigh.

7. Take a few deep inhalations and then repeat on the right, substituting the word 'left' for the word 'right'.

EFFECTS

The legs will develop properly by the practice of this āsana. Persons suffering from sciatica and paralysis of the legs will derive great benefit from it. The blood is made to circulate in the legs and hips where the nerves are rejuvenated. The pose removes stiffness in the hip joints and prevents hernia. It can be practised by both men and women.



129



130



131



132

53| *Bharadvājāsana*

ONE*

Bharadvāja was the father of Droṇa, the military preceptor of the Kauravas and Pāṇḍavas, who fought the great war described in the Mahābhārata. This āsana is dedicated to Bharadvāja.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. (Plate 35)

2. Flex the knees, move the legs back and bring both feet to the right side beside the hip.

3. Rest the buttocks on the floor, turn the trunk about 45 degrees to the left, straighten the right arm and place the right hand on the outer side of the left thigh near the left knee. Insert the right hand underneath the left knee, the palm touching the floor.

4. Exhale, turn the left arm from the shoulder behind the back, bend the left elbow and with the left hand clasp the right upper arm above the right elbow.

5. Turn the neck to the right and gaze over the right shoulder. (Plates 131 and 132)

6. Hold the position for half a minute with deep breathing.

7. Loosen the hand grip, straighten the legs and repeat the pose on the other side. Here, bring both the feet beside the left hip, turn the trunk to the right, straighten the left arm, place the left palm underneath the right knee and catch the left upper arm near the elbow with the right hand from behind the back. Stay there for an equal length of time.

EFFECTS

This simple āsana works on the dorsal and lumbar regions of the spine. People with very stiff backs find the other lateral twisting positions extremely difficult. This pose helps to make the back supple. People with arthritis will find it very beneficial.

54| *Marīchyāsana II*

TEN*

This is one of the sitting lateral twisting postures.

TECHNIQUE

1. Sit on the floor with the legs stretched straight in front. (Plate 35)

2. Bend the left knee, place the sole and heel of the left foot flat on the floor. The shin of the left leg should be perpendicular to the floor and the calf should touch the thigh. Place the left heel near the perineum. The inner side of the left foot should touch the inner side of the outstretched right thigh.

3. With an exhalation, turn the spine about 90 degrees to the left, so that the chest goes beyond the bent left thigh and bring the right arm over the left thigh. (Plate 133)

4. Place the right shoulder beyond the left knee and stretch the right arm out forwards by turning the spine still more to the left and stretching the region at the back of the right floating ribs. (Plate 134) Take two breaths.

5. With an exhalation, twist the right arm round the left knee, flex the right elbow and place the right wrist at the back of the waist. Inhale and hold the pose.

6. Exhale deeply and turn the left arm from the shoulder behind the back. Either clasp the left hand behind the back with the right hand or vice versa. (Plates 135 and 136) In the beginning, one finds it difficult to twist the trunk sideways, but with practice, the armpit touches the bent knee. After one has twisted the arm round the knee, one also finds it difficult to clasp the fingers of one hand with the other. Gradually one learns to clasp the fingers, then the palm and lastly to hold the hand at the wrist behind the back.


133


134

7. The right arm should lock the left bent knee tightly. There should be no space between the right armpit and the bent left knee.

8. After clasping the hands at the back, turn the spine still more to the left by tugging at the clasped hands.

9. The whole of the outstretched right leg should remain straight and securely on the floor, but you will not be able to achieve this to start with. Tighten the muscles of the outstretched thigh so that the knee-cap is pulled up towards the thigh and also tighten the muscles of the calf of the outstretched leg. Then the leg will remain firm and extend on the floor.



135



136

10. Stay in this position from half a minute to a minute with normal breathing. The neck may be turned either way to gaze at the toes of the extended leg on the floor or to look over the shoulder.

11. Unclasp the hands at the back and turn the trunk back to its original position. Lower the bent leg and extend it fully on the floor.

12. Then repeat the pose on the other side. This time bend the right knee and place the right foot firmly on the floor so that the right heel touches the perineum and the inner side of the right foot touches the outstretched left thigh. Turn the trunk about 90 degrees to the right so that the left armpit touches the bent right knee. With an exhalation, twist the left arm round the right knee and bring the left hand to the back of the waist. Then throw the right arm behind the back from the shoulder and flexing the right elbow, bring the right hand to the left hand and clasp them. Turn still more to the right and gaze at either the toes of the outstretched left leg or over the right shoulder. Stay on this side also for the same length of time. Unclasp the hands, turn the trunk back to normal, stretch the right leg on the floor and relax.

EFFECTS

By the regular practice of this āsana, splitting backaches, lumbago and pains in the hips disappear rapidly. The liver and the spleen are contracted and so are toned and cease to be sluggish. The muscles of the neck gain power. Sprains in the shoulder and displacement of the shoulder joints are relieved and the shoulder movements become free. The intestines also benefit from this āsana. Its effects will be less on lean persons, for whom there are better poses described later. It also helps to reduce the size of the abdomen.

55| *Ardha Matsyendrāsana*

EIGHT*

Ardha means half. In the Haṭha Yoga Pradīpikā, *Matsyendra is mentioned as one of the founders of Haṭha Vidyā. It is related that once Lord Śiva went to a lonely island and explained to his consort Pārvati the mysteries of Yoga. A fish near the shore heard everything with concentration and remained motionless while listening. Śiva, realizing that the fish had learnt Yoga, sprinkled water upon it, and immediately the fish gained divine form and became Matsyendra (Lord of the Fishes) and thereafter spread the knowledge of Yoga.*

TECHNIQUE

1. Sit on the floor, with the legs stretched straight in front. (Plate 35)

2. Bend the left knee and join the thigh and calf; raise the seat from the floor, place the left foot under the buttocks and sit on the left foot so that the left heel rests under the left buttock. The foot used as the seat should be kept horizontal on the floor, the outer side of the ankle and the little toe of the foot resting on the ground. If the foot is not so placed, it will be impossible to sit on it. Balance securely in this position.

3. Then bend the right knee and lifting the right leg from the floor, place it by the outer side of the left thigh so that the outer side of the right ankle touches the outer side of the left thigh on the floor. Balance in this position, keeping the right shin perpendicular to the floor. (Plate 137)

4. Turn the trunk 90 degrees to the right until the left armpit touches the outer side of the right thigh. Bring the armpit over the right knee. (Plate 138) Exhale, stretch the left arm from the shoulder and twist it round the right knee. Bend the left elbow and move the left wrist to the back of the waist.



137



138

5. The left arm should lock the bent right knee tightly and there should be no space between the left armpit and the bent right knee. To achieve this, exhale and move the trunk forward. Stay in this position and take 2 breaths.

6. Now exhale deeply and swing back the right arm from the shoulder, bend the right elbow, move the right hand behind the waist and either clasp it with the left hand or vice versa. At first you will be able to catch a finger or two. With practice it will be possible to catch the palms and then the wrists behind the back.

7. The neck may be turned to the left and the gaze directed over the left shoulder (Plate 139), or to the right, and the gaze fixed at the centre of the eyebrows. (Plate 140) The spinal twist will be greater if the neck is turned to the left than when to the right.

8. As the diaphragm is squeezed by the spinal twist, the breathing will at first become short and fast. Do not be nervous. After some practice the pose can be held from half a minute to a minute with normal breathing.

9. Release the hands, remove the right foot from the floor and straighten the right and then the left leg.

10. Repeat the pose on the other side and hold it for the same length of time. Here, bend the right leg and sit on the right foot so that the right heel is under the right buttock. Place the left leg over the right leg and rest the left foot on the floor so that the outer side of the left ankle touches the outer side of the right thigh on the floor. Turn the trunk 90 degrees to the left, placing the right armpit over the left knee and twist the right arm round the left knee. Flex the right elbow and move the right hand behind the waist. Hold the pose and take 2 breaths. Again exhale completely and swing the left arm back from the shoulder, bend the left elbow and clasp the hands behind the back at the wrist. Then release and relax.

11. In the beginning it may not be possible to twist either arm round the opposite knee. In that case try and hold the opposite foot, keeping the arm straight at the elbow. It also takes time to clasp the hands behind the back. Gradually, the backward stretch of the arms will increase, and one will be able to catch at first the fingers, next the palms, then the wrist and as the pose is mastered even the forearms above the wrists. Beginners who find it difficult to sit on the foot can sit on the floor.

EFFECTS

By the practice of this āsana, one derives the benefits mentioned under Marīchyāsana III. (Posture 54 and Plate 135) But here as the range of movement is more intensified, the effects will also be greater. In Marīchyāsana III the upper part of the abdomen is squeezed. Here the lower part of the abdomen has the benefit of the exercise. The prostate and bladder are not enlarged if one practises regularly.


139


140

56| Ūrdhva Dhanurāsana

SEVEN*

Ūrdhva means upwards. Dhanu means a bow. In this posture the body is arched back and supported on the palms and soles.

TECHNIQUE

1. Lie flat on the back on the floor. (Plate 48)

2. Bend and raise the elbows over the head, and place the palms under the shoulders. The distance between the palms should not be wider than the shoulders and the fingers should point towards the feet.

3. Bend and raise the knees, then bring the feet nearer until they touch the hips. (Plate 141)

4. Exhale, raise the trunk and rest the crown of the head on the floor. (Plate 142) Take two breaths.

5. Now exhale, lift the trunk and head and arch the back so that its weight is taken on the palms and the soles. (Plate 143)

6. Stretch the arms from the shoulders until the elbows are straightened, at the same time pulling the thigh muscles up. (Plate 144)

7. To get a better stretch, exhale and pull the thigh muscles still higher by lifting the heels off the floor. (Plate 145) Extend the chest, stretch up the sacral region of the spine until the abdomen is taut as a drum and then lower the heels to the floor, maintaining the stretch of the spine.

8. Remain in this position from half a *minute* to a *minute*, with normal breathing.

9. With an exhalation, lower the body to the floor by bending the knees and elbows.



141



142



143



144

EFFECTS

This āsana is the beginning of the advanced and difficult back-bending poses. It tones the spine by stretching it fully and keeps the body alert and supple. The back feels strong and full of life. It strengthens the arms and wrists and has a very soothing effect on the head. It gives one great vitality, energy and a feeling of lightness.



145

57| *Śavāsana (also called Mṛtāsana)*

Śava or Mṛta means a corpse. In this āsana the object is to imitate a corpse. Once life has departed, the body remains still and no movements are possible. By remaining motionless for some time and keeping the mind still while you are fully conscious, you learn to relax. This conscious relaxation invigorates and refreshes both body and mind. But it is much harder to keep the mind than the body still. Therefore, this apparently easy posture is one of the most difficult to master.

TECHNIQUE

1. Lie flat on the back full length like a corpse. Keep the hands a little away from the thighs, with the palms up.

2. Close the eyes. If possible place a black cloth folded four times over the eyes. Keep the heels together and the toes apart.

3. To start with breathe deeply. Later the breathing should be fine and slow, with no jerky movements to disturb the spine or the body.

4. Concentrate on deep and fine exhalations, in which the nostrils do not feel the warmth of breath.

5. The lower jaw should hang loose and not be clenched. The tongue should not be disturbed, and even the pupils of the eyes should be kept completely passive.


146

6. Relax completely and breath out slowly.

7. If the mind wanders, pause without any strain after each slow exhalation.

8. Stay in the pose from 15 to 20 minutes.

9. One is apt to fall asleep in the beginning. Gradually, when the nerves become passive, one feels completely relaxed and refreshed.

When well refreshed one feels energy flow from the back of the head towards the heels and not the other way round. One also feels as if the body is elongated.

EFFECTS

Verse 32 of the First Chapter of the *Haṭha Yoga Pradīpikā* states: 'Lying upon one's back on the ground at full length like a corpse is called Śavāsana. This removes the fatigue caused by the other āsanas and induces calmness of mind.'

Mṛtāsana is thus described in verse 11 of the Second Chapter of the *Gheraṇḍa Saṁhitā*:

'Lying flat on the ground (on one's back) like a corpse is called Mṛtāsana. This posture destroys fatigue, and quiets the agitation of the mind.'

'The mind is the lord of the Indriyas (the organs of senses); the Praṇa (the Breath of Life) is the lord of the mind.' 'When the mind is absorbed it is called Mokṣa (final emancipation, liberation of the soul); when Prāṇa and Manas (the mind) have been absorbed, an undefinable joy ensues.'

Verses 29 and 30, chapter IV, Haṭha Yoga Pradīpikā.

To tame Prāṇa depends upon the nerves. Steady, smooth, fine and deep breathing without any jerky movements of the body soothes the nerves and calms the mind. The stresses of modern civilization are a strain on the nerves for which Śavāsana is the best antidote.

PART III

Prāṇāyāma

HINTS AND CAUTIONS

Read and digest thoroughly the following hints and cautions before attempting the prāṇāyāma techniques mentioned later.

QUALIFICATIONS FOR FITNESS

1. Just as post-graduate training depends upon the ability and discipline acquired in mastering the subject in which one graduated, so prāṇāyāma training demands mastery of āsanas and the strength and discipline arising therefrom.

2. The fitness of the aspirant for training and advancement in prāṇāyāma is to be gauged by an experienced Guru or teacher and his personal supervision is essential.

3. Pneumatic tools can cut through the hardest rock. In Prāṇāyāma the yogi uses his lungs as pneumatic tools. If they are not used properly, they destroy both the tool and the person using it. The same is true of prāṇāyāma.

CLEANLINESS AND FOOD

4. One does not enter a temple with a dirty body or mind. Before entering the temple of his own body, the yogi observes the rules of cleanliness.

5. Before starting prāṇāyāma practices the bowels should be evacuated and the bladder emptied. This leads to comfort in the bandhas.

6. Preferably prāṇāyāma should be practised on an empty stomach, but if this is difficult, a cup of milk, tea, coffee or cocoa may be taken. Allow at least six hours to elapse after a meal before practising prāṇāyāma.

7. Light food may be taken half an hour after finishing prāṇāyāma practices.

TIME AND PLACE

8. The best time for practice is in the early morning (preferably before sunrise) and after sunset. According to the *Haṭha Yoga Pradīpikā,* prāṇāyāma should be practised four times a day, in the early morning, noon, evening and midnight, with 80 cycles at a time (chapter II, verse 11). This is hardly possible in the fast modern age. What is therefore recommended is to practice at least 15 minutes a day, but the 80 cycles are for intensely devoted practitioners, and not for the average householder.

9. The best seasons in which to start the practice are spring and autumn when the climate is equable.

10. Prāṇāyāma should be done in a clean airy place, free from insects. Since noise creates restlessness practice during quiet hours.

11. Prāṇāyāma should be practised with determination and regularity at the same time and place and in the same posture. Variation is permissible only in the type of prāṇāyāma practised, that is to say, if Sūrya Bhedana Prāṇāyāma is done one day, Śitalī may be done the next day and Bhastrikā be done on the third day. Nāḍī Sodhana Prāṇāyāma, however, should be practised daily.

POSTURE

12. Breathing in prāṇāyāma practices is done through the nose only, except in Śitalī and Śitakāri.

13. Prāṇāyāma is best done sitting on the floor on a folded blanket. The postures suitable are Siddhāsana, Vīrāsana, Padmāsana and Baddhakoṇāsana. Any other sitting posture may be taken provided the back is kept absolutely erect from the base of the spine to the neck and perpendicular to the floor. Some types, however, may be done in a reclining position as detailed later.

14. During practice no strain should be felt in the facial muscles, eyes and ears, or in the neck muscles, shoulders, arms, thighs and feet. The thighs and arms should be relaxed deliberately since they are unconsciously tensed during prāṇāyāma.

15. Keep the tongue passive or saliva will accumulate in the mouth. If it does, swallow it before exhalation (rechaka) and not while holding the breath (kumbhaka).

16. During inhalation and retention the rib cage should expand both forwards and sideways, but the area below the shoulder-blades and armpits should only expand forwards.

17. To start with there will be perspiration and trembling which will disappear in course of time.

18. In all the prāṇāyāma practices done in a sitting posture, the head should hang down from the nape of the neck, the chin resting in the notch between the collar-bones on the top of the breast-bone. This chin-lock or Jālandhara Bandha should be used except where specifically stated in the techniques hereafter given.

19. Keep the eyes closed throughout as otherwise the mind will wander after outside objects and be distracted. The eyes, if kept open, will feel a burning sensation, and irritability.

20. No pressure should be felt inside the ear during the practice of prāṇāyāma.

21. The left arm is kept straight, the back of the wrist resting on the left knee. The forefinger is bent towards the thumb, its tip touching the tip of the thumb. This is the Jñāna Mudrā described later in the technique.

22. The right arm is bent at the elbow and the hand is kept on the nose to regulate the even flow of breath and to gauge its subtlety. This is felt through the tips of the ring and little fingers which control the left nostril and through the tip of the thumb which controls the right nostril. Details of the right hand position are discussed in the technique. In some methods of prāṇāyāma both the hands rest on the knees in the Jñāna Mudrā.

23. When a baby learns to walk by itself, the mother remains passive bodily, but alert mentally. In an emergency, as when the child stumbles, her body springs into action to save it from a fall. So also, in the practice of prāṇāyāma the brain is kept passive but alert. Whenever the organs of the body fail to work properly, the watchful brain sends messages of warning. The ear is told to listen for the proper sound of the breath (which is described below). The hand and nose are told to observe the sensitivity of the breath flowing through the nasal passages.

24. It may be asked that if the brain is required to send warnings to the senses, how can one concentrate on prāṇāyāma? A painter absorbed in his work notes various details like perspective and composition, the colour tones and shades, the foreground and background and the strokes of the paint-brush all at once. A musician playing a melody watches his finger movements and sound patterns, the tuning of the instrument and its pitch. Though the artist and the musician are both observing and correcting the details, they are concentrating on their work. So also the yogi observes details like time, posture and an even breath rhythm, and is alert and sensitive to the flow of prāṇa within him.

25. As a careful mother teaches her child to walk carefree, so the careful mind of the yogi teaches the senses to be carefree. By continued practice of prāṇāyāma the senses become free of obsession for the things they once pined for.

26. Each should measure his own capacity when doing prāṇāyāma and not exceed it. This may be gauged as follows: suppose one can with comfort inhale and exhale for 10 seconds each in rhythmic cycles for a given length of time, say 5 minutes. If there is any change in the rhythm in which the period of inhalation decreases, to say 7 or 8 seconds, one has reached one's capacity. To go beyond this point, strains the lungs unduly and brings in its wake a host of respiratory diseases.

27. Faulty practice puts undue stress on the lungs and diaphragm. The respiratory system suffers and the nervous system is adversely affected. The very foundation of a healthy body and sound mind is shaken by faulty practice of prāṇāyāma. Forceful and strained inhalation or exhalation is wrong.

28. Evenness of breathing leads to healthy nerves and so to evenness of mind and temper.

29. Āsanas should never be practised immediately after prāṇāyāma. If prāṇāyāma is done first, allow an hour to elapse before starting āsanas, for the nerves which are soothed in prāṇāyāma are liable to be ruffled by the bodily movement of the āsanas.

30. Prāṇāyāma, however, may be done not less than 15 minutes after mild practice of āsanas.

31. Strenuous āsanas cause fatigue. When exhausted do not practise prāṇāyāma in any sitting posture, as the back cannot stay erect, the body trembles and the mind becomes disturbed. Deep breathing as in Ujjāyī done in a reclining position relieves fatigue.

32. When deep, steady and long breathing cannot be maintained rhythmically, stop. Do not proceed further. The rhythm should be gauged from the nasal sound produced in inhalation ('ssssssa' which sounds like a leak in a cycle tube) and exhalation (the aspirate 'huuuuuuuum' sound). If the volume of the sound is reduced, stop.

33. Try to achieve an even ratio in inhalation (puraka) and exhalation (rechaka). For example, if one is for 5 seconds during a given continuous cycle, the other should be for the same time.

34. The Ujjāyī and Nāḍī Śodhana types of prāṇāyāma are the most beneficial ones which can be practised by pregnant women, preferably in Baddhakoṇāsana. During pregnancy, however, the breath should never be held without the guidance of an experienced teacher.

35. After completing any prāṇāyāma practice always lie down on the back like a corpse in Śavāsana (Plate 146) for at least 5 to 10 minutes in silence. The mind should be completely switched off and every limb and sense organ completely passive as if dead. Śavāsana after prāṇāyāma refreshes both the body and the mind.

KUMBHAKAS

36. Thorough mastery of inhalation (puraka) and exhalation (rechaka) is essential before any attempt is made to learn antara kumbhaka (retention following inhalation).

37. Bāhya kumbhaka (restraint following exhalation) should not be tried until antara kumbhaka has become natural.

38. During the practice of kumbhaka there is a tendency to draw in air as well as to tighten and loosen the diaphragm and abdominal organs for the sake of increasing the period of retention. This is unconscious and unintentional. Care should be taken to avoid it.

39. If it is found difficult to hold the breath (khumbaka) after each inhalation or exhalation, do some cycles of deep breathing and then practise kumbhakas. For instance, 3 cycles of deep breathing may be followed by one cycle of kumbhaka. Then there should be another 3 cycles of deep breathing followed by a second cycle of kumbhaka, and so on.

40. If the rhythm of inhalation or exhalation is disturbed by holding the breath, lessen the duration of kumbhaka.

41. Persons suffering from eye or ear trouble (like glaucoma and pus in the ear) should not attempt to hold the breath.

42. Sometimes constipation occurs in the initial stages following upon the introduction of kumbhaka. This is temporary and will disappear in due course.

43. The normal rate of breaths per minute is 15. This rate increases when the body is upset by indigestion, fever, cold and cough, or by emotions like fear, anger or lust. The normal rate of breathing is 21,600 breaths inhaled and exhaled every 24 hours. The yogi measures his span of life not by the number of days, but of breaths. Since breathing is lengthened in prāṇāyāma, its practice leads to longevity.

44. Continuous practice of prāṇāyāma will change the mental outlook of the practitioner and reduce considerably the craving of his senses for worldly pleasures like smoking, drinking and sexual indulgence.

45. In the practice of prāṇāyāma the senses are drawn inwards and in the silence of the kumbhaka the aspirant hears his inner voice calling: 'Look within! The source of all happiness is within!' This also prepares him for the next stage of yoga, pratyāhāra, which leads to freedom from the domination and tyranny of the senses.

46. Since the eyes are kept closed throughout the practice of prāṇāyāma, the passage of time is noted by the mental repetition (japa) of a sacred word or name. This repetition of the sacred words or names is the seed (bija) planted in the yogi's mind. This seed grows and makes him fit for dhyāna or concentration, the sixth stage of Yoga. Ultimately it produces the fruit of samādhi, where there is experience of full consciousness and supreme joy, where the yogi merges with the Maker of the Universe and feels what he can never express – yet cannot entirely conceal. Words fail to convey the experience adequately, for the mind cannot find words with which to describe it. It is a feeling of that peace which passeth all understanding.

TECHNIQUE AND EFFECTS OF PRĀṆĀYĀMA

58| *Ujjāyī Prāṇāyāma*

The prefix ud attached to verbs and nouns, means upwards or superiority in rank. It also means blowing or expanding. It conveys the sense of pre-eminence and power.

Jaya means conquest, victory, triumph or success. Looked at from another viewpoint it implies restraint or curbing.

Ujjāyi is the process in which the lungs are fully expanded and the chest puffed out like that of a proud conqueror.

TECHNIQUE

1. Sit in any comfortable position like Padmāsana (Plate 53), Siddhāsana (Plate 38) or Vīrāsana (Plate 43).

2. Keep the back erect and rigid. Lower the head to the trunk. Rest the chin in the notch between the collar-bones just above the breast-bone. (This is the Jālandhara Bandha. Jāla means a net, web, lattice or a mesh.)

3. Stretch the arms out straight and rest the back of the wrists on the knees. Join the tips of the index fingers to the tips of the thumbs, keeping the other fingers extended. (This position or gesture of the hand is known as the Jñāna Mudrā, the symbol or seal of knowledge. The index finger symbolizes the individual soul and the thumb the Universal Soul. The union of the two symbolizes knowledge.)



147

4. Close the eyes and look inwards. (Plate 147)

5. Exhale completely.

6. Now the Ujjāyi method of breathing begins.

7. Take a slow, deep steady breath through both nostrils. The passage of the incoming air is felt on the roof of the palate and makes a sibilant sound (sa). This sound should be heard.

8. Fill the lungs up to the brim. Care should be taken not to bloat the abdomen in the process of inhalation. (Observe this in all types of Prāṇāyāma.) This filling up is called puraka (inhalation).

9. The entire abdominal area from the pubes up to the breast-bone should be pulled back towards the spine.

10. Hold the breath for a second or two.

11. Exhale slowly, deeply and steadily, until the lungs are completely empty. As you begin to exhale, keep your grip on the abdomen. After two or three seconds of exhalation, relax the diaphragm gradually and slowly. While exhaling the passage of the outgoing air should be felt on the roof of the palate. The brushing of the air on the palate should make an aspirate sound (ha). This exhalation is called rechaka.

12. Wait for a second before drawing a fresh breath. This waiting period is called bāhya kumbhaka.

13. The process described from para. 7 to para. 12 completes one cycle of Ujjāyi Prāṇāyāma.

14. Repeat the cycles for five to ten minutes keeping the eyes closed throughout.

15. Lie on the floor for Śavāsana. (Plate 146)

16. Ujjāyi Prāṇāyāma may be done without the Jālandhara Bandha even while walking or lying down. This is the only prāṇāyāma which can be done at all times of the day and night.

EFFECTS

This type of prāṇāyāma aerates the lungs, removes phlegm, gives endurance, soothes the nerves and tones the entire system. Ujjāyi without kumbhaka, done in a reclining position, is ideal for persons suffering from high blood pressure or coronary troubles.

59| *Sūrya Bhedana Prāṇāyāma*

Sūrya is the sun. Bhedana is derived from the root bhid meaning to pierce, to break or pass through.

In Sūrya Bhedana Prāṇāyāma, the breath is inhaled through the right nostril. In other words the prāṇa passes through the Piṅgāla or Sūrya nādī. A kumbhaka is then performed and the breath is then exhaled through the left nostril which is the path of the Idā nāḍī.

TECHNIQUE

1. Sit in any comfortable position like Padmāsana (Plate 53), Siddhāsana (Plate 38) or Vīrāsana (Plate 43).

2. Keep the back erect and rigid. Lower the head to the trunk. Rest the chin in the notch between the collar-bones just above the breast-bone. (This is Jālandhara Bandha.)

3. Stretch the left arm. Rest the back of the left wrist on the left knee. Perform Jñāna with the left hand (as stated in stage 3 of the technique of Ujjāyi).

4. Bend the right arm at the elbow. Bend the index and middle fingers towards the palm, keeping them passive. Bring the ring and little fingers towards the thumb. (Plate 148)



148

5. Place the right thumb on the right side of the nose just below the nasal bone, the ring and little fingers on the left side of the nose just below the nasal bone, just above the curve of the fatty tissue of the nostrils above the upper jaw.

6. Press the ring and the little finger to block the left side of the nose completely.

7. With the right thumb, press the fatty tissue on the right side so as to make the outer edge of the right nostril parallel to the lower edge of the cartilage of the septum.

8. The right thumb is bent at the top joint and the tip of the thumb is placed at a right angle to the septum. (Plate 149)

9. Now inhale slowly and deeply controlling the aperture of the right nostril with the tip of the thumb nearer the nail. Fill the lungs to the brim (puraka).

10. Then block the right nostril so that both are now blocked.

11. Hold the breath for about 5 seconds (antara kumbhaka).

12. Keeping the right nostril completely blocked, open the left nostril partially and exhale through it slowly and deeply (rechaka).

13. During the exhalation regulate the rhythmic flow of air from the left nostril by adjusting pressure with the ring and little fingers, so that the outer edge of the left nostril is kept parallel to the septum. The pressure should be exerted from the inner sides of the tips of the fingers (away from the nails).

14. This completes one cycle of Sūrya Bhedana Prāṇāyāma. Continue with more cycles at a stretch from 5 to 10 minutes, according to capacity.

15. All the inhalations in Sūrya Bhedana are from the right nostril and all the exhalations from the left nostril.



149

16. Throughout the process, the passage of air is felt at the tips of the fingers and the thumbs and in the nasal membranes where pressure is applied. The passage of air makes a sound similar to air escaping from a cycle tube. This sound should be maintained constant throughout by varying pressure on the nostrils.

17. The eyes, temples, eyebrows and the skin on the forehead should remain completely passive and show no sign of strain.

18. The mind should be absorbed completely in listening to the proper sound of the passage of air and in maintaining a proper rhythm in breathing.

19. Each inhalation and exhalation should last for the same length of time.

20. The inhalation and the exhalation should not be forced. An even and slow rhythm should be maintained throughout.

21. Lie down in Śavāsana after completing prāṇāyāma. (Plate 146)

EFFECTS

By reason of the pressure on the nostrils, in this Prāṇāyāma the lungs have to work more than in the case of Ujjāyi. In Sūrya Bhedana they filled more slowly, steadily, and fuller than in Ujjāyi. Sūrya Bhedana increases digestive power, soothes and invigorates the nerves, and cleans the sinuses.

NOTE

It often happens that the passages of both the nostrils are not of the same width, one being bigger than the other. In that case the pressure of the fingers has to be adjusted. In some cases the right nostril is completely blocked while the left one is clear. In that case, inhalation may be done only through the left nostril, while exhalation is done only through the right nostril. In course of time due to the manipulation of the fingers the right nostril clears and inhalation through it becomes possible.

Persons suffering from low blood pressure will derive benefit but those with high blood pressure or heart trouble should not hold their breath after inhalation (antara kumbhaka) whilst practising this prāṇāyāma.

60| Nāḍī Śodhana Prāṇāyāma

Nāḍī is a tubular organ of the body like an artery or a vein for the passage of prāṇa or energy. A nāḍī has three layers like an insulated electric wire. The innermost layer is called sirā, the middle layer damanī and the entire organ as well as the outer layer is called nāḍī.

Śodhana meaning purifying or cleansing, so the object of Nāḍī Śodhana Prāṇāyāma is the purification of the nerves. A little obstruction in a water pipe can cut off the supply completely. A little obstruction in the nerves can cause great discomfort and paralyse a limb or organ.

TECHNIQUE

1. Follow the technique in paras 1 to 8 of Sūrya Bhedana Prāṇāyāma. (Plate 149)

2. Empty the lungs completely through the right nostril. Control the aperture of the right nostril with the inner side of the right thumb, away from the nail.

3. Now inhale slowly, steadily and deeply through the right nostril, controlling the aperture with the tip of the right thumb near the nail. Fill the lungs to the brim (puraka). During this inhalation the left nostril is completely blocked by the ring and little fingers.

4. After full inhalation, block the right nostril completely with the pressure of the thumb and release the pressure of the ring and little fingers on the left nostril. Readjust them on the outer edge of the left nostril and keep it parallel to the septum. Exhale slowly, steadily and deeply through the left nostril. Empty the lungs completely. The pressure should be exerted from the inner sides of the tips of the ring and little fingers (away from the nails) (rechaka).

5. After full exhalation through the left nostril, change the pressure on it by adjusting the fingers. In the changed position, the tips of the ring and little fingers nearer the nails exert the pressure.

6. Now inhale through the left nostril slowly, steadily and deeply, filling the lungs to the brim (puraka).

7. After full inhalation through the left nostril, block it and exhale through the right nostril, adjusting the pressure of the right thumb on the right nostril as stated in para. 2 above (rechaka).

8. This completes one cycle of Nāḍī Śodhana Prāṇāyāma. Here the rhythm of breathing is as follows:

(a) Exhale through the right nostril.
(b) Inhale through the right nostril.
(c) Exhale through the left nostril.
(d) Inhale through the left nostril.
(e) Exhale through the right nostril.
(f) Inhale through the right nostril.
(g) Exhale through the left nostril.
(h) Inhale through the left nostril.
(i) Exhale through the right nostril.
(j) Inhale through the right nostril . . . and so on.

Stage (a) above is the preparatory one. The first real Nāḍī Śodhana Prāṇāyāma cycle starts at stage (b) and ends at stage (e). The second cycle starts at stage (f) and ends at stage (i). Stage (j) is the safety measure in order to prevent gasping, breathlessness and strain on the heart.

9. Do 8 to 10 cycles at a stretch as described above. This may take 6 or 8 minutes.

10. Inhalation and exhalation from each side should take the same time. In the beginning the duration will be unequal. Persevere until equality is achieved.

11. After achieving mastery over the equal duration and precision over inhalation and exhalation on either side an attempt may be made to retain breath (antara kumbhaka) after inhaling.

12. This precision is only achieved after long practice.

13. Retention should not disturb the rhythm and equality of inhalation and exhalation. If either are disturbed curtail the period of retention or hold the breath on alternate cycles.

14. Do not attempt to hold the breath after exhalation (bāhya kumbhaka) until you have mastered retention after inhalation (antara kumbhaka).

15. Retention and the lengthening of inhalation and exhalation should only be attempted with the help and under the guidance of an experienced Guru.

16. Always conclude by lying down in Śavāsana. (Plate 146)

EFFECTS

The blood receives a larger supply of oxygen in Nāḍī Śodhana than in normal breathing, so that one feels refreshed and the nerves are calmed and purified. The mind becomes still and lucid.

NOTE

In the beginning the body perspires and shakes, while the thigh and arm muscles become tense. Such tension should be avoided.

Persons suffering from high blood pressure or heart trouble should never attempt to hold their breath (kumbhaka). They can practise Nāḍī Śodhana Prāṇāyāma without retention (kumbhaka) with beneficial effect.

Persons suffering from low blood pressure can do this prāṇāyāma with retention after inhalation (antara kumbhaka) *only*, with beneficial effects.

61| *Viloma Prāṇāyāma*

Loma means hair. The particle vi is used to denote negation or privation. Viloma thus means against the hair, against the grain, against the natural order of things.

In Viloma Prāṇāyāma inhalation or exhalation is not one uninterrupted continuous process, but is interrupted by several pauses. For instance, if continuous inhalation to fill the lungs or continuous exhalation to expel the air were to take 15 seconds in each case, in Viloma there would be a pause of about 2 seconds after every third second of inhalation or of exhalation. The process of inhalation or of exhalation is thus lengthened to 25 seconds. The technique given below is in two stages, which are distinct.

TECHNIQUE: STAGE I

1. Viloma Prāṇāyāma can be done either in a sitting posture or while lying down.

2. If done when seated, keep the back erect, lower the head to the trunk so that the chin rests in the notch between the collar-bones on the top of the breast-bone. This is Jālandhara Bandha. Keep the hands in Jñāna Mundra (see p. 119, para 21).

3. Inhale for 2 seconds, pause for 2 seconds holding the breath, again inhale for 2 seconds, again pause for 2 seconds holding the breath, and continue like this until the lungs are completely full.

4. Now hold the breath for 5 to 10 seconds (antara kumbhaka) according to capacity.

5. Exhale slowly and deeply as in Ujjāyi with an aspirate sound (huuuum).

6. This completes one cycle of the first stage of Viloma Prāṇāyāma.

7. Repeat 10 to 15 cycles of this first stage at a stretch.

STAGE II

8. Rest for a minute or two.

9. Then take a deep breath without any pauses as in Ujjāyi with a sibilant sound (sssssssa), keeping the chin on the top of the breast-bone. Fill the lungs completely.

10. Hold the breath from 5 to 10 seconds (antara kumbhaka), keeping the Mūla Bandha grip.

11. Exhale for 2 seconds and pause for 2 seconds. Again exhale for 2 seconds, pause for 2 seconds and continue like this until the lungs are completely emptied.

12. This completes one cycle of the second stage of Viloma Prāṇāyāma.

13. Repeat the second stage of Viloma 10 to 15 times at a stretch.

14. This completes Viloma Prāṇāyāma.

15. Then lie down in Śavāsana. (Plate 146)

EFFECTS

Viloma Prāṇāyāma in the first stage helps those suffering from low blood pressure. In the second stage it benefits persons suffering from high blood pressure.

The second stage of Viloma should only be done when lying down by persons suffering from high blood pressure.

Those suffering from heart complaints should not attempt it until they have mastered the Nāḍī Śodhana and Ujjāyi Prāṇāyāmas.

As a wind drives smoke and impurities from the atmosphere, prāṇāyāma drives away the impurities of the body and the mind. Then, says Patañjali, the DIVINE FIRE within blazes forth in its full glory and the mind becomes fit for concentration (dhāraṇā) and meditation (dhyāna). (*Yoga Sutras*, chapter II, 52 and 53.) This takes a long time. By degrees is the darkness banished by the dawn.



150

Appendix

Āsana Courses

I am giving the āsanas in a serial order for practice and the possible time it may take to gain control of them.

(The figures within the brackets after the āsanās denote the number.)

1ST AND 2ND WEEK

Tādāsana (1); Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Sālamba Sarvāngāsana (102); Halāsana (113); Savāsana (146).

3RD AND 4TH WEEK

Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Vīrabhadrāsana I and II (9 and 10); Pārśvottānāsana (13); Sālamba Sarvāngāsana (102); Halāsana (115); Śavāsana (146).

5TH AND 6TH WEEK

Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Vırabhadrāsana I and II (9 and 10); Pārśvottānāsana (13); Prasārita Pādottānāsana (17); Stay ½ a minute on each side in all these āsanās. Paripūrna Nāvāsana (36); Sālamba Sarvāngāsana (102); Halāsana (113); Paschimottānāsana (81); Śavāsana (146).

7TH AND 8TH WEEK

Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Vīrabhadrāsana I and II (9 and 10); Pārśvottānāsana (13); Prasārita Pādottānāsana (17); Pādānguṣṭhāsana (22); Pāda Hastāsana (24); Uttānāsana (25); Sālamba Sarvāngāsana (102); Halāsana (113); Karṇapīḍāsana (114); Daṇḍāsana (35); Paripurṇa Nāvāsana (36); Ardha Nāvāsana (37); Paschimottānāsana (81); Poorvottānāsana (82); Savāsana (146).

9TH WEEK

Consolidate the āsanās and increase the length of stay in all of them.

10TH WEEK

Repeat all the āsanās and do Ujjāyī Prāṇāyāma (Section 58) without sitting in Siddhāsana (38) for 5 minutes and do Śavāsana (146) for 5 minutes.

11TH AND 12TH WEEK

Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Vīrabhadrāsana I and II (9 and 10); Pārśvottānāsana (13); Prasārita Pādottānāsana (17) Pādānguṣṭhāsana (22); Pāda Hastāsana (24); Uttānāsana (25); Daṇḍāsana

(35); Paripūrna Nāvāsana (36); Ardha Nāvāsana (37); Mahā Mudrā (61); Jānu Śīrsāsana (63); Paschimottānāsana (81); Poorvottānāsana (82); Chaturanga Daṇḍāsana (30) Bhujangāsana (31); Śalabhāsana (26); Dhanurāsana (28) Urdhva Mukha-Śvānāsana (32); Uṣṭrāsana (20); Adho Mukha Śvānāsana (33); Baddha Koṇāsana (51); Sālamba Sarvāngāsana (102); Halāsana (113); Karṇapīdāsana (114); Supta Koṇāsana (115); Pārśva Halāsana (116); Savāsana (146) for 5 minutes; Ujjāyī Prāṇāyāma without retention (Section 58) in Siddhāsana (38) for 5 minutes.

13TH WEEK

Repeat. Do Ujjāyī Prāṇāyāma with inhalation retention (Section 58) in Siddhāsāna (38) or in Śavāsana (146).

14TH TO 18TH WEEK

(Observe the change in the order of the āsanās)
Sālamba Śīrṣāsana (90); Utthita Trikoṇāsana (3 and 4); Utthita Pārśvakoṇāsana (5 and 6); Vīrabhadrāsana I and II (9 and 10); Pārśvottānasana (13); Prasārita Pādottānāsana (17); Pādānguṣṭhāsana (22); Pāda Hastāsana (24); Uttānāsana (25); Mahā Mudrā (61); Jānu Śīrṣāsana (63); Ardha Baddha Padma Paschimottānāsana (66); Paschimottānāsana (81); Paripoorṇa Nāvāsana (36); Ardha Nāvāsana (37); Pūrvottanāsāna (82); Uṣṭrāsana (20); Śalabhāsana (26); Dhanurāsana (28); Chaturanga Daṇḍāsana (30); Bhujangāsana (31); Ūrdha Mukha Svānāsana (32); Adho Mukha Śvānāsana (33); Vīrāsana (42); Baddha Koṇāsana (51); Sālamba Sarvāngāsana (102); Halāsana (113); Karṇapīdāsana (114); Supta Koṇāsana (115); Pārśva Halāsana (116); Eka Pāda Sarvāngāsana (117); Pārśvaika Pāda Sarvāngāsana (118); Jatara Parivartanāsana (127 and 128); Śavāsana (146). Do Ujjāyī Prāṇāyāma (without inhalation retention) (Section 58) in Siddhāsana (38) or in Vīrāsana (42) or in Baddhakoṇāsana (50).

19TH AND 20TH WEEK

Repeat.

If you now find all the standing āsanās are easy enough, you can do them on alternate days or twice a week. The day you do not do the standing āsanās, devote your time to Ujjāyī Prānāyāma (Section 58) first without inhalation retention for 5 minutes and then with inhalation retention for 5 minutes and then with inhalation retention for 5 minutes.

21ST AND 23RD WEEK

Sālamba Sīrṣāsana (90); if possible Ūrdhva Daṇḍāsana (94); Sālamba Sarvāngāsana (102); Halāsana (113); Karṇapīdāsana (114); Supta Koṇāsana (115); Pārśva Halāsana (116); Ekapāda Sarvangāsana (117); Pārśvaika Pāda Sarvangāsana (118); Supta Pādānguṣṭhāsana (130); Jaṭara Parivartanāsana (127 and 128); Jānu Śīrṣāsana (63); Ardha Baddha Padma Paschimottānāsana (66); Triang Mukhaika-pāda Paschimottānāsana (69); Marichyāsana I (71); Paschimottānāsana (81); Upaviṣṭha Koṇāsana (74); Baddhakoṇāsana (51); Pūrvottānāsana (82); Bharadwājāsana (131 and 132); Virāsana (42);

Chaturangadandāsana (30); Bhujangāsana (31); Ūrdhva Mukha Śvānāsana (32); Adho Mukha Śvānāsana (33); Śalabhāsana (26); Dhanurāsana (28); Uśtrāsana (20); Uttānāsana (25); Savāsana (146); Ūjjāyī Prānāyāma (Section 58) without inhalation retention in Śavāsana for 5 minutes and with inhalation retention in Siddhāsana (38); or in Padmāsana (53); or in Vīrāsana (42) or in Baddha Koṇāsana (52).

23RD TO 25TH WEEK

Follow the serial order up to Padmāsana (53) as in the 21st week. Then Parvatāsana (54); Matsyāsana (56); Vīrāsana (42); Supta Vīrāsana (49); Bharadwājāsana (131 and 132); Marichyāsana II (135 and 136); Poorvottānāsana (82); Chaturanga Daṇḍāsana (30); Urdva Mukha Śvānāsana (32); Adho Mukha Śvānāsana (33); Salabhāsana (26); Dhanurāsana (28); Uṣṭrāsana (20); Ūrdhva Dhanurāsana (144); Śavāsana (146); then do Viloma Prāṇāyāma (Section 61) Stage I for 5 minutes and stage II for 5 minutes in Siddhāsana (38) or Padmāsana (53).

When you do the standing positions, eliminate the various movements of Sarvāngāsana cycle and do the rest. For some it is easy to get Padmāsana earlier than the stipulated period and for some it may take a little longer time to get mastery in the position.

26TH TO 30TH WEEK

Sālamba Śīrṣāsana (90); Ūrdhva Daṇḍāsana (94); Sālamba Sarvāngāsana (102); Halāsana (113); Karṇapīdāsana (114); Supta Koṇāsana (115); Pārśva Halāsana (116); Eka Pāda Sarvāngāsana (117); Pārśvaikapāda Sarvāngāsana (118); Ūrdva Padmāsana in Sarvāngāsana (122); Pinḍāsana in Sarvāngāsana (123); Setu Bandha Sarvāngāsana (121); Jaṭara Parivartanāsana (127 and 128); Paripūrṇa Nāvāsana (36); Ardha Nāvāsana (37); Jānu Śīrṣāsana (63); Ardha Baddha Padma Paschimottānāsana (66); Triang Mikhaika Pāda Paschimottānāsana (69); Marichyāsana I (71); Paschimottānāsana (81); Upaviṣṭha Koṇāsana (74); Baddha Koṇāsana (51); Padmāsana (53); Parvatāsana (54); Baddha Padmāsana (58 and 59); Yoga Mudrāsana (60); Matyāsana (56); Vīrāsana (42); Supta Vīrāsana (49); Bharadwājāsana (131 and 132); Marichyāsana II (135 and 136); Ardha Matsyendrāsana (139 and 140); Adho Mukha Śvānāsana (33); Ūrdhva Mukha Śvānāsana (32); Chaturanga Daṇḍāsana (30); Śalabhāsana (26); Dhanurāsana (28); Bhujangāsana (31); Poorvottānāsana (82); Uṣṭrāsana (20); Ūrdhva Dhanurāsana (144) for 4 times; Śavāsana (146). Ujjāyī Prāṇāyāma with Antar Kumbhaka (inhalation retention Section 58) and Viloma Prāṇāyāma (Section 61) in Siddhāsana (38); or in Vīrāsana (42) or in Padmāsana (53).

31ST TO 32ND WEEK

Consolidate all the āsanās concentrating on perfection as well as timings. Stay in all the forward bendings for a minute on each āsanā and Paschimottānāsana for 5 minutes.

32ND TO 35TH WEEK

Follow the serial order up to Pinḍāsana in Sarvāngāsana (123) as in the 26th week. Then Pārśva Pinḍāsana in Sarvāngāsana (124 and 125) and continue the serial order from Setu Bandha Sarvāngāsana (121) as in the 26th week up to Śavāsana (146). Do Sūrya Bhedana Prāṇāyāma for 5 minutes and Nāḍi Śodhaṇa Prāṇāyāma 8 cycle only without retention. Sit in Dhyāna (Plate 150) for 3 to 5 minutes.

One Week Course

The following is a course which covers one week and will benefit the body and bring harmony to the mind.

FIRST DAY OF THE WEEK

Sālamba Sīrṣāsana (90) for 10 minutes; Ūrdhva Danḍāsana (94) for 1 minute; Sālamba Sarvāngāsana (10 minutes; Halāsana (113) for 5 minutes; Utthita Trikoṇāsana (3 and 4) for 30 seconds on each side; Utthita Pārśva Konāsana (5 and 6) for 30 seconds on each side; Virabhadrāsana I and II for 20 seconds on each side; Pārśvottānāsana (13) for 1 minute on each side; Prasārita Padottānāsana (17) for 1 minute; Pādānguṣṭāsana (22) for 30 seconds; Pāda Hastāsana (24) for 30 seconds; Uttānāsana (25) for 1 minute; Paschimottānāsana (81) for 5 minutes; Poorvottānāsana (82) for 30 seconds; Marīchyāsana II (135 and 136) for 30 seconds on each side; Ardha Matsyendrāsana (139 and 140) for 30 seconds on each side; Ūrdhva Dhanurāsana for 8 to 10 times staying 15 seconds each time; Śavāsana (146) for 5 minutes. Ūjjāyi Prāṇāyāma (with inhalation retention) (Section 58) for 15 minutes and meditation (150) to the capacity, in any āsana. Again Śavāsana (146) for 5 minutes.

SECOND DAY OF THE WEEK

Sālamba Śīrṣāsana (90) for 10 minutes; Ūrdhva Danḍāsana (94) from 30 seconds to 1 minute; Sālamba Sarvāngāsana (102) for 10 minutes; Halāsana (113) for 5 minutes; Jaṭara Parivartanāsana (127) for half a minute on each side; Supta Pādānguṣṭāsana (130) for 20 seconds on each side; Paripūrṇa Nāvāsana (36) for 1 minute; Ardha Nāvāsana (37) 20 to 30 seconds; Paschimottānāsana (81) for 5 minutes; Bharadwājāsana (131 and 132) for 30 seconds each side; Marīchyāsana II (135 and 136) for 30 seconds each side; Ardha Matyendrāsana (139 and 140) for 30 seconds on each side; Parvātāsana (54) for 1 minute; Vīrāsana (42) for 1 minute; Supta Vīrāsana (49) for 1 minute; Uṣṭrāsana (20 for 30 seconds; Śalabhāsana (26) for 20 to 30 seconds; Dhanurāsana (28) for 30 seconds; Urdhva Mukha Śvānāsana (32) for 20 to 30 seconds; Adho Mukha Śvānāsana (33) for 1 minute; Uttānāsana (25) for 1 to 2 minutes; Śavāsana (146) for 5 minutes and Sūrya Bhedana Prāṇāyāma (Section 59) in Padmāsana (53) or in Siddhāsana (38) or in Vīrāsana (42) for 5 minutes and Nādi Śodhana Prāṇāyāma without retention for 10 minutes and sit in Dhyāna (150) for 2 minutes. Again do Śavāsana (146) for 5 minutes.

THIRD DAY OF THE WEEK

Sālamba Śīrṣāsana (90) for 10 minutes, Ūrdhva Daṇḍāsana (94) for 1 minute; Sālamba Sarvāngāsana (102) for 10 minutes; Halāsana (113) for 5 minutes; Karṇapīdāsana (114) for 30 seconds; Supta Koṇāsana (115) for 30 seconds; Pārsva Halāsana (116) for 30 seconds on each side; Eka Pāda Sarvāngāsana (117) for 30 seconds on each side; Pārśvaikapada Sarvāngāsana (118) for 30 seconds on each side; Setu Bandha Sarvāngāsana (121) from 30 seconds to 2 minutes; Ūrdhva Padmāsana in Sarvāngāsana (122) for 30 seconds; Pinḍāsana in Sarvāngāsana (123) for 30 seconds; Pārśva Pinḍāsana in Sarvāngāsana (124) for 30 seconds on each side; Jaṭara Parivartanāsana (127 and 128) for 30 seconds on each side twice; Supta Pādānguṣṭhāsana (130) for 30 seconds on each side; Marīchyāsana II (135 and 136) from 30 seconds to 60 seconds on each side; Ardha Matsyendrāsana (139 and 140) from 30 seconds to 60 seconds on each side; Paschimottānāsana (81) for 5 minutes; Śavāsana (146) for 5 minutes. Nādiśodhana Prāṇāyāma (Section 60) without Kumbhaka or retention 10 minutes, Sūrya Bhedana Prāṇāyāma (Section 59) 10 cycles; Dhyāna (150) for 5 minutes.

FOURTH DAY OF THE WEEK

Sālamba Śīrṣāsana (90) for 5 minutes; Ūrdhva Daṇḍāsana (94) for 1 minute; Sālamba Sarvāngāsana (102) for 5 minutes; Halāsana (113) for 5 minutes; Mahā Mudra (61) for 30 seconds on each side; Jānu Śīrṣāsana (63) for 1 minute on each side; Ardha Baddha Padma Paschimottānāsana (66 and 67) for 1 minute on each side; Trianga Mukhaika Pāda Paschimottānāsana (69) for 1 minute on each side; Marīchyāsana I (71) for 1 minute on each side; Upaviṣṭha Koṇāsana (74) for 1 minute; Vīrāsana (42) for 1 minute; Supta Vīrāsana for 1 minute; Baddha Padmāsana (58 and 59) for 1 minute; Yoga Mudrāsana (60) for 1 minute; Parvatāsana (54) for 30 seconds; Baddha Koṇāsana (51) for 1 minute; Paschimottānāsana (81) for 5 minutes; Ujjāyi Prāṇāyāma (Section 58) with inhalation retention to capacity for 8 times. Śavāsana (146) with Viloma Prāṇāyāma (Section 61) Stage I for 5 minutes.

FIFTH DAY OF THE WEEK

Sālamba Śīrṣāsana (90) for 10 minutes; Ūrdhva Daṇḍāsana (94) for 1 minute; Sālamba Sarvāngāsana (102) for 10 minutes; Halāsana (113) for 5 minutes; Paschimottānāsana (81) for 5 minutes; Bharadwājāsana (131 and 132) for 30 seconds on each side; Marīchyāsana II (135 and 136) for 30 seconds on each side; Ardha Matsyendrāsana (139 and 140) for 30 seconds on each side; Baddha Padmāsana (58 and 59) for 1 minute; Matsyāsana (56) for 30 seconds; Supta Vīrāsana (49) for 1 minute; Śalabhāsana (26) three times of 15 seconds duration; Dhanurāsana (28) for 20 seconds; Bhujangāsana (31) for 30 seconds; Ūrdhva Mukha Śvānāsana (32) for 30 seconds; Ūrdhva Dhanurāsana (144) for 15 times staying to capacity; Śavāsana (146) with Viloma Prāṇāyāma (Section 61) Stage I and Stage II for 5 minutes each. Dhyāna (150) for 5 minutes.

SIXTH DAY OF THE WEEK

Sâlamba Śīrṣāsana (90) for 5 minutes; Utthita Trikoṇāsana (3 and 4) for 15 seconds on each side; Utthita Parśvakoṇāsana (5 and 6) for 15 seconds on each side; Vīrabhadrāsana I and II (9 and 10) for 10 seconds on each side; Pārśvottānāsana (13) for 10 seconds on each side; Prasārita Pādottānāsana (17) for 15 seconds; Uttānāsana (25) for 20 seconds; Sālamba Sarvāngāsana (102) for 5 minutes; Halāsana (113) for 5 minutes; Karṇapīdāsana (114) for 15 seconds; Suptakoṇāsana (115) for 15 seconds; Parśva Halāsana (116) for 15 seconds on each side; Ekapāda Sarvāngāsana (117) for 15 seconds on each side; Pārśvaikapāda Sarvāngāsana (118) for 15 seconds on each side; Setu Bandha Sarvāngāsana (121) for 1 minute; Ūrdhva Padmāsana and Pinḍāsana in Sarvāngāsana (122 and 123) for 15 seconds; Pārśva Pinḍāsana (124 and 125) for 15 seconds on each side; Jānu Sīrṣāsana (63); Ardha Baddha Padma Paschimottānāsana (66); Triang Mukhaikapāda Paschimottānāsana (69); Marīchyāsana I (71) all for 15 seconds on each side; Upaviṣtha Koṇāsana (74) for 15 seconds; Paripūrṇa Nāvāsana (36) for 30 seconds; Ardha Nāvāsana (37) for 30 seconds; Baddha Koṇāsana (51) for 30 seconds; Paschimottānāsana (81) for 1 minute; Poorvottānāsana (82) for 15 seconds; Vīrāsana (42) and Supta Vīrāsana (49) for 15 seconds each; Parvatāsana in Padmāsana (54) for 30 seconds; Marichyāsana II (135 and 136) for 30 seconds on each side; Ardha Matyendrāsana (139 and 140) for 30 seconds on each side; Ūrdhva Dhanurāsana (114) for 3 times to capacity; Śavāsana (146) for 5 minutes. Nādi Śodhana Prāṇāyāma (Section 60) 8 cycles with inhalation retention. Dhyāna (150) for 3 minutes.

On Sundays do Nādi Śodhana Prāṇāyāma (Section 60) for 15 minutes with inhalation retention and Viloma Prāṇāyāma (Section 61) Stages I and II for 10 minutes in Śavāsana (146).

If one finds the number of āsanās or the length of time to do them has increased one can adjust according to capacity and the time at one's disposal.

Do Śavāsana (146) after Prāṇāyāma. Do Antarkumbhaka (inhalation retention) only when you have mastered the art of deep inhalation and deep exhalation without any jerks.

Do not do the āsanās and Prāṇāyāma together. You may feel strained and fatigued.

If you do Prāṇāyāma in the mornings then āsanās can be done in the evenings or half an hour after the āsanās.

Never do āsanās immediately after Prāṇāyāma, but one can practise Prāṇāyāma after āsanās if one is still fresh.

Those who wish to prostrate to the Sun (Sūryanamaskar) and to develop the arms and chest, can do the following āsanās in sequence at first for six rounds, increasing the number according to capacity.

	Asanās	*Method of breathing*
1	Tāḍasana (1)	Inhalation
2	Uttānāsana (25)	Exhalation, inhalation with head up
3	Chaturanga Danḍāsana (30)	Exhalation
4	Ūrdhva Mukha Svanasana (32) and go back to	Inhalation
5	Chaturanga Danḍāsana (30)	Exhalation, inhale
6	Adho Mukha Śvānāsana (33) and from here jump to	Exhale
7	Uttānāsana (25) and then back to	Inhalation
8	Tāḍāsana (1)	Exhalation

Table of Asanas

The following table correlates the āsanas with the plates that illustrate them:

NAMES OF ĀSANAS, ETC.	INTERMEDIATE ĀSANAS PLATE NO.	FINAL ĀSANAS PLATE NO.
1. Tāḍāsana	—	1
2. Utthita Trikoṇāsana	2	3 and 4
3. Utthita Pārśvakoṇāsana	—	5 and 6
4. Vīrabhadrāsana I	7 and 8	9
5. Virabhadrāsana II	—	10
6. Pārśvōttānāsana	11 and 12	13 and 14
7. Prasārita Pādottānāsana	15 and 16	17 and 18
8. Ustrāsana	19	20
9. Pādānguṣṭhāsana	21	22
10. Pāda Hastāsana	23	24
11. Uttānāsana	—	25
12. Śalabhāsana	27	26
13. Dhanurāsana	—	28
14. Chaturanga Daṇḍāsana	29	30
15. Bhujangāsana	—	31
16. Ūrdhva Mukha Śvānāsana	—	32
17. Adho Mukha Śvānāsana	—	33 and 34
18. Danḍāsana	—	35
19. Paripūrṇa Nāvāsana	—	36
20. Ardha Nāvāsana	—	37
21. Siddhāsana	—	38
22. Vīrāsana	39 to 41	42 to 45
23. Supta Vīrāsana	46 to 48	49
24. Baddha Koṇāsana	50	51 and 52
25. Padmāsana	—	53
26. Parvatāsana	—	54
27. Matsyāsana	55 and 57	56
28. Baddha Padmāsana	—	58 and 59
29. Yaga Mudrāsana	—	60
30. Mahā Mudrā	—	61
31. Jānu Śīrṣāsana	62	63
32. Ardha Baddha Padma Paschimottānāsana	64 and 65	66 and 67

33. Triang Mukhaikapâda Paschimottānāsana	68	69
34. Marīchyāsana I	70	71
35. Upaviṣṭha Konāsana	72 and 73	74
36. Paschimottānāsana (or Urgrāsana or Brahmacharyāsana)	75 to 80	81
37. Pūrvottānāsana	—	82
38. Sālamba Śīrṣāsana	83 to 89 and 92 to 95, 97	90, 91 and 96
39. Ūrdhva Daṇḍāsana	—	94
40. Sâlamba Sarvāngâsana	98 to 101 and 104 to 107	102, 103 and 108
41. Halāsana	109 to 112	113
42. Karṇapīdāsana	—	114
43. Supta Koṇāsana	—	115
44. Pārśva Halāsana	—	116
45. Eka Pāda Sarvāngāsana	—	117
46. Pārśvaika Pāda Sarvāngāsana	—	118
47. Setu Bandha Sarvāngāsana (or Uttāna Mayūrāsana)	119 and 120	121
48. Ūrdhva Padmāsana in Sarvāngāsana	—	122
49. Pindāsana in Sarvāngāsana	—	123
50. Pārśva Piṇḍāsana in Sarvāngāsana	—	124 and 125
51. Jaṭhara Parivartanāsana	126	127 and 128
52. Supta Pâdânguṣṭhāsana	129	130
53. Bharadvājāsana	—	131 and 132
54. Marīchyāsana II	133 and 134	135 and 136
55. Ardha Matsyendrāsana	137 and 138	139 and 140
56. Ūrdhva Dhanurāsana	141 to 143 and 145	144
57. Śavāsana	—	146
Prāṇāyāma		
58. Ujjāyi	—	147
59. Sūrya Bhedana	148	149
60. Nāḍi Śodhana	—	—
61. Viloma	—	—
— Dhyāna	—	150

Glossary

A	Negative particle meaning 'non', as in non-violence.
Abhaya	Freedom from fear.
Abhiniveśa	Instinctive clinging to life and the fear that one may be cut off from all by death.
Abhyāsa	Constant and determined study or practice.
Ādhaḥ	Down, lower.
Adhāra	A support.
Adhimātra	Beyond measure, superior.
Adhimātratama	The supreme one, the highest.
Adho-mukha	Face downwards.
Ādīśvara	The primeval Lord; an epithet of Śiva.
Advaita	Non-duality of the Universal Spirit with the individual soul.
Āgama	Testimony or proof of an acceptable authority when the source of knowledge has been checked and found trustworthy.
Ahaṁkāra	Ego or egotism; literally 'the I-Maker', the state that ascertains 'I know'.
Ahimsā	Non-violence. The word has not merely the negative and restrictive meaning of 'non-killing or non-violence', but the positive and comprehensive meaning of 'love embracing all creation'.
Ajapa-mantra	Unconscious repetitive prayer. Every living creature unconsciously breathes the prayer 'So'ham' (Saḥ = He (the Universal Spirit), aham = am I) with each inward breath, and with each outgoing breath prays 'Haṁsah' (Aham = I am, Saḥ = He (the Universal Spirit)).
Akrodha	Freedom from anger.
Alabhdha-bhūmikatva	Failure to attain firm ground or continuity in practice, feeling that it is not possible to see reality.
Ālamba	Support.
Ālasya	Idleness, sloth, apathy.
Amanaska	The mind which is free from thoughts and desires.
Ananta	Infinite; a name of Viṣṇu as also of Viṣṇu's couch, the serpent Śeṣa.
Anavasthitattva	Instability to continue the practices feeling that it is not necessary to continue as he thinks that he has reached the highest state of Samādhi.

Aṅga	The body; a limb or a part of the body; a constituent part.
Aṅgamejayatva	Unsteadiness or tremor of the body.
Aṅgula	A finger; the thumb.
Aṅguṣṭha	The big toe.
Antara	Within; interior.
Antara Kumbhaka	Suspension of breath after full inhalation.
Antaranga Sādhanā	The inward quest of the soul by Prāṇāyāma and Pratyâhâra whereby the mind is brought under control and the senses are emancipated from the thraldom of objects of desire.
Antarâtmā	The Supreme Soul residing in the heart of man.
Antarātmā Sādhanā	The innermost quest of the soul by means of Dhāranā (concentration), Dhyāna (meditation) and Samâdhi.
Anumāna	An inference.
Apāna	One of the vital airs which move in the sphere of the lower abdomen and control the function of elimination of urine and faeces.
Aparigraha	Freedom from hoarding or collecting.
Apuṇya	Vice or demerit.
Ardha	Half.
Arjuna	A Pāṇḍava prince, the mighty bowman and hero of the epic Mahābhârata.
Āsana	Posture. The third stage of yoga.
Asmitā	Egotism.
Aṣṭa	Eight.
Aṣṭāṅga Yoga	The eight limbs of Yoga described by Patañjāli.
Asteya	Non-stealing.
Ātmā or *Ātman*	The Supreme Soul or Brahman.
Ātma Ṣaṭkam	A group of six verses written by Śankarāchārya describing the soul in the state of Samadhi.
Ātmīyatā	The feeling of oneness, as a mother's feeling for her children.
Auṁ	Like the Latin word 'Omne', the Sanskrit word 'Auṁ' means 'all' and conveys concepts of 'Omniscience', 'Omnipresence' and 'Omnipotence'.
Avasthā	State or condition of the mind.
Avatāra	Descent, advent or incarnation of God. There are ten avatāras of Viṣṇu: Matsya (the Fish); Kūrma (the Tortoise); Varāha (the Boar), Narasiṁha (the Man-lion); Vāmana (the Dwarf); Paraśurāma; Rāma (hero of the epic Rāmāyaṇa); Krishna (hero of the epic Mahâbhârata who related the Bhagavad Gīta); Balarāma and Kalki.
Avidyā	Ignorance.
Avirati	Sensuality.
Āyāma	Length, expansion, extension. It also conveys the idea of restraint, control and stopping.

Baddha	Bound, caught, restrained, firm.
Bahiraṅga Sādhanā	The outward quest of the soul for its Maker. The first three stages of Yoga, namely, Yama, Niyama and Āsana, are the outward quest and keep the seeker in harmony with his fellow men and nature.
Bāhya Kumbhaka	Suspension of breath after full exhalation when the lungs are completely empty.
Bandha	Bondage or fetter. It means a posture where certain organs or parts of the body are contracted and controlled.
Bhagavad Gītā	The Song Divine, the sacred dialogues between Krishna and Arjuna. It is one of the source books of Hindu philosophy, containing the essence of the Upanishads.
Bhagavān	Lord; venerable, holy.
Bhakti	Worship, adoration.
Bhakti-mārga	The way or path to realization through adoration of a personal god.
Bharadvāja	A sage.
Bhaya	Fear.
Bhedana	Piercing, breaking through, passing through.
Bhoga	Enjoyment; an object of pleasure.
Bhoktṛ	One who enjoys or experiences.
Bhrānti-darśana	Erroneous (bhrānti) vision or knowledge (darśana), delusion.
Bhu	Land.
Bhūdāna	The donation of land.
Bhuja	The arm or the shoulder.
Bhujaṅga	A serpent, a snake.
Bhūmikatva	Firm ground.
Bīja	Seed or germ.
Bīja-mantra	A mystical syllable with a sacred prayer repeated mentally during prāṇāyāma, and the seed thus planted in the mind germinates into one-pointedness.
Brahmā	The Supreme Being, the Creator. The first deity of the Hindu Trinity entrusted with the work of creation of the world.
Brahma-vidyā	The knowledge of the Supreme Spirit.
Brahmachāri	A religious student vowed to celibacy and abstinence. One who is constantly moving (chārin) in Brahman (the Supreme Spirit); one who sees divinity in all.
Brahmacharya	A life of celibacy, religious study and self-restraint.
Brahman	The Supreme Being, the cause of the universe, the all-pervading spirit of the universe.
Brahmāṇḍa-prāna	The cosmic breath.
Buddhi	Intellect, reason, discrimination, judgement.

Chandra	The moon
Chatur	The number four.
Chitta	The mind in its total or collective sense, being composed of three categories: (a) Mind, having the faculty of attention, selection and rejection; (b) Reason, the decisive state which determines the distinction between things and (c) Ego, the I-maker.
Chitta-vikṣepa	Distraction, confusion, perplexity.
Chitta-vṛtti	Fluctuations of the mind. A course of behaviour, mode of being, condition or mental state.
Dadhīcha	A celebrated sage, who donated his bones to the gods. From these bones was fashioned the thunderbolt, with which Indra, the king of the gods, slew the demon Vṛtra.
Dakṣa	A celebrated prajāpati, a lord of created beings.
Dakṣiṇa	The right side.
Damanī	A layer with a nāḍī or channel for the passage of energy.
Dānava	A demon.
Daṇḍa	A staff.
Daurmanasya	Despair, dejection.
Deva	A god.
Devadatta	One of the vital airs which provides for the intake of extra oxygen in a tired body by causing a yawn.
Dhanu	A bow.
Dhāraṇā	Concentration or complete attention. The sixth stage of Yoga mentioned by Patañjali.
Dhasaṅjaya	One of the vital airs which remains in the body even after death, and sometimes bloats up a corpse.
Dhṛ	To hold, to support, to maintain.
Dhyāna	Meditation. The seventh stage of Yoga mentioned by Patañjali.
Droṇa	The preceptor of the Pāṇḍava and Kaurava princes in the arts of war, especially archery. He was the son of the sage Bharadvāja.
Duḥkha	Pain, sorrow, grief.
Dveṣa	Hate, dislike, repugnance.
Dwi-hasta	Two hands.
Eka	One, single, alone, only.
Eka-tattvābhyāsa	The study of the single element, the Supreme Spirit that pervades the innermost self of all beings.
Ekāgra	(Ek = one; agra = foremost.) Fixed on one object or point only; closely attentive, where the mental faculties are all focused on a single object.
Ekāgratā	One-pointedness.

Gaṇa	A troop of demigods, who were Śiva's attendants.
Gaṅgā	The river Ganges, the most sacred river in India.
Gheraṇḍa	A sage, the author of Gheraṇḍa-Saṁhitā, a classical work on Haṭha-yoga.
Gheraṇḍa-Saṁhitā	*See* above.
Gu	First syllable in the word 'Guru', meaning darkness.
Gulma	The spleen.
Guṇa	A quality, an ingredient or constituent of nature.
Guṇātīta	One who is freed from and gone beyond or crossed the three guṇas of Sattva, Rajas and Tamas.
Guru	Spiritual preceptor, one who illumines the darkness of spiritual doubt.
Ha	First syllable of the word 'Haṭha', which is composed of the syllables 'ha' meaning the sun, and 'ṭha' meaning the moon. The object of Haṭha-yoga is to balance the flow of solar and lunar energy in the human system.
Hala	A plough.
'Haṁsaḥ'	'I am He, the Universal Spirit', the unconscious repetitive prayer that goes on with each exhalation within every living creature throughout life.
Hanumān	A powerful monkey chief of extraordinary strength and prowess, whose exploits are celebrated in the epic Rāmāyana. He was the son of Añjana and Vāyu, the god of wind.
Hasta	The hand.
Haṭha	Force. The word 'hatha' is used adverbially in the sense of 'forcibly' or 'against one's will'. Haṭha-yoga is so called because it prescribes rigorous discipline, in order to find union with the Supreme.
Haṭha-vidyā	The science of Haṭha-yoga.
Haṭha-yoga	The way towards realization through rigorous discipline.
Hatha-yoga-pradīpikā	A celebrated textbook on Haṭha-yoga written by Svātmārāma.
Himālaya	The abode of ice and snow. Name of the mountain ranges on the northern borders of India.
Hiṁsā	Violence, killing.
Iḍā	A nāḍī, a channel of energy starting from the left nostril, then moving to the crown of the head and thence descending to the base of the spine. In its course it conveys lunar energy and so is called chandra nāḍī (channel of the lunar energy).
Indra	Chief of the gods. The god of thunder, lightning and rain.

Indriya	An organ of sense.
Indriya-jaya	Conquest, restraint or mastery of the senses by controlling desires.
Īśvara	The Supreme Being, God.
Īśvara-praṇidhāna	Dedication to the Lord of one's actions and one's will.
Jāgrata-avasthā	The complete awareness of the state of the mind.
Jālandhara-bandha	Jālandhara is a posture where the neck and throat are contracted and the chin is rested in the notch between the collar-bones at the top of the breast-bone.
Jamunā	A tributary of the Ganges.
Jānu	The knee.
Japa	A repetitive prayer.
Jatara-parivartana	An āsana, in which the abdomen is made to move to and fro.
Jaṭhara	The abdomen, stomach.
Jaya	Conquest, victory. It also means control, mastery.
Jīva	A living being, a creature.
Jīvana	Life.
Jīvana-mukta	A person who is emancipated during his lifetime by true knowledge of the Supreme Spirit.
Jīvana-mukti	The emancipated state.
Jīvātmā	The individual or personal soul.
Jñāna	Sacred knowledge derived from meditation on the higher truths of religion and philosophy, which teaches a man how to understand his own nature.
Jñāna-mārga	The path of knowlege by which man finds realization.
Jñāna-mudrā	The gesture of the hand where the tip of the index finger is brought in contact with the tip of the thumb, while the remaining three fingers are kept extended. The gesture is a symbol of knowledge (jñāna). The index finger is the symbol of the individual soul, the thumb signifies the Supreme Universal Soul, and the union of these two symbolizes true knowledge.
Jñānendriya	Hearing, touch, sight, taste and smell.
Kailāsa	A mountain peak in the Himālayas, considered as the abode of Śiva.
Kaivalya	Final emancipation.
Kaivalya-pāda	The fourth and last part of Patañjāli's Yoga Sūtra, dealing with Absolution.
Kālidāsa	The most renowned dramatist and poet in Sanskrit literature, whose work 'Śakuṅtalā' is universally respected.
Kapila	A sage, the founder of the Sāankhya system, one of the six orthodox systems of Hindu philosophy.
Karma	Action.

Karma-mārga	The way of an active man towards realization through action.
Karma-yoga	The achievement of union with the Supreme Universal Soul through action.
Karmendriya	Organs of excretion, generation, hands, feet and speech.
Karṇa	The ear, also one of the heroes in the Mahābhārata.
Karṇa-pīdā	Pressure around the ear.
Karuṇā	Compassion, pity, tenderness. It also implies devoted action to alleviate the suffering of the afflicted ones.
Kaṭhopaniṣad	One of the principal Upanishads in verse and in the form of a dialogue between the seeker Nachiketā and Yama, the god of Death.
Kauravas	Descendants of Kuru, who fought the fratricidal Mahābhārata war with their cousins the Pāṇḍavas.
Kāyā	The body.
Kāyika	Relating to the body.
Kevala	Whole, entire, absolute, perfect, pure.
Klésa	Pain, anguish, suffering.
Koṇa	An angle.
Krishṇa	The most celebrated hero in Hindu mythology. The eighth incarnation of Viṣṇu.
Kṛkara	Name of one of the subsidiary vital airs, whose function is to prevent substances going up the nasal passages and throat by bringing on sneezes and coughing.
Kṛta	Name of first of the four ages of the world of men.
Kṣatriya	A member of the warrior class.
Kṣipta	Distracted, neglected.
Kumbha	A water pot, a pitcher, a chalice.
Kumbhaka	Kumbhaka is the interval of time or retention of breath after full inhalation or after full exhalation.
Kuṇḍalinī	The Kuṇḍalinī (kuṇḍala = the coil of a rope; Kuṇḍalinī = a coiled female serpent) is the divine cosmic energy. This force or energy is symbolized as a coiled and sleeping serpent lying dormant in the lowest nerve centre at the base of the spinal column, the Mūlādhāra-chakra. This latent energy has to be aroused and made to ascend the main spinal channel, the Suṣumṇa piercing the chakras right up to the Sahasrāra, the thousand-petalled lotus in the head. Then the Yogi is in union with the Supreme Universal Soul.

Lac	100,000.
Laya	Dissolution; absorption of the mind, devotion.
Laya-yoga	The achievement of union with the Supreme Universal Soul through adoration or devotion.
Lobha	Greed.
Loma	Hair.

Madhyama	Middling, average, mediocre.
Mahā	Great, mighty, powerful, lofty, noble.
Mahābhārata	The celebrated epic composed by Vyāsa. It includes the Bhagavad Gītā.
Maharṣi	A great sage.
Maitri	Friendliness coupled with a feeling of oneness.
Man	To think.
Manas	The individual mind having the power and faculty of attention, selection and rejection. The ruler of the senses.
Mānasika	Of the mind, mental.
Manomanī	The state of samādhi.
Mantra	A sacred thought or a prayer.
Manu	Name of the father of the human race.
Mārga	A way, road, path.
Marīchi	Name of one of the sons of Brahmā. He was a sage and the father of Kaśyapa, q.v.
Matsya	A fish.
Matsyendra	One of the founders of Haṭha-yoga.
Moha	Delusion, infatuation.
Mokṣa	Liberation, final emancipation of the soul from recurring births.
Mṛdu	Soft, gentle, mild.
Mṛta	Dead, a corpse.
Mūdha	Perplexed, confounded, foolish, dull, stupid.
Muditā	Joy, delight.
Mudrā	A seal: a sealing posture.
Mukha	Face, mouth.
Mukta	Liberated.
Mukti	Release, liberation, final absolution of the soul from the chain of birth and death.
Muṇḍakopaniṣad	Name of a Upanishad dealing with the mystic syllable Auṁ.
Nachiketā	Name of the seeker and one of the principal characters in the Kaṭhopaniṣad. His father Vājaśravas wanted to give away all his possessions so as to acquire religious merit. Nachiketā felt puzzled and asked his father again and again: 'To whom will you give me?' His father said: 'I give you to Yama (the god of Death).' Nachiketā went down to the realm of Death and obtained three boons, the last of which was the knowledge of the secret of life after death. Yama tried to divert Nachiketā from obtaining his wish by offering the greatest earthly pleasures, but Nachiketā was not swayed from his purpose and ultimately Yama gave him the knowledge desired.
Nāda	Inner mystical sound.

Nāḍī	A tubular organ of the subtle body through which energy flows. It consists of three layers, one inside the other, like insulation of an electric wire. The innermost layer is called the 'sirā' and the middle layer 'damanī'. The entire organ as well as the outer layer is called 'nāḍī'.
Nāḍī-śodhana	The purification or cleansing of the nāḍīs.
Nāga	One of the subsidiary vital airs which relieves abdominal pressure, causing one to belch.
Nāva	A boat.
'Neti Neti'	'Not This! Not this!' The experience of samādhi is not like other experiences, which can be described in words. About it the sages say 'It is not this! It is not this!', for speech fails to convey the feeling of joy and peace experienced in that state.
Nirālamba	Without support.
Niranjana	Unstained; free from falsehood, pure.
Nirodha	Restraint, suppression.
Niruddha	Restrained, checked, controlled.
Niyama	Self-purification by discipline. The second stage of yoga mentioned by Patañjāli.

Pāda	The foot or leg; also part of a book.
Pādāṅguṣṭha	The big toe.
Padma	A lotus.
Pāṇḍava	Name of any of the five sons of Pāṇḍu, the heroes in the Mahābhārata.
Paramapāda	The highest step, the supreme state, final beatitude.
Paramātmā	The Supreme Spirit.
Parigraha	Hoarding.
Paripūrṇa	Entire, complete.
Parivartana	Turning round, revolving.
Parivṛtta	Turned around, revolved.
Parivṛttaika-pāda	With one leg turned around.
Pārśva	The side, flank; lateral.
Parśvaika-pāda	With one leg turned sideways.
Parvata	A mountain.
Pārvati	A goddess, consort of Śiva, daughter of Himālaya.
Paśchima	West; the back of the whole body from head to heels.
Paśchimottana	Intense stretch of the back side of the body from the nape to the heels.
Patañjali	The propounder of Yoga philosophy. He was the author of the Yoga Sūtras, the Mahābhāśya (a classical treatise on grammar) and a treatise on medicine.
Pīḍā	Pain, suffering, pressure.
Piṇḍa	The foetus or embryo, the body.
Piṇḍa-prāṇa	The individual breath, as contrasted with the cosmic or Universal breath.

Piṅgalā	A nāḍī or channel of energy, starting from the right nostril, then moving to the crown of the head and thence downwards to the base of the spine. As the solar energy flows through it it is also called the sūrya-nāḍī. Piṅgalā means tawny or reddish.
Plīhā	The spleen.
Prajñā	Intelligence, wisdom.
Prajñātmā	The intelligential self.
Prakṛti	Nature, the original source of the material world, consisting of three qualities, sattva, rajas and tamas.
Pramāda	Indifference, insensibility.
Pramāṇa	A standard or ideal; authority.
Prāṇa	Breath, respiration, life, vitality, wind, energy, strength. It also connotes the soul.
Prāṇa-vāyu	The vital air which pervades the entire human body. It moves in the region of the chest.
Praṇava	Another word for the sacred syllable Auṁ.
Prāṇāyāma	Rhythmic control of breath. The fourth stage of yoga.
Praṇidhāna	Dedication.
Prasārita	Spread out, stretched out.
Praśvāsa	Expiration.
Pratyāhāra	Withdrawal and emancipation of the mind from the domination of the senses and sensual objects. The fifth stage of yoga.
Pratyakṣa	Direct evidence.
Puṇya	Virtue, merit, righteous, just, good.
Puraka	Inhalation.
Pūrṇatā	Fullness, perfection.
Pūrva	East. The front of the body.
Pūrvottana	The intense stretch of the front side of the body.
Rāga	Love, passion, anger.
Rāja	A king, a ruler.
Rāja-mārga	The royal road to self-realization through the control of the mind.
Rāja-yoga	The achievement of union with the Supreme Universal Spirit, by becoming the ruler of one's own mind by defeating its enemies. The chief of these enemies are: Kāma (passion or lust), krodha (anger or wrath), lobha (greed), moha (delusion), mada (pride) and matsara (jealousy or envy). The eightfold yoga of Patañjāli shows the royal road (rāja-mārga) for achieving this objective.
Rāja-yogī	One who has complete mastery over his mind and self. One who has conquered himself.
Rajas	Mobility or activity; one of the three qualities or constituents of everything in nature.
Rajo-guṇa	The quaity of mobility or activity.

Rechaka	Exhalation, emptying of the lungs.
Ṛṣi	An inspired sage.
Ṙu	The second syllable in the word 'guru', meaning light.
Sādhaka	A seeker, an aspirant.
Sādhanā	Practice, quest.
Sādhana-pāda	The second part of Patañjāli's Yoga Sūtras, dealing with the means.
Sahajāvasthā	The natural state of the soul in samādhi.
Śalabha	A locust.
Sālamba	With support.
Sama	Same, equal, even, upright.
Sama-sthiti	Standing still and straight.
Samādhi	A state in which the aspirant is one with the object of his meditation, the Supreme Spirit pervading the universe, where there is a feeling of unutterable joy and peace.
Samādhi-pāda	The first part of Patañjali's Yoga Sūtras, dealing with the state of samādhi.
Samāna	One of the vital airs, whose function is to aid digestion.
Saṁśaya	Doubt.
Saṁskāra	Mental impression of the past.
Śankarāchārya	A celebrated teacher of the doctrine of Advaita.
Ṣaṇmukhī-mudrā	A sealing posture where the apertures in the head are closed and the mind is directed inwards to train it for meditation.
Santoṣa	Contentment.
Saraswatī	A tributary of the Ganges. Also the name of the goddess of speech and learning, the consort of Brahmā.
Sarva	All, whole.
Sarvāñga	The whole body.
Satī	The daughter of Dakṣa Prajāpati. She immolated herself for the insult offered to her husband Śiva by her father, and was then reborn as the daughter of Himālaya and again won Siva as her husband. She was the mother of Kārtikeya (the god of war) and of Ganapati (the god of learning, wisdom and good luck).
Sattva	The illuminating, pure and good quality of everything in nature.
Sattva-guṇa	The quality of goodness and purity.
Śaucha	Purity, cleanliness.
Śava	A corpse, a dead body.
Setu	A bridge.
Setu-bandha	The construction of a bridge. Name of an āsana in which the body is arched.
Siddha	A sage, seer or prophet; also a semi-divine being of great purity and holiness.

Sirā	A tubular organ in the body. *See* nāḍī.
Śirṣa	The head.
Śiṣya	A pupil, a disciple.
Śiva	Name of the third god of the Hindu Trinity, who is entrusted with the task of destruction.
Śiva-saṁhitā	A classical textbook on Haṭha-yoga.
Smṛti	Memory, a code of law.
Śodhana	Purification, cleansing.
'Soham'	'He am I'; the unconscious repetitive prayer that goes on with every inhalation within every living creature throughout life.
Śoka	Anguish, distress, grief, sorrow.
Śraddhā	Faith, trust.
Steya	Theft, robbery.
Sthita-prajñā	One whose wisdom is firmly established and does not waver; one who is unmoved by the dualities of pleasure and pain, gain and loss, joy and sorrow, victory and defeat.
Sthiti	Stability.
Styāna	Languor, sloth.
Sukha	Happiness, delight, joy, pleasure, comfort.
Sumanasya	Benevolence.
Śunyāśūnya	The mind is in a state of void (Śūnya) and yet a state that is not void (aśūnya).
Supta	Sleeping.
Sūrya	The sun.
Sūrya-bhedana	Piercing or passing through (bhedana) the sun. Here the inhalation is done through the right nostril, from where the Piṅgalā-nāḍī or Sūrya-nāḍī starts. Exhalation is done through the left nostril, from where the Iḍā-nāḍī or Chandra-nāḍī starts.
Sūrya-nāḍī	The nāḍī of the sun. Another name for Piṅgalā-nāḍī.
Suṣumṇā	The main channel situated inside the spinal column.
Suṣupti-avasthā	The state of the mind in dreamless sleep.
Sva	One's own, innate, vital force, soul, self.
Svādhyāya	Education of the self by study of divine literature.
Śvāna	A dog.
Svapnāvasthā	The state of the mind in a dream.
Śvāsa	Inspiration.
Śvāsa-praśvāsa	Heaving and sighing.
Svātmārāma	The author of the Haṭha-yoga-pradīpikā, a classical textbook on Haṭha-yoga.
Tāḍa	A mountain.
Tamas	Darkness or ignorance, one of the three qualities or constituents of everything in nature.
Tamo-guṇa	The quality of darkness or ignorance.
Tan or *Tān*	To stretch, extend, lengthen out.

Tap	To burn, to blaze, to shine, to suffer pain, to be consumed by heat.
Tapas	A burning effort which involves purification, self-discipline and austerity.
'Tat twam asi'	'Thou that art.' The realization of the real nature of man as being part of the divine, and of the divinity within himself, which liberates the human spirit from the confines of his body, mind, intellect and ego.
Tattva	The true or first principle, an element or primary substance. The real nature of the human soul or the material world and the Supreme Universal Spirit pervading the universe.
Tattva-jñāna	The knowledge of the true principle.
Tejas	Lustre, brilliance, majesty.
Ṭha	The second syllable of the word 'haṭha'. The first syllable 'ha' stands for the sun, while the second syllable 'ṭha' stands for the moon. The union of these two is Haṭha-yoga.
Tirieng	Horizontal, oblique, transverse, reverse and upside down.
Tri	Three.
Triaṅga	Three limbs.
Trikoṇa	A triangle.
Tṛṣṇā	Thirst, longing, desire.
Turīyāvasthā	The fourth state of the soul, combining yet transcending the other three states of waking, dreaming and sleeping state – the state of samādhi.

Ubhaya	Both.
Udāna	One of the vital airs which pervades the human body, filling it with vital energy. It dwells in the thoracic cavity and controls the intake of air and food.
Ugra	Formidable, powerful, noble.
Ujjāyi	A type of prāṇāyāma in which the lungs are fully expanded and the chest is puffed out.
Unmanī	The state of samādhi.
Upaniṣad	The word is derived from the prefixes 'upa' (near) and 'ni' (down), added to the root 'sad' (to sit). It means sitting down near a Guru to receive spiritual instruction. The Upanishads are the philosophical portion of the Vedas, the most ancient sacred literature of the Hindus, dealing with the nature of man and the universe and the union of the individual soul or self with the Universal Soul.
Upaviṣṭha	Seated.
Upekṣā	Disregard. Upekṣā is not only a feeling of disdain for a person who has fallen into vice or a feeling of

	indifference or superiority towards him. It is also a self-examination to find out how one would have behaved in like circumstances and also how far he is responsible for the state of the fallen one and to help him on to the right path.
Ūrdhva	Raised, elevated, tending upwards.
Ūrdhva-mukha	Face upwards.
Uṣṭra	A camel.
Ut	A particle, denoting intensity.
Uttāna	An intense stretch.
Utthita	Raised up, extended, stretched.
Vāchā	Speech.
Vāchika	Relating to speech, oral.
Vairāgya	Absence of worldly desires.
Vajra	A thunderbolt, the weapon of Indra.
Valli	A chapter of the Upanishads.
Vāma	The left side.
Vāsanā	A celebrated sage, author of several Vedic hymns.
Vāyu	The wind, the vital airs.
Veda	The sacred scriptures of the Hindus, revealed by the Supreme Being.
Vibhūti	Might, power, greatness.
Vibhūti-pāda	The third part of the Yoga Sūtras of Patañjāli, dealing with the powers that the yogi comes across in his quest.
Vidyā	Knowledge, learning, lore, science.
Vikalpa	Fancy, resting merely on verbal expression, without any factual basis.
Vikṣepa	Distraction, confusion, perplexity.
Vikṣipta	Agitated state of the mind.
Viloma	Against the hair, against the order of things. The particle 'vi' denotes negation or privation.
Viparyaya	A mistaken view, which is later observed to be such, after study.
Vīra	A hero, brave.
Vīrabhadra	A powerful hero created out of Śiva's matted hair.
Virochana	A demon prince, who was the son of Prahlāda and the father of Bali.
Vīrya	Vigour, strength, virility, enthusiasm.
Viṣama-vṛtti	Uneven or vehement movement while breathing.
Viṣṇu	The second deity of the Hindu trinity, entrusted with the preservation of the world.
Viśvāmitra	A celebrated sage.
Vitasti	A span.
Vṛkṣa	A tree.
Vṛt	To turn, to revolve, to roll on.

Vṛtti	A course of action, behaviour, mode of being, condition or mental state.
Vyādhi	Sickness, disease, illness.
Vyāna	One of the vital airs, which pervades the entire body and circulates the energy derived from food and breathing all over the body.
Yama	The god of death. Yama is also the first of the eight limbs or means of attaining yoga. Yamas are universal moral commandments or ethical disciplines transcending creeds, countries, age and time. The five mentioned by Patañjali are: non-violence, truth, non-stealing, continence and non-coveting.
Yoga	Union, communion. The word 'yoga' is derived from the root 'yuj' meaning to join, to yoke, to concentrate one's attention on. It is the union of our will to the will of God, a poise of the soul which enables one to look evenly at life in all its aspects. The chief aim of yoga is to teach the means by which the human soul may be completely united with the Supreme Spirit pervading the universe and thus secure absolution.
Yoga-mudrā	A posture.
Yoga Sūtra	The classical work on yoga by Patañjali. It consists of 185 terse aphorisms on yoga and it is divided into four parts dealing respectively with samādhi, the means by which yoga is attained, the powers the seeker comes across in his quest and the state of absolution.
Yogi or *Yogin*	One who follows the path of yoga.
Yoni-mudrā	Yoni means the womb or source and mudrā a seal. Yoni-mudrā is a sealing posture where the apertures of the head are closed and the aspirant's senses are directed within to enable him to find out the source of his being.
Yuga	An age.
Yuj	To join, to yoke, to use, to concentrate one's attention on.
Yukta	One who has attained communion with the Supreme Spirit pervading the universe.

International Addresses

Main Associations and Centres Worldwide

AUSTRALIA

BKS Iyengar Association of Australasia
1 Rickman Avenue
Mosman 2088
NSW

Bondi Junction School of Yoga
First Floor
2A Waverley Street
Bondi Junction
Sydney 2022
NSW

CANADA

BKS Iyengar Yoga Association
27–F Meadowlark Village
Edmonton
Alberta
T5R 5X4

Centre de Yoga Iyengar de Montreal
919 Mont-Royal Oest
Montreal
PQ H2J 1X3

BKS Iyengar Yoga Association
PO 65694, Station F
Vancouver, BC
V5N 5K7

Victoria Yoga Centre
3918 Olympic View Drive
RR4, Victoria, BC
V9B 5T8

BKS Iyengar Yoga Association of Ontario
c/o 85 Glenforest Road
Toronto, Ontario
M4N 2A1

FRANCE

Centre de Yoga Iyengar de Paris
also Association Francaise de Yoga Iyengar
35 ave Victor Hugo
75116 Paris

Centre de Yoga Iyengar de Lyon
Clos de Fourviere
40 Rue Roger Rodisson
69005 Lyon

Centre de Yoga Iyengar de Montpellier
5 bis Enclos Tissie Sarrus
34000 Montpellier

For classes in Marseille, Strasbourg, Toulouse, Nice, Tours, Grenoble, Nantes and Rouen, contact the Centre de Yoga Iyengar de Paris.

INDIA

R.I.M. Yoga Institute
1107 B/1 Shivajinagar
Pune 411 016

ITALY

Associazione Light on Yoga Italia
Via delle Route 49
50129 Firenze

JAPAN

Japanese Iyengar Yoga Association
Sembon Minami 557
Nishinari-Ku
Osaka Shi, Osaka Fu
Japan T557

HOLLAND

Iyengar Yoga Centre of Amsterdam
also Iyengar Yoga Association of Holland
8 Karthuizersdwars St
1015 KP Amsterdam

NEW ZEALAND

Information available from BKS Iyengar Association of Australasia (*see* Australia)

RUSSIA

Iyengar Yoga Centre of Moscow
c/o 16–49 Leninsky Prospect
Moscow 117 071

SOUTH AFRICA

BKS Iyengar Institute
58 Trelawney Road
Pietermaritzburg
Natal 3201

Iyengar Yoga Association of South Africa
PO Box 78648
Sandton 2146

SPAIN

EYI—Centro de Yoga Iyengar de Madrid
Carrera de San Jeronimo 16
5 28014
Madrid

Scola de Yoga
C—Hortes 2
17600 Figueres

UK

Manchester & District Institute of
Iyengar Yoga
134 King Street
Dukinfield
Tameside
Greater Manchester

Edinburgh Iyengar Yoga Centre
195 Bruntsfield Place
Edinburgh EH10 4DQ

Contact the above for information about other local Institutes:

Birmingham Iyengar Yoga Institute
Bradford & District Institute of Iyengar Yoga
Bristol Iyengar Yoga Institute
Cambridge Iyengar Yoga Institute
Hampshire Iyengar Yoga Association
Light on Yoga Association
Liverpool & District Institute of Iyengar Yoga
North East Institute of Iyengar Yoga
Nottingham Iyengar Yoga Institute
Oxford Region Iyengar Yoga Group
South West Iyengar Yoga Institute
Sussex Iyengar Yoga Institute

USA

BKS Iyengar Yoga Institute of Los Angeles
also BKS Iyengar Yoga National Association of the United States, Incorporated
and Iyengar Yoga Association of Southern California
8223 W. Third Street
Los Angeles
CA 90038

Iyengar Yoga Institute of San Francisco
also Iyengar Yoga Association of Northern California
2404–27th Avenue
San Francisco
CA 94116

Ann Arbor 'Y' Iyengar Yoga
350 S 5th Avenue
Ann Arbor
MI 48014

Iyengar Yoga Institute of New York
also BKS Iyengar Yoga Association of Greater New York
27 W 24th Street
Suite 800
New York
NY 10011

Iyengar Yoga Association of Massachusetts, Inc.
240–A Elm Street
Somerville
MA 02114

Iyengar Yoga Association of Minnesota
Box 10381
Minneapolis
MN 55458–3381

Iyengar Yoga Assocaiation of Wisconsin
Route 2
Box 70E
La Crosse
WI 54601

Iyengar Yoga Association of the Midwest Bioregions
310 Gralake
Ann Arbor
MI 48103

Iyengar Yoga Association of Northern Michigan
2319 W. Midland Road
Auburn
MI 48611



THE 100 DEADLIEST KARATE MOVES





The Master Teacher The
Imperial Grand Potentate, Noble: Rev. Dr. Malachi Z. York 33°/720°.
Defines Success"

QUESTION: What is Success?

ANSWER: Success is the progressive realization of a worthy idea. If you have a goal and you are working towards that goal, then you're on the path to success.

"A 30 Day Program "

All One Has to Do Is Apply The Method To Their Life And Your Life Will Never Be The Same Again!

~~~~~~``

SAY This for 30 days straight

I plant positive thoughts in my mind

I am practicing this for 30 days straight.

I am doing a 30 day practical method.

I am applying this method for 30 days straight.

This is going to be easy.

This will alter my life for the better and for ever.

I think and I relax.

I am writing down my want list on a card.

I am imagining and concentrating on my want list for 30 days straight and 3 times a day.

I am looking at this want list for 30 days straight and 3 times a day.

SAY This for 30 days straight

I want (state wish or want)____?

This is my reality the moment I think about it

____
~~~~~~

I create positive habits.

I always think positive.

I take control of my mind.

My mind will only think of what I allow it to think.

I Do more.

I think more.
I give myself more then I ever did before.

I don't worry about how I am going to achieve my goals.

All The answers will come to me.

I think of all the reasons I can be successful.

I write out the persons that I love to become

I am like ____
I can not live no other way after this right knowledge.

I my whole life to live in a superior way.

I am super-strong mentally.

I am a super-strong physical .

I am super-strong 9 Ethereally

I am cured of all mental diseases, namely ignorance.

I am a Supreme Being of the pure radiant Green Light.

I change my mental environment and I change my life.

I am a superior thinker.

I am bred to be superior in mind.

I am programmed by my superior mental environment

I am educated In a Superior mental environment.

Named Nuwaubu/Wu-Nuwaubu

I am physically and spiritually free.

I am a supreme being.

I am goal-minded.

I achieve anything I want to achieve in my life.

I am financially independent.

I know how to use my superior knowledge to become super-successful.

I get everything I want in my life.

I have the super-magic touch.

Anything I touch turns Into success.

I continue to become more & more successful in my life.

I always think big and successful.

I am a super-successful supreme being.

I am progressive In the realization of my worthy ideas.

I do everything in any field I choose to.
I am successful in anything I choose to do, because that's what I want to do.

I propagate the 'Message of the Most High'.

I set goals.

I am going to ....(state action)____.

I am going to ....(state action)____.

I am going to ....(state action) _______________________________________

(set date for deadline).

____

I will succeed.

I will reach all of the goals that I set for myself.

I set out to achieve all of them.

I want to become a "Supreme Being "

I am a "Supreme Being "

Success is anybody that's doing a pre-determined job.

I will (state action)____.

I am (Determine)____.

I posses a burning desire to be what I think about all the time.

I create all my opportunities in my life.

I know where I am going.
I have complete plans.
I know my directions.
I know my destination.
I know where I am going all the time.
I have the superior guidance.

I am a superior sales man.
I have no limits in ALL

I always achieve.
I sell anything, because I want to.
I sell everything.
I believe in what I am selling.

I don't hurt anybody.

I don't displease anybody.

I make everything I do marketable to all.

I am superior competitor.
I am a super-winner.
I super-succeed in my life.
I really overstand this principle completely.

My life is altered for super-success

The Bes things are always attracted to me.

Everything I want, I get.

From now on, I won't have any problems.

I won't have any worries.

I don't have any doubt, nor any fears in my life.

~~~~~~
"THIS IS THE KEY!!"
SAY This for 30 days straight

I am what I think about all the time.

(say what you want to think about All the time)

<<<here>>>

____ ________

Everything will come if I only be patient and wait for it.

I am completing my purpose.

I alter my life for The Bes.

I alter my attitude to a superior state of mind.

I am a superior mind.

I care enough for super results.

I will achieve it.

I achieve all

I am super-rich.
I am super wealthy
I am super-healthy.
I am super-intelligent.
I am super- knowledgeable on all subjects on earth and the whole boundless universe.
~~~~~~

Anything I think in my mind, I am it.
Anything I feel in my heart I am it.

My life is what my thoughts make it.

I posses positive, crystal clear and vivid pictures in my mind of what I want to do.

I posses positive, crystal clear and vivid pictures in my mind of what I want to become

I know my goals and purposes In my life.

I have set a target before me.

I am prepared.

I practice.

I am talented.

I am skillful.

I have the complete idea.

I achieve all of my goals when I think about them.

I am helping to save positive agreeable Nubian people

who don't believe in themselves.

Possible Nine-mind revision:
(I am helping to save positive agreeable Nubian people who don't KNOW themselves.)

I totally believe in myself.

Possible Nine-mind revision:
(I totally trust in my abilities within myself.)

I will instill this superior mind-concept in all of my children.

I am the greatest of the great.

My children are the greatest of the great.

I am a chosen child of Anu.

I have the superior-faith

I have super-determination.

I will succeed.

I succeed

I know all things are possible to me.

I think in only positive terms.
I get only positive things sent to me.

I believe and I succeed.

Possible Nine-mind revision:
(I am conscious of my ability to achieve success)

I know and I succeed.

I have no doubt in myself.

I attempt all things I want & wish for.

I make everything happen for me in my life

I become what I think about.

I think about positive, concrete, worth-while goals and ideas.

I will always become what I think about.

I think about all the positive things I want to become in my life.

I become what I think about.

Anything I plant in my mind I become it.

I plant super-success in my mind and everything I want and wish for in my life becomes reality.

I concrete on only worth-while goals.

I always value my mind, my body, my soul and my spirit.
I don't take my mind, my body, my soul and my spirit for granted.

I plan my goals in my mind.
I am making the most important decision in my life.

I plan all my goals in my mind and I achieve them.

I picture myself as a Supreme Being.

I see myself as having already achieving all goals in my life.
I am outstanding in everybody's eyes.
I am a great, supreme being.

I find everything I need in my life to help all others.
I am super-rich in personality, fame and respect.

I plant any thought In my mind and I easily achieve it.

I care and work towards achieving my goals in life and everything
I plant in my mind becomes a reality.
That is Universal law.

This always works, because this is Universal law.
I am where I want to be.

I am guided by my Inner Being

I think, I think and I think

I am learnt in this superior science.

I overstand this Supreme science.

I know this supreme science works with the forces of nature

put your want and wish in the lines

I am ________________________.

I believe in____________________________.

Possible Nine-mind revision:
(I focus on) ____________________________.

I have faith in______________________________.

Possible Nine-mind revision:
(I strive towards) ______________________________.

I am in control of____________________________.

I do the job that I love doing.

I only do super-great things in my life

I am A Supreme Being of the pure radiant GREEN LIGHT